


z/VM and Linux on IBM System z: The Virtualization Cookbook for RHEL 5

**A cookbook for installing and customizing z/VM 5.2
and Linux RHEL 5 on the mainframe**



**Michael MacIsaac, Brad Hinson
February 2007**

Contents

Preface	ix
Summary of changes to August 2006 version	ix
Summary of changes to February 2007 version	ix
Conventions	x
The team that wrote this trilogy	xi
Comments welcome	xi
 Notices	 xii
Trademarks	xiii
 Part 1. z/VM	 1
 Chapter 1. Introduction to z/VM and Linux	 3
1.1 What is virtualization?	4
1.2 A philosophy adopted in this book	4
1.3 Choices and decisions made in this book	4
1.4 IBM Director and z/VM Center Extension	5
1.5 Infrastructure design	5
1.6 Usability tests performed for this book	6
1.7 The chapters in this book	7
 Chapter 2. Planning	 9
2.1 Bill of materials	9
2.1.1 Hardware resources	9
2.1.2 Software resources	10
2.1.3 Networking resources	10
2.2 z/VM conventions	10
2.2.1 Volume labeling convention	11
2.2.2 Backup file naming convention	11
2.2.3 The command retrieve convention	12
2.3 Disk planning	12
2.4 Memory planning	13
2.5 Password planning	13
2.6 Planning worksheets	14
2.6.1 z/VM resources used in this book	14
2.6.2 z/VM DASD used in this book	15
2.6.3 Linux resources used in this book	15
2.6.4 Linux user IDs used in this book	16
2.7 Blank worksheets	17
2.7.1 z/VM resources worksheet	17
2.7.2 z/VM DASD worksheet	18
2.7.3 Linux resources worksheet	19
2.7.4 Linux user ID worksheet	19
 Chapter 3. Configuring a desktop machine	 21
3.1 PuTTY: A free SSH client for Windows	21
3.2 Setting up a VNC client	25
3.2.1 Downloading and running RealVNC	25
3.2.2 Customizing RealVNC	26

3.3 3270 emulators	27
Chapter 4. Installing and configuring z/VM.	29
4.1 Installing z/VM from DVD	29
4.1.1 Booting z/VM from DVD	30
4.1.2 Copying a vanilla z/VM system to DASD	32
4.1.3 IPL the vanilla z/VM from DASD	35
4.1.4 Completing the z/VM installation	37
4.2 Configuring TCP/IP	38
4.2.1 Use the IPWIZARD tool	39
4.3 Configuring the XEDIT profile	41
4.4 Customizing the SYSTEM CONFIG file	42
4.5 Configuring TCP/IP to start at IPL time	43
4.5.1 Renaming the TCPIP configuration file	45
4.5.2 Copy the PROFILE XEDIT file	45
4.5.3 Configuring the FTP server	45
4.5.4 Shutting down and relPLing the system	46
4.6 Adding paging volumes	47
4.6.1 Formatting the paging volumes	47
4.6.2 Formatting DASD for minidisks	49
4.6.3 Updating the SYSTEM CONFIG file	51
4.6.4 Testing the changes	52
4.7 Creating a user ID for common files	53
4.7.1 Define the user in the USER DIRECT file	53
4.7.2 Logging and customizing the new user ID	55
4.7.3 Copying a PROFILE XEDIT	55
4.7.4 Creating a PROFILE EXEC	56
4.7.5 Copying files associated with this book to LNXMAINT	56
4.8 Customizing system startup and shutdown	57
4.8.1 Configuring the AUTOLOG1 PROFILE EXEC	57
4.8.2 Testing the changes	58
4.9 Addressing z/VM security issues	59
4.9.1 Changing passwords in USER DIRECT	60
4.10 Backing up your z/VM system to tape	61
4.11 Relabeling the system volumes	61
4.11.1 Modifying labels in the SYSTEM CONFIG file	62
4.11.2 Modifying labels in the USER DIRECT file	64
4.11.3 Changing the labels on the five volumes	65
4.11.4 Shutting down your system and restarting it	66
4.12 Restoring your z/VM system from tape	67
Chapter 5. Servicing z/VM	69
5.1 Applying a PTF	70
5.1.1 Determining if a PTF has been applied	70
5.1.2 Getting service via Internet FTP	71
5.1.3 Downloading the service to z/VM	72
5.1.4 Receiving, applying, and building service	73
5.1.5 Putting the service into production	74
5.2 Applying a Recommended Service Upgrade or RSU	75
5.2.1 Getting service from the Internet	75
5.2.2 Downloading the service to z/VM	76
5.2.3 Receiving, applying, and building the service	77
5.2.4 Putting the service into production	79

5.3 Determining z/VM's service level	80
Part 2. RHEL 5	81
Chapter 6. Configuring an NFS server for RHEL 5	83
6.1 Installing Linux on the PC	83
6.2 Downloading files associated with this book	84
6.3 Setting up a RHEL 5 install tree	84
6.3.1 Copying from physical DVD	84
6.3.2 Verifying the ISO image	85
6.3.3 Copying the DVD contents	85
6.3.4 Building the repository directory	86
6.4 Enabling the NFS server	86
Chapter 7. Installing and configuring RHEL 5	89
7.1 Creating the user ID RHEL5	90
7.2 Adding RHEL5 to AUTOLOG1's PROFILE EXEC	92
7.3 Preparing RHEL5 bootstrap files	93
7.4 Installing the master image	95
7.4.1 Stage 1 of the RHEL 5 installation	97
7.4.2 Stage 2 of the RHEL 5 installation	99
7.4.3 Booting your new Linux system from disk	105
7.5 Configuring the master image	105
7.5.1 Configuring VDISK swap	106
7.5.2 Configuring automount of install tree	107
7.5.3 Configuring yum for online updates	107
7.5.4 Adding additional RPMs	108
7.5.5 Changing automount to point to controller	109
7.5.6 Turning off unneeded services	109
7.5.7 Configuring the VNC server	110
7.5.8 Configuring rsyncd	111
7.5.9 Creating the script nightly.sh	112
7.5.10 Setting the software clock accurately	112
7.5.11 Setting system to halt on SIGNAL SHUTDOWN	113
7.5.12 Modifying modprobe.conf	113
7.5.13 Rebooting the system	113
7.5.14 Verifying the changes	114
7.5.15 Red Hat bug 224257 workaround	115
7.6 Installing the controller	116
7.6.1 Verifying the installation	121
7.7 Configuring the controller	121
7.7.1 Copying files to the controller	122
7.7.2 Retire the PC NFS server	123
7.7.3 Configuring swap spaces	123
7.7.4 Configuring yum	123
7.7.5 Adding additional RPMs	123
7.7.6 Turning off unneeded services	124
7.7.7 Configuring the VNC server	125
7.7.8 Turning on the NFS server	125
7.7.9 Turning on the NTP server	125
7.7.10 Setting system to halt on SIGNAL SHUTDOWN	126
7.7.11 Configuring SSH keys	126
7.7.12 Inserting the vmcp module	127
7.7.13 Configuring Apache for DAZL	127

7.7.14	Rebooting the system	130
7.7.15	Verifying the changes	131
Chapter 8.	Configuring RHEL 5 for cloning	133
8.1	Defining a new user ID for a virtual server	133
8.1.1	Adding LINUX01 to AUTOLOG1's PROFILE EXEC	134
8.1.2	Creating a parameter file for the new LINUX ID	135
8.2	Cloning a virtual server manually	136
8.3	Cloning a virtual server automatically	140
8.4	Cloning five more virtual servers	142
8.4.1	Formatting and label six new DASD	143
8.4.2	Defining six more user IDs	144
8.4.3	Creating six new parameter files	145
8.4.4	Granting user IDs access to VSWITCH	146
8.4.5	Testing logging on to a new user ID	147
8.5	Reviewing system status	148
Chapter 9.	Installing Linux with kickstart	149
9.1	Configure the controller for kickstart	149
9.2	Configure the LINUX07 user for kickstart	152
9.3	Kickstart the LINUX07 user	152
Chapter 10.	Servicing Linux with Red Hat Network	155
10.1	Registering your system with RHN	155
10.2	Installing and updating packages using yum	156
10.3	Managing your Linux guest through RHN	157
10.4	Updating a system without Internet access	158
10.4.1	Configuring the server	158
10.4.2	Configuring the client	158
10.4.3	Updating packages on the server	159
Chapter 11.	Cloning open source virtual servers	161
11.1	Creating a virtual Web server	161
11.1.1	Installing Apache RPMs	161
11.1.2	Testing Apache	162
11.1.3	Turning on a firewall	163
11.1.4	Configuring SSL for Apache	164
11.1.5	Populating your Web site	165
11.1.6	Apache resources	165
11.2	Creating a virtual LDAP server	165
11.2.1	Cloning a Linux virtual server	166
11.2.2	Installing the openldap server	166
11.2.3	Configuring the OpenLDAP server	167
11.2.4	Migrating existing users to LDAP	168
11.2.5	Configuring an LDAP client	171
11.2.6	Adding new user accounts	172
11.3	Creating a virtual file and print server	173
11.3.1	Cloning a Linux virtual server	173
11.3.2	Installing necessary RPMs	174
11.3.3	Configuring Samba configuration file	175
11.3.4	Adding a Samba user	175
11.3.5	Starting Samba at boot time	176
11.3.6	Testing your changes	176
11.3.7	Configuring printing	177

11.4 Creating a virtual application development server	177
11.4.1 Additional resources	178
Chapter 12. Miscellaneous Recipes	181
12.1 Adding a logical volume	181
12.1.1 Adding minidisks to the z/VM directory entry	181
12.1.2 Making the new minidisks available	182
12.1.3 Formatting and partitioning the minidisks	182
12.1.4 Create the logical volume and file system.	184
12.1.5 Updating the file system table.	186
12.2 Extending an existing logical volume	187
12.3 Centralizing home directories for LDAP users	189
12.3.1 Configuring the NFS server.	189
12.3.2 Configuring the master image for LDAP and automount	190
12.4 Rescuing a Linux system	192
12.4.1 Entering single user mode	192
12.4.2 Entering a rescue environment.	192
Part 3. Common tasks	195
Chapter 13. Monitoring z/VM and Linux	197
13.1 Using INDICATE and other commands	197
13.1.1 Using the INDICATE command	198
13.1.2 Using other basic commands	200
13.2 The z/VM Performance Toolkit	201
13.2.1 Configuring the z/VM Performance Toolkit	201
13.2.2 Configuring Web Browser support	202
13.2.3 Configuring PERFSVM	203
13.2.4 Starting the z/VM Performance Toolkit	205
13.2.5 Using the z/VM Performance Toolkit.	205
13.3 Monitoring Linux	208
13.3.1 Monitoring Linux with rmfpm	208
13.3.2 Monitoring Linux performance data from the kernel	209
13.4 Registering Linux images with the Performance Toolkit	210
13.5 Monitoring z/VM and Linux via a Web application	211
13.5.1 Overall design	211
13.5.2 DAZL screen captures	212
13.5.3 DAZL design	220
Chapter 14. Backup and restore	223
14.1 Incremental backup of z/VM	224
14.1.1 The getVMinfo.sh script	224
14.1.2 The backupVM.sh script	225
14.2 Incremental backup of Linux virtual servers	227
14.2.1 Configuring rsync on the controller	227
14.2.2 Configuring sitar to run nightly on the virtual servers	228
14.3 Disaster recovery of z/VM and virtual Linux servers	228
Appendix A. References	229
A.1 Related books	229
A.2 Online resources	230
A.3 Important z/VM files	230
A.4 Cheat sheets	230
A.4.1 XEDIT cheat sheet	231

A.4.2 vi cheat sheet	231
Appendix B. Common source code.	233
B.1 z/VM REXX EXECs and XEDIT macros.	233
B.1.1 The CPFORMAT EXEC	233
B.1.2 The CHPW52 XEDIT macro.	237
B.1.3 The LABEL520 EXEC	240
B.1.4 The LABEL520 XEDIT macro.	242
B.2 Linux source code	243
B.2.1 Bash scripts on the controller	243
Appendix C. Source code specific to Linux	249
C.1 Obtaining and using the Web material	249
C.2 The clone.sh script	249
Index	259

Preface

“The search for truth is more precious than its possession.”

— Albert Einstein

This book describes how to *roll your own* Linux virtual servers on IBM System z hardware under z/VM. It adopts a cookbook format that provides a concise, repeatable set of procedures for installing and configuring z/VM in an LPAR and then installing and customizing Linux. You need an IBM System z logical partition (LPAR) with associated resources, z/VM 5.2 media, and a Linux distribution.

In February of 2007, two books were published, each book targeting a different distribution:

- ▶ *z/VM and Linux on IBM System z: The Virtualization Cookbook for SLES 10*
- ▶ *z/VM and Linux on IBM System z: The Virtualization Cookbook for RHEL 5*

In August of 2006 a book was published that addresses both 31-bit and 64-bit SLES 9:

- ▶ *z/VM and Linux on IBM System z: The Virtualization Cookbook 2*

In addition to these books, there are associated REXX EXECs and Linux scripts to help speed up the installation and configuration of both z/VM and Linux. These tools are not IBM products nor formally supported. However, they will be informally supported. They are available on the Web.

This book assumes that you have a general familiarity with System z technology and terminology. It does not assume an in-depth understanding of z/VM and Linux. It is written for those who want to get a quick start with z/VM and Linux on the mainframe.

Summary of changes to August 2006 version

The second release of the cookbook in August of 2006 was based on the IBM redbook *z/VM and Linux on IBM System z: The Virtualization Cookbook for SLES9*, SG24-6695-01. The content that was added to that book is as follows:

- ▶ **Manual cloning:** A new section in chapter 9, Cloning a virtual server manually was added so you can better understand the steps involved in the cloning process
- ▶ **Cloning of IBM Middleware:** A new chapter 11 *Cloning IBM Middleware* was added that describes installing, sharing, customizing and cloning IBM WebSphere Application Server, DB2 and MQ Series.
- ▶ The `c1one.sh` script has three new flags added: `--was`, `--db2` and `--mq` to support the cloning of IBM middleware.

Summary of changes to February 2007 version

The release of two new books in February of 2007 added the following:

- ▶ SLES 10 is described in the book *z/VM and Linux on IBM System z: The Virtualization Cookbook for SLES 10*.

- ▶ RHEL 5 is described in the book *z/VM and Linux on IBM System z: The Virtualization Cookbook for RHEL 5*.
- ▶ Two VDISK swap spaces are used rather than one VDISK and one minidisk - this allows for both more potential swap space and a larger root file system.
- ▶ Associated files for the controller are distributed as RPMs - one for SLES 10 and one for RHEL 5. This removes the need to recursively copy the content of the associated tar files.
- ▶ A section is added to the chapter “Miscellaneous recipes” entitled “Centralizing home directories for LDAP users”. This ties together a virtual LDAP server, authentication (PAM, NSS), LVM, NFS and automount so that cloned virtual servers share a common user/group/password LDAP database and a common /home/ directory that is automatically mounted.
- ▶ Another section is added to the chapter “Miscellaneous recipes” entitled “Rescuing a Linux system”. This is a quick reference on how to begin to repair a system that is no longer able to boot. Hopefully this section will not be referenced often (or at all :)).
- ▶ A Web Application named Data About z/VM and Linux (DAZL) is described in Chapter 13, “Monitoring z/VM and Linux” on page 197. This allows the controller to run a password protected Web Server that makes much z/VM and Linux data quickly available via a browser. It relies on the /backup/ file system being populated correctly via the `clone.sh` script, rsync, key-based authentication and cron.
- ▶ The `clone.sh` script was moved from /usr/local/sbin/ to /sbin/. The hard coded reference to the master image’s mount point has been removed. Rather, only the root file system minidisk (100) is cloned. That value was made into a variable to more easily allow for multiple master images to be cloned.
- ▶ Installing z/VM onto 3390-9s is addressed - a LBL520-9 EXEC and XEDIT macro are supplied to allow for the relabeling of the system volumes.

The release of two new books also removed some sections:

- ▶ The chapter on Cloning of IBM Middleware has been removed - at the time of publishing not all the middleware was not supported on the new distributions.
- ▶ DCSS/XIP2 - it does not seem that this environment is being widely used.

Conventions

The following font conventions are used in this book:

Monospace and bold	Commands entered by the user on the command line
<value>	Value inside angle brackets is to be replaced
monospace	File, directory and user ID names

The following command conventions are used in this book:

- ▶ z/VM commands are prefixed with ==>
- ▶ z/VM XEDIT subcommands are prefixed with =====>
- ▶ Linux commands running as root are prefixed with #
- ▶ Linux commands that will not fit on one line are suffixed with \
- ▶ Linux commands running as non-root are usually prefixed with \$

The team that wrote this trilogy

This book was originally written in 2005 by Michael MacIsaac, Jin Xiong and Curtis Gearhart. It was updated in 2006 by Michael MacIsaac, Carlos Ordonez and Jin Xiong. It was updated a third time in late 2006 and early 2007 by Marian Gasparovic taking the lead on the SLES 10 version and Brad Hinson of Red Hat working on the RHEL 5 version. The DCSS/XIP2 section was based on work by Carlos Ordonez, which was in turn based on work by Carsten Otte. Most of the section on the CP INDICATE command was written by Bill Bitner.

Sincere thanks goes out to the following people who contributed to this project in various ways:

Jerry Epker
Fidelity Information Services

Bill Bitner, Bruce Hayden, Denny Refsnider, Roger Lunsford, Jim Switzer and Romney White
IBM Endicott

Carsten Otte, Claudia Prawirakusumah
IBM Germany

Kim Betros, Duane Beyer, Michel Considine, Roy Costa, Greg Geiselhart, Dionne Graff, Susan Greenlee, Ernest Horn, Rong Lee, Bill Norton, Bruce Smilowitz, Kyle Smith, Paul Sutura, Helen Tsang, Donna Von Dehsen, Hossee Wakil and Dennis Wunder
IBM Poughkeepsie

Bernard Wu
NCCI

Mark Post
Novell

Matthew Eernisse
OpenSource Applications

David Boyes, Adam Thornton
Sine Nomine Associates

Chester Hood
State of Tennessee

Rob van der Heij
Velocity Software

Thanks the zBMC team in IBM Poughkeepsie and to the many who answered questions on the linux-390 list server.

Special thanks to Tony Giaccone from IBM Poughkeepsie for always finding another free LPAR and more DASD.

Comments welcome

Your comments are important. You can send your comments in e-mail directly to:

[mikemac at us.ibm.com](mailto:mikemac@us.ibm.com)
[marian.gasparovic at sk.ibm.com](mailto:marian.gasparovic@sk.ibm.com)
[bhinson at redhat.com](mailto:bhinson@redhat.com) // For the RHEL 5 book

Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing, IBM Corporation, North Castle Drive Armonk, NY 10504-1785 U.S.A.

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious, like anyone will ever read this, and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

Trademarks

The following terms are trademarks of the International Business Machines Corporation in the United States,

developerWorks®
eServer™
ibm.com®
iSeries™
z/OS®
z/VM®
System z®
AIX®
DirMaint™
Domino®
ECKD™
ETE™
HiperSockets™
Hummingbird®
IBM®
Lotus®
Notes®
Perform™
Requisite®
RACF®
RMF™
S/390®
SLC™
Tivoli®
Workplace™

The following terms are trademarks of other companies:

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

Intel, Intel Inside (logos), MMX, and Pentium are trademarks of Intel Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Other company, product, and service names may be trademarks or service marks of others.

Part 1

z/VM

This part of the book has an introduction chapter and then discusses z/VM installation, configuration, and servicing.

Introduction to z/VM and Linux

“Everything should be made as simple as possible, but not simpler.”

— Albert Einstein

Virtualization is hot. The mainframe and z/VM have been doing virtualization for decades. When Linux came to the mainframe in 2000, it was a natural fit to run under z/VM. You can run many tens of Linux images on the same System z logical partition (LPAR). Some customers are running hundreds.

With a z/VM and Linux infrastructure, you can reduce the time between deciding on new servers and implementing them because new servers can be deployed in a matter of minutes. This powerful capability can enable you to launch new products and services without planning, purchasing, installing and configuring new hardware and software. Development groups who need test environments built and rebuilt rapidly to efficiently handle change management can also benefit from this unique advantage.

Some of the mainframe's and z/VM's best strengths are:

- ▶ z/VM and the mainframe's virtualization capabilities are more mature and robust than any other hardware and virtualization combination.
- ▶ z/VM's virtual switch (VSWITCH) has made networking Linux much simpler.
- ▶ Full volume backup of systems allows for complete disaster recovery when another data center is available.
- ▶ z/VM is one of the easiest operating systems to customize. There is only a handful of configuration files. Once it is set up, z/VM will run for months with little maintenance and administration required.

z/VM 5.2, available in December of 2005, provides major improvements when operating on System z servers with large memory configurations. Scalability is improved with the Control Program (CP) now using memory above 2 GB for a much broader set of operations. Previously, guest pages had to be moved below 2GB for many reasons, for example in both standard I/O and Queued Direct I/O (QDIO). Now I/O can be done using buffers anywhere in real memory, and QDIO structures can reside above 2 GB, as can most CP control blocks. These improvements offer constraint relief for large-real-memory virtual server environments that are memory intensive.

Read more about System z virtualization capabilities on the Web at:

<http://www-1.ibm.com/servers/eserver/zseries/virtualization/features.html>

A lot of books and papers are talking about virtualization today, but not telling you how to do it. This book puts the *HOWTO* behind these marketing words.

1.1 What is virtualization?

Virtualization is the ability for a computer system to share resources so that one physical server can act as many *virtual servers*. z/VM allows the sharing of the mainframe's physical resources such as disk (DASD), memory (storage), network adapters (OSA cards) and CPU (CPs or IFLs). These resources are managed by a *hypervisor*. z/VM's hypervisor is called Control Program (CP). When the user logs onto z/VM, the hypervisor creates a virtual machine which can run one of many different operating systems. The two operating systems that are discussed in this book are the Conversational Monitoring System (CMS) and Linux. CMS can be thought of as a z/VM shell. Virtual machines running Linux become the *virtual servers*.

1.2 A philosophy adopted in this book

An important philosophy adopted in this book is to keep all solutions simple. Two common expressions used are “the KISS method” (Keep It Simple, Stupid) and the quote from Albert Einstein at the start of this chapter: *Everything should be made as simple as possible, but not simpler*. Because the former is somewhat condescending and because 2005 was both the first year this book was published and the centennial anniversary of Albert Einstein's many famous papers, this book will use the latter.

1.3 Choices and decisions made in this book

When deciding on installing, maintaining and provisioning (cloning) Linux virtual servers under z/VM, there are many basic choices to make. Here are some of the more important choices and assumptions made in writing this book:

- Cloning product versus “roll your own” cloning:

Cloning products, such as Aduva's Onstage, IBM Tivoli Provisioning Manager, IBM Director function ‘z/VM Center’ (briefly discussed in “IBM Director and z/VM Center Extension” on page 5) and Levanta, are outside the scope of this book. While these are all viable solutions, the cloning described in this book allows you to *roll your own* Linux images without requiring such products. However, these products are more sophisticated than the simple EXECs and scripts in this book.

- Directory Maintenance product versus the USER DIRECT file:

The USER DIRECT file is chosen over a directory maintenance product such as IBM *DirMaint* or Computer Associates' *VM:Direct*. If you feel that *DirMaint* as a directory maintenance product is better for your enterprise, you can use the book *Getting Started With Linux*, SC24-6096, to configure z/VM. You can still use this book to configure Linux.

- Provisioning versus predefined user IDs:

z/VM user IDs must be predefined to clone. There is no attempt to *provision* them (define and bring Linux user IDs online automatically) as part of the cloning process. The target Linux user ID must exist with the appropriate minidisks defined or the cloning script will fail.

- ▶ Shared read-only Linux `/usr/` file system versus read-write:
Many cloning solutions use an environment which shares the `/usr/` file system. This choice often makes the solution more complex, especially when adding software to the virtual servers. A read-write `/usr/` file system on the virtual servers is chosen to keep things as simple as possible.
- ▶ Conventional 3390 ECKD DASD versus FBA disks accessed via SCSI over FCP:
The System z server has traditionally only supported 3390 (or older 3380) DASD. Support has been extended to include SCSI/FBA disks in storage area networks (SANs). The support of FBA disks is slightly more complicated than conventional DASD. In keeping things as simple as possible, only conventional DASD is described in this book.
- ▶ Cloning script or EXEC versus manual installation:
It is easy to spend more time setting up an infrastructure for cloning Linux under z/VM than the time that it saves you over manually installing Linux, given the number of times you actually clone. When cloning works quickly, it can be an extremely useful tool in the system administrator's toolbox. Therefore, this book discusses both cloning and manual installation. These two methods of provisioning Linux servers hinge on the existence of an installation parameter file for each Linux user ID. If you want a more complete solution, the products recommended in the first bullet point are recommended.

1.4 IBM Director and z/VM Center Extension

IBM Director 5.10 brings a comprehensive management functionality to Linux on IBM system z. The base IBM Director functions (e.g. monitoring, event action plans, software distribution, inventory, remote control, task scheduling) are now provided for any Linux end point on System z. In addition, the z/VM Center Extension provides further functionality for provisioning and configuration of z/VM Linux guests.

The z/VM Center extension includes the following tasks:

- ▶ Virtual Server Deployment - creation of virtual servers and deployment of operating systems into them by using virtual server and operating system templates, management of virtual servers (create/delete/activate/properties) and provisioning resources.
- ▶ Server Complexes - automatic fashion of controlling the configuration (and creation) of groups of Linux guests, handling both the z/VM side and Linux side aspects, supporting z/VM Resource Manager performance goals, virtual networking (based on VM Guest LAN, OSA and VSWITCH), z/VM minidisk attachments and configuration scripts.

The integration of the z/VM Center virtualization functionality with the full breadth of IBM Director on Linux managed end points provides a powerful tool for managing Linux guest colonies on z/VM systems.

1.5 Infrastructure design

To clone Linux, or *provision virtual servers*, there must be a certain infrastructure design in place. A System z server with associated resources and the z/VM operating system define much of this infrastructure. Figure 1-1 on page 6 shows a block diagram of a System z9 with many LPARs. z/VM 5.2 is installed in one of these LPARs. z/VM comes with many user IDs predefined. The most important six IDs are shown in the z/VM LPAR above the dashed line. Below the dashed line, you see the user IDs described in this book. Important z/VM minidisks and configuration files are shown next to each user ID.




Figure 1-1 System infrastructure and z/VM user IDs

The user IDs above the dashed line are those important user IDs defined in z/VM 5.2. The user IDs below the dashed line are described in this book and have the following functions:

- ▶ **LNXMAINT:** A user ID on which to store files that will be used by both CMS and Linux
- ▶ **<MAIN ID>:** The user ID that stores the master (or golden) image that is cloned and IPLed from minidisk 100 and the controller (or cloner) image that does the cloning and is IPLed from minidisk 200. In the RHEL 5 book, this user ID is named RHEL5 and in the SLES 10 book it is named SLES10.
- ▶ **LINUX01-04:** The Linux virtual servers described in the *Cloning open source virtual servers* chapter. In addition, creating LINUX05-07 is described so you can have additional user IDs to clone to. Each virtual server is configured with a single 3390-3 minidisk which is slightly more than 2 GB of space.

1.6 Usability tests performed for this book

During the writing of this book, many usability tests were conducted. The participants had a variety of skills, but none had both Linux and z/VM system administration skills. By the end of the first day in all of the formal tests, most participants had all completed up to and including Chapter 5, "Servicing z/VM" on page 69, so z/VM was installed, serviced and customized for TCP/IP communications with a highly available VSWITCH. By the end of the second day, most participants had cloned their first Linux virtual server. You should be able to complete most steps in the book in four solid days of work, if all goes well.

1.7 The chapters in this book

The remaining chapters and appendixes in this book are summarized in the following list:

- ▶ Chapter 2, “Planning” on page 9 describes how to plan hardware, software and networking resources. It discusses DASD labeling conventions used in the book and a password planning. Sample worksheets are provided for the examples used in the book, as are blank copies for your use.
- ▶ Chapter 3, “Configuring a desktop machine” on page 21 describes how to set up Windows desktops. Specifically, the following tools are discussed:
 - How to get and set up PuTTY: a commonly used SSH client
 - How to get and set up a VNC client: a tool for running graphical applications
 - 3270 emulator applications
- ▶ Chapter 4, “Installing and configuring z/VM” on page 29 shows how to install and configure z/VM. This is where you roll up your sleeves and start to work.
- ▶ Chapter 5, “Servicing z/VM” on page 69 describes how to apply service to z/VM both in the form of Programming Temporary Fixes (PTFs) and Recommended Service Upgrades (RSUs).
- ▶ Chapter 6, “Configuring an NFS server for RHEL 5” on page 83, explains how to set up a temporary NFS server on a Linux PC for the purpose of installing the first two Linux images. After the System z controller Linux is installed, you can copy the Linux install tree to it and retire the Linux PC server.
- ▶ Chapter 7, “Installing and configuring RHEL 5” on page 89, describes how to install and configure two Linux images onto the first Linux user ID: the *master image*, which it is cloned from, and the *controller*, which does the cloning among other tasks.
- ▶ Chapter 8, “Configuring RHEL 5 for cloning” on page 133 explains how to prepare z/VM user IDs and clone your first virtual server.
- ▶ Chapter 9, “Installing Linux with kickstart” on page 149 explains how to use Red Hat’s kickstart tool to install virtual servers.
- ▶ Chapter 10, “Servicing Linux with Red Hat Network” on page 155 explains how to use the Red Hat Network and its ability to manage virtual servers.
- ▶ Chapter 11, “Cloning open source virtual servers” on page 161, shows how to configure cloned Linux images into the following virtual servers:
 - Web server virtual server
 - LDAP virtual server
 - File and print virtual server
 - Basic application development system
- ▶ Chapter 12, “Miscellaneous Recipes” on page 183 describes how to add a logical volume to a Linux system and how to set up a z/VM Discontiguous Saved Segment (DCSS) in conjunction with the Linux eXecute In Place 2 (xip2) file system.
- ▶ Chapter 13, “Monitoring z/VM and Linux” on page 197, describes basic steps to begin monitoring z/VM and your new Linux virtual servers.
- ▶ Chapter 14, “Backup and restore” on page 223, shows basic steps on how to back up these new systems.
- ▶ Appendix A, “References” on page 229, provides references Web sites, books and other pertinent information.
- ▶ Appendix B, “Common source code” on page 233 lists source code of the REXX EXECs and shell scripts common, regardless of Linux distribution.

- ▶ Appendix C, “Source code specific to Linux” on page 249 lists source code of the REXX EXECs and shell scripts common, regardless of Linux distribution.

Planning

“The only reason for time is so that everything doesn’t happen at once.”

— Albert Einstein

This chapter covers the planning that should be done before installing z/VM. It begins by discussing a *bill of materials*, or all the resources that you need. Then it explains the labeling of 3390 volumes. Finally resource worksheets are presented for:

- ▶ z/VM resources other than direct access storage device (DASD)
- ▶ DASD resources
- ▶ Linux resources
- ▶ Linux user IDs

2.1 Bill of materials

The resources needed for a Linux on zSeries project can be divided into:

- ▶ Hardware
- ▶ Software
- ▶ Networking

2.1.1 Hardware resources

The following hardware is needed:

- ▶ A zSeries logical partition (LPAR); z800, z900, z890 or z990, or System z9
 - Processors or CPUs: One IFL (or CP) minimum, two or more recommended
 - Memory: 3 GB central/1 GB expanded minimum, 6 GB/2 GB or more recommended. This 3:1 ratio of central to expanded storage is a good starting point.

See the following Web site for a discussion of how to apportion memory:

<http://www.vm.ibm.com/perf/tips/storconf.html>

- DASD: 24 3390-3s or 9 3390-9s at an absolute minimum

- Open Systems Adapter (OSA) network cards: One card minimum with 12 device numbers (technically 9, but OSA “triplets” usually start on an even address). Two OSA Express cards with eight device numbers on one and four on the other is recommended for high availability.
- ▶ A network-attached computer that will act as an Network File System (NFS) server temporarily with at least 6 GB of disk space, but more may be needed. A Linux PC or UNIX server is recommended.
- ▶ A workstation or desktop that has network access to the mainframe

2.1.2 Software resources

The following software resources are needed:

- ▶ z/VM 5.2 install media with documentation (DVD install is described in this book.)
- ▶ Linux install media (SLES or RHEL)
- ▶ An operating system for the NFS server
- ▶ The code associated with this book
- ▶ Tools on the workstation and desktop:
 - A 3270 Emulator such as *Attachmate Extra*, *Hummingbird Host Explorer*, or *IBM Personal Communications* for Windows desktops (for Linux desktops, a 3270 emulator named *x3270* is available)
 - A Linux SSH client such as PuTTY (recommended) or TeraTerm (for Linux desktops the `ssh` client is built in)
 - A VNC viewer

These resources are described in more detail in the chapters that follow.

2.1.3 Networking resources

The following network resources are needed:

- ▶ A TCP/IP address for z/VM
- ▶ One TCP/IP address for each Linux virtual server
- ▶ Associated TCP/IP information:
 - DNS host name
 - DNS domain
 - DNS server TCP/IP address
 - TCP/IP gateway
 - TCP/IP subnet mask
 - TCP/IP broadcast address (usually calculated from address and subnet mask)
 - TCP/IP MTU size

The TCP/IP addresses should be routed to the OSA card(s).

2.2 z/VM conventions

It is good to use conventions so that you and others can recognize z/VM resources by their names. This section discusses conventions for DASD volume names and backup file names.

2.2.1 Volume labeling convention

You should have a convention for labeling DASD. Your shop may already have a labeling convention which will largely determine the labels to be given to the DASD used by your z/VM and Linux LPAR.

Each zSeries DASD is addressed with a device number consisting of four hexadecimal digits. Each zSeries DASD has a six character label. It is convenient to include the four-digit address in the label so that you can easily tell the address of each DASD from its label. When followed, this convention guarantees that no two DASD will have the same label. This can be an important issue especially when z/OS has access to the DASD.

Sometimes DASD is shared among LPARs in which case your z/VM LPAR can *see* DASD *owned* by other LPARs. In this situation, it is convenient to identify the LPAR that *owns* the DASD. Therefore the volume labeling convention used in this book identifies the LPAR via the first character. That leaves the second character in the label to identify the basic function of the DASD.

The LPAR used in this book is identified by the character *M*. The following characters are used for the types of DASD in the second character of the label:

- M** Minidisk space (PERM)
- P** Paging space (PAGE)
- S** Spool space (SPOL)
- T** Temporary disk space (TDISK)
- V** z/VM operating system volumes

For example, Figure 2-1 shows the labeling convention for the DASD in LPAR *M*, of type *minidisk* at real address *A700*.




Figure 2-1 DASD labeling convention

The letter M is hard-coded into two EXECs that adopt this convention. If you want a different LPAR identifier character, they can easily be changed.

2.2.2 Backup file naming convention

It is recommend that you keep copies of important z/VM and Linux configuration files. You should always keep copies of original configuration files in case you need to go back to them. Since z/VM file names are limited to 16 characters (eight for the file name and eight for the file type), only the last four characters of the file type are used. This often requires some characters to be overwritten. For the original file, the suffix ORIG is used, and for the most recent working copy, the suffix WRKS (for “it WoRKS”!) is used. For example, the original USER DIRECT file is copied to the file USER DIREORIG before it is modified the first time.

2.2.3 The command retrieve convention

The ability to retrieve past commands is a common tool. Often it is nice to retrieve in both directions in case you “pass” the command you’re looking for. The default Linux shell, **bash**, does this by default with the up arrow and down arrow keys.

There is a convention in z/VM to use the **F12** function key (labeled PF12 on physical 3270 devices) to retrieve the last command, though it is not defined to all user IDs. There is no convention retrieve commands in the other direction but it is possible to set another key to that function. Therefore, **F11** is used to *retrieve forward* since it is right next to F12. Also, the same function is useful in the editor, **XEDIT**. The **?** subcommand retrieves past commands, so it is recommended that you assign it to **F12**.

2.3 Disk planning

There are different aspects to consider when planning how to choose and allocate disk storage. Some aspects include the following

- ▶ Conventional ECKD DASD vs. FBA disks over SCSI/FCP
- ▶ 3390-3s vs. 3390-9s or large disk support
- ▶ Amount of disk storage per Linux image and how to allocate file systems

DASD vs SCSI/FCP

This book describes how to use conventional ECKD DASD and does not discuss FBA disks accessed over SCSI/FCP. This is not because either technology is superior, but simply because DASD seems to be much more common than SCSI/FCP disks. If you were to use SCSI/FCP disks, cloning via the **clone.sh** script would have to be modified to account for World Wide Port Names and Numbers. Sometimes a combination of these two types of disk storage is used - when that is the case the ECKD emulated DASD is often used for the root file system and SCSI/FCP disks are used for large data storage areas.

3390-3s vs. 3390-9s

Emulated 3390-3s format to about 2.3GB, while 3390-9s are three times the size or about 6.9MB. Either size will work, though 3390-3s have been recommended over 3390-9s by some performance analysts. This book describes mainly using 3390-3s, however, comments are added where using 3390-9s differs - especially with installing z/VM.

Disk storage per Linux image

A single 3390-3, or 3339 cylinders, is allocated to the root file system (/) for each Linux image. Often recommendations are made to create many more file systems to be mounted over other directories, such as /usr/, /var/, /tmp/, /home/, /opt/, etc. This model is not used for two reasons:

- ▶ It is difficult to come up with a default set of file system sizes given that the Linux virtual servers will be running many different applications and workloads after being cloned.
- ▶ Under the philosophy of *keep things as simple as possible*.

One common argument for having many mounted file systems is so that the root file system will not fill up. To help prevent this from happening, it is recommended to add mounted file systems after cloning under the directory where data and applications will be added. For example, in the chapters that follow, a /nfs/ file system is added to the controller to store the install tree and a /home/ file system is added to LINUX02 to store user’s data.

2.4 Memory planning

Planning memory may be the most difficult issue with System z Linux and z/VM, yet the most important to ensure adequate performance. The simplest solution may be to have enough central memory (storage) in the LPAR so that z/VM never pages and Linux never swaps. However, such resource may not be realistically available.

Discussing memory planning further is outside the scope of this book (and the authors' knowledge :)). The following resources are recommended:

- ▶ The Redbook *Linux on IBM zSeries and S/390: Performance Measurement and Tuning*, 2003, on the Web at:

<http://www.redbooks.ibm.com/abstracts/sg246926.html?Open>

- ▶ The IBM z/VM Performance Resource pages in general, on the Web at:

<http://www.vm.ibm.com/perf/>

- ▶ The IBM z/VM page specifically discussing memory allocation:

<http://www.vm.ibm.com/perf/tips/storconf.html>

One simple rule that can be recommended is to have as few virtual machines logged on (or disconnected) as possible. Every virtual machine that can be logged off will mean more memory for the other virtual servers.

2.5 Password planning

Good passwords are critical to good security. However, requiring many different passwords leads to people writing them down, which detracts from good security. Sometimes it is difficult to balance these two extremes.

This book considers different system administration roles:

- ▶ The z/VM system administrator
- ▶ The Linux system administrator
- ▶ The Linux virtual server end users

The z/VM and Linux system administrator may well be the same person.

The method of backing up z/VM data onto the Linux controller means that the Linux administrator will have access to all z/VM passwords. Therefore, the examples in this book set all z/VM and Linux system administration passwords to the same value, 1nx4vm. If the z/VM and Linux system administrator roles must be kept separate and the Linux administrator is not to have access to the z/VM passwords, then a different method of backing up z/VM data must be chosen.

You may want to define a finer granularity for passwords based on the following system administration roles:

- ▶ The main z/VM system administrator (MAINT)
- ▶ The z/VM network administrator (TCPMAINT)
- ▶ The z/VM Linux administrator (LNXMAINT, Linux controller, Linux virtual server user IDs)
- ▶ The Linux virtual server end users (with or without access to 3270 sessions, with or without the root passwords)

The sets of passwords that you define will depend on the roles that your organization will adopt.

2.6 Planning worksheets

Four worksheets are included in this section. They are populated with the resources used in writing this book. There are also four corresponding blank worksheets in 2.7, “Blank worksheets” on page 17.

2.6.1 z/VM resources used in this book

Table 2-1 lists the z/VM resource values used in the examples in this book. You can use these values as a reference for completing the blank worksheets that follow.

Table 2-1 z/VM resources worksheet

Name	Value	Comment
LPAR name	P21	3 GB central storage/1 GB expanded, 4 shared IFLs
CPC name	PELCP01	Name of CPC on which the LPAR is located
z/VM system name	LNXVM52	Name to be assigned to z/VM system
TCP/IP host name	lat120	Assigned by a network administrator; helpful to set in DNS beforehand, but not necessary
TCP/IP domain name	pbm.ihost.com	Helpful to set in DNS beforehand
TCP/IP gateway	129.40.178.254	The router to and from the local subnet
DNS server 1	129.40.106.1	Assigned by the network administrator
DNS server 2/3 (optional)		Not used
OSA device name	eth0	Name of the interface to be assigned by IPWIZARD
OSA starting device number	3000	Start of OSA <i>triplet</i> for the z/VM TCP/IP stack
TCP/IP address	129.40.178.120	The TCP/IP address of the z/VM system
Subnet mask	255.255.255.0	Assigned by network administrator
OSA device type	QDIO	Often “QDIO” for OSA/Express cards
Network type	Ethernet	Usually “Ethernet”
Port name (optional)		Not required by z/VM
Router type	None	Usually “None”
Primary OSA device number for VSWITCH	3004	Specify the first device number (must be even number) and the next two device numbers will also be used
Secondary OSA device number for VSWITCH	3008	Should be on a different CHPID/OSA card

2.6.2 z/VM DASD used in this book

Table 2-2 lists the z/VM DASD resource values used in the examples in this book.

Table 2-2 z/VM DASD worksheet

Device number	Label	Type	Notes
A700	520RES	CP owned	z/VM System residence volume
A701	520SPL	System spool	Spool volume 1 from z/VM installation
A702	520PAG	CP owned	Paging volume 1 from z/VM installation
A703	520W01	System spool	z/VM W01 volume
A704	520W02	System paging	z/VM W02 volume
A705	MPA705	System paging	Paging volume 2
A706	MPA706	System paging	Paging volume 3
A707	MPA707	System paging	Paging Volume 4
A708	MPA708	System paging	Paging Volume 5
A709	MPA709	System paging	Paging volume 6
A728	MMA728	System minidisk	RHEL5 100 - the <i>master image</i>
A729	MMA729	System minidisk	RHEL 5 200 - the <i>controller</i>
A72A	MMA72A	System minidisk	RHEL 5 203 and LNXMAINT 191 and 192
A72B	MMA72B	System minidisk	RHEL 5 204, part of the /nfs/ logical volume
A72C	MMA72C	System minidisk	RHEL 5 205, part of the /nfs/ logical volume
A72D	MMA72D	System minidisk	RHEL 5 206, part of the /nfs/ logical volume
A72E	MMA72E	System minidisk	RHEL 5 207, part of the /nfs/ logical volume
A740	MMA740	System minidisk	LINUX01 100
A741	MMA741	System minidisk	LINUX02 100
A742	MMA742	System minidisk	LINUX03 100
A743	MMA743	System minidisk	LINUX04 100
A744	MMA744	System minidisk	LINUX05 100
A745	MMA745	System minidisk	LINUX06 100
A746	MMA746	System minidisk	LINUX07 100

2.6.3 Linux resources used in this book

Table 2-3 lists the Linux resources used in the examples in this book.

Table 2-3 Linux resources worksheet

Name	Value	Comment
Linux install password	lnx4vm	

Name	Value	Comment
Linux TCP/IP gateway	129.40.178.254	
Linux TCP/IP broadcast	129.40.178.255	
Linux DNS server	129.40.106.1	Often the same as z/VM's
NFS server TCP/IP address	129.40.46.206	
VNC installation password	lnx4vm	

2.6.4 Linux user IDs used in this book

Table 2-4 lists the Linux user IDs used in the examples in this book.

Table 2-4 Linux user ID worksheet

Linux user ID	IP address	DNS name	Notes
RHEL5	129.40.178.128	lat128.pbm.ihost.com	A 64-bit controller (cloner) and master (golden) image
LINUX01	129.40.178.121	lat121.pbm.ihost.com	A Web virtual server
LINUX02	129.40.178.122	lat122.pbm.ihost.com	An LDAP virtual server
LINUX03	129.40.178.123	lat123.pbm.ihost.com	A file and print virtual server
LINUX04	129.40.178.124	lat124.pbm.ihost.com	An application development server
LINUX05	129.40.178.125	lat125.pbm.ihost.com	Available for use
LINUX06	129.40.178.126	lat126.pbm.ihost.com	Available for use
LINUX07	129.40.178.127	lat127.pbm.ihost.com	A test server for kickstart

2.7 Blank worksheets

Blank copies of the same four worksheets are provided for your use.

2.7.1 z/VM resources worksheet

Use the worksheet in Table 2-5 to document the z/VM resources that you will use.

Table 2-5 z/VM resources blank worksheet

Name	Value	Comment
LPAR name		
CPC name		
System name		
TCP/IP host name		
TCP/IP domain name		
TCP/IP gateway		
DNS server 1		
DNS server 2/3 (optional)		
OSA device name		Often "eth0"
OSA starting device number		
TCP/IP address		
Subnet mask		
OSA device type		Often "QDIO"
Network Type		Often "Ethernet"
Port name (optional)		
Router Type		Often "None"
Primary OSA device number for VSWITCH		
Secondary OSA device number for VSWITCH		Should be on a different CHPID/OSA card than primary

2.7.2 z/VM DASD worksheet

Use the worksheet in Table 2-6 to document the z/VM DASD that you will use.

Table 2-6 z/VM DASD blank worksheet

[illegible]

2.7.3 Linux resources worksheet

Use the worksheet in Table 2-7 to document your Linux resources.

Table 2-7 Linux resources blank worksheet

Name	Value	Comment
NFS server TCP/IP address		
Linux install password		
Linux root password		
Apache user ID and password		
Linux TCP/IP gateway		
Linux TCP/IP broadcast		
Linux DNS server		
VNC Installation password		

2.7.4 Linux user ID worksheet

Use the worksheet in Table 2-8 to document the Linux user IDs that you will create.

Table 2-8 Linux user ID blank worksheet

Linux user ID	IP address	DNS name	Notes

Configuring a desktop machine

“Technological progress is like an axe in the hands of a pathological criminal.”

— Albert Einstein

Many people use Microsoft Windows as a desktop operating system. This chapter addresses the following tools that are recommended for accessing z/VM and Linux from a Windows desktop:

- ▶ An SSH client: PuTTY is recommended
- ▶ A VNC client: RealVNC is recommended
- ▶ A 3270 emulator: Many choices are available

3.1 PuTTY: A free SSH client for Windows

Throughout this book, SSH is used to log into Linux systems. It is easy to use and cryptographically secure. If you are using a Linux desktop system, an SSH client is built in. But if you are using a Windows desktop, you will need a good SSH client.

PuTTY is probably the most commonly used. You can find a PuTTY client for Windows on CD1 of a SLES 9 or 10 distribution in the `/dosutils/putty` directory. You can download PuTTY from the Web at:

<http://www.chiark.greenend.org.uk/~sgtatham/putty/download.html>

To download from this page, click on the **putty.exe** link for your architecture. Save the file in a directory path such as `C:\WINNT`. PuTTY is a stand-alone executable (no installation needed other than copying the file). You may also want to create a shortcut on your desktop or task bar.

Open PuTTY and the configuration window shown in Figure 3-3 should open. If you spend a few minutes to configure PuTTY it may pay off in time savings.

1. In the *PuTTY Configuration* window, in the left Category panel, click **SSH**.
2. Under the Protocol heading on the right, click the **SSH** radio button. This specifies to use the SSH protocol.




Figure 3-1 PuTTY Configuration window

3. Click on **Logging** in the left panel. Click the radio button **Log printable output only**. This will allow you to go back and check on the output of certain commands. Set the *Log file name* to **&H&M&D&T.log** so it will include a timestamp in the file name.




Figure 3-2 Setting Logging

4. In the left panel, click **SSH** near the bottom.
5. On the right side, under *Preferred SSH protocol version*, click the **2 only** radio button.




Figure 3-3 Customizing PuTTY SSH settings (Part 1 of 4)

6. In the left Category panel, click **Terminal**.
7. Select the **Use background colour to erase screen** check box, which results in a better job of painting the screen for applications that uses curses (block graphics).




Figure 3-4 Customizing PuTTY SSH settings (Part 2 of 4)

8. Click **Window** in the left pane.
9. You see the window in Figure 3-5. You may choose more rows and columns than the default of 24x80. In this example, 43 rows and 100 columns are set.




Figure 3-5 Customizing PuTTY window settings (Part 3 of 4)

Saving sessions

1. Click **Session** to get back to the initial window when PuTTY is invoked (see Figure 3-6).
2. In the *Save Sessions* area, select **Default Settings** and click **Save**. This makes all future sessions that you define inherit the preferences you just set.




Figure 3-6 Customizing PuTTY window settings (Part 4 of 4)

Now to save a session for each virtual server, perform the following:

1. In the Host Name (or IP address) field, enter the TCP/IP address (or DNS name).
2. Under Saved Sessions, choose a name that you will remember. In this example, the name `lat40 (LINUX00)` is used. This is the DNS name and the z/VM user ID.
3. Again click **Save** and you should see the name added to the *Saved Session* list.

Now whenever you start PuTTY, you can simply double-click any saved session name, and an SSH session to the desired Linux system is invoked. The final window should appear similar to that shown in Figure 3-7.




Figure 3-7 Saving default PuTTY settings and creating new sessions

3.2 Setting up a VNC client

A VNC client allows access to a graphical environment with System z Linux.

If you are using a Linux desktop you probably have, or at least have access to a VNC client, named **vncviewer**. It is part of the **tightvnc** package.

3.2.1 Downloading and running RealVNC

If you have a Windows desktop, the VNC client from RealVNC is a popular choice (you can also find a TightVNC client for Windows on CD1 of a SLES 9 or 10 distribution in the `/dosutils/tightvnc` directory).

You can purchase a full function RealVNC client, or there is a free version. The RealVNC home page is:

<http://www.realvnc.com>

The download page is:

<http://www.realvnc.com/download.html>

Fill out the Web form and download the executable. When you have downloaded it, run it and an install program will start. At the time of writing of this book, RealVNC 4.1.1 was the current version.

Accept all defaults, however, you probably do not need a VNC server on your desktop. So you can **deselect VNC Server** from the *Select Components* panel as shown in Figure 3-8.




Figure 3-8 RealVNC Select Components panel

Complete the screens and the installation process should go quickly.

3.2.2 Customizing RealVNC

The latest VNC protocol is version 4, which is the default with the VNC client. This version will work with the VNC servers shipped with SLES 10 or RHEL5, however, version 3.3 is required to communicate with the VNC server shipped with SLES 9.

If you need to use protocol version 3.3 for SLES 9, open the VNC client and click on the **Options** button as shown in the left side of Figure 3-9. Click on the **Misc** tab. Click the checkbox named **Use only protocol version 3.3** as shown in the center of the figure. Finally, click the **Load/Save** tab and click **Save** the changes.




Figure 3-9 Setting VNC client to use protocol 3.3 - required for SLES 9 only.

Your VNC client should now be ready to connect to the VNC server that your Linux systems will have.

3.3 3270 emulators

To access a logon session with z/VM, it is common to use a 3270 emulator that runs on Windows. Many commercial products are available. Some of the more common ones are:

- ▶ Attachmate Extra!
- ▶ Hummingbird Host Explorer
- ▶ IBM Personal Communications
- ▶ Quick3270

It is beyond the scope of this book to explain the details of configuring all the various emulators. However, it is recommended that you investigate the following settings for your emulator:

- ▶ Set the **Enter** and **Clear** function keys to be where you would expect them. On some emulators, the default Enter key action is set to the right **Ctrl** key of modern keyboards. Likewise the Clear key action is sometimes set to the **Esc** key in the upper left corner of modern keyboards or the **Pause** key in the upper right.
- ▶ Set a larger screen. Often the default number of lines in an emulator session is 24. You will probably be more productive with a 32 or 43 lines if that can easily fit in a window given your desktop display size and resolution.
- ▶ Have the session automatically reconnect after logoff. Having a new logon screen come back immediately after you log off can also save you time in the long run. This is often not the default behavior.
- ▶ Save your connection sessions. Rather than continually typing in the IP address or DNS name of the z/VM system to which you want to connect, spend a few minutes to define and save a session for each system to which you may connect, as was described for PuTTY. Then you can usually double-click the saved connection to quickly access a new 3270 session.

Installing and configuring z/VM

“Example isn't another way to teach. It is the only way to teach.”

— Albert Einstein

To complete this chapter, you must complete the majority of chapter 6 *Configuring an NFS server*. However, it is recommended that you start here, because there is a step when installing z/VM (**instdvd**) that takes over two hours or possibly much longer near the end of section 4.1.2, “Copying a vanilla z/VM system to DASD” on page 32. While that process is running, you can configure the Network File System (NFS) server. Alternatively, if you have other personnel who can work on the project, you can start both chapters at the same time on the different systems.

4.1 Installing z/VM from DVD

The section that follows assumes a first level installation of z/VM from DVD onto DASD. If you have not already done so, complete the worksheet in 2.7.1, “z/VM resources worksheet” on page 17. You will need access to the Hardware Management Console (HMC) with a user ID that has authority to go into single object operations mode.

z/VM 5.2 is shipped on tape and DVD. z/VM should install faster from tape due to faster I/O speeds, however, installing from tape may require more trips between and the HMC and the tape drive.

If you are familiar with the HMC, you can use the two page *z/VM Summary for Automated Installation and Service (DVD Installation)* to replace or augment the description that follows.

If you are not familiar with the HMC and z/VM, you may want to use the complete installation manual *z/VM Guide for Automated Installation and Service Version 5 Release 2.0*, GC24-6099. If you are installing z/VM at the *second level* (z/VM under z/VM) or onto SCSI disk, you will want to use the z/VM manual as the sections that follow don't address these options.

4.1.1 Booting z/VM from DVD

This section explains how to install z/VM 5.2 from an HMC with a DVD-ROM onto 3390-3 DASD. Some words are included for installing onto 3390-9s. For alternative configurations such as installing from tape or onto SCSI disks, refer to the z/VM documentation.

1. On the Hardware Management Console, select the LPAR on which you want to install z/VM.
2. If necessary, click the *racetrack* buttons (two buttons that are circular arrows on the bottom right corner) to traverse to the *CPC Recovery* (sometimes named just *Recovery*) menu.
3. On the *CPC Recovery* menu, double-click the **Integrated 3270 Console** as shown at the bottom of Figure 4-1. A window entitled *Integrated 3270 Console for <yourCPC>* will open (on older HMC levels, the window may be entitled *Personal Communications*).

Hint: It is convenient to use the Alt-Tab key sequence to move between the HMC window and 3270 console.




Figure 4-1 Integrated 3270 Console icon

4. Place the **z/VM Product Package Version 5 Release 2.0** DVD in the HMC DVD drive.
5. Get into *Single Object Operations* mode. To get into this mode, perform the following steps:
 - a. Double-click the **Groups** icon in the *Views Area*
 - b. Double-click **Defined CPCs** in the *Groups Work Area*.
 - c. Select your CPC.
 - d. If necessary, go around the *racetrack* (the buttons with circular arrows on the bottom right corner) to the *CPC Recovery* menu.
 - e. Double-click the **Single Object Operations** icon. Click **yes** to confirm. Now a new window *Primary Support Element Workplace* should appear (on older HMC levels it will be a “window within a window”). A window about a certificate. If so, click **OK**.
 - f. Double-click **Groups** near the top of this window.
 - g. Double-click **Images** in the Groups Work Area.

Important: If you are unable to get into Single Object Operations mode, it may be because you do not have sufficient permission. Check with the system administrator.

6. Select the LPAR that z/VM will be installed into.
7. Go around the racetrack in this window to the CPC Recovery menu. Double-click the **Load from CD-ROM or Server** icon when you see it (see Figure 4-2 on page 31).




Figure 4-2 CPC Recovery menu with “Load from CD-ROM or Server” icon present.

8. On the *Load CD-ROM or Server* window as shown in Figure 4-3, the radio button **Hardware Management Console CD-ROM/DVD** should be selected.
9. In the same *Load CD-ROM or Server* window, fill in *File Location* with **/cpdvd**. This is the directory on the DVD with the z/VM 5.2 installation code.
10. Click **OK**.




Figure 4-3 Load from CD-ROM or Server panel

11. Load the RAMDISK:

- a. From the *Load from CD-ROM or Server* panel, the software **520vm.ins** should be selected as shown in Figure 4-4. Click **OK**.




Figure 4-4 Selecting z/VM 5.2 RAMdisk system

- b. From the Confirm the action window, click **Yes**. You should see the *Load from CD-ROM, DVD or Server Progress* window. The green light on the DVD drive should light up.
- c. When you see the message *Completed successfully*. Click **OK** to close. This should normally take about four to six minutes.

Attention: Normally, the z/VM RAMdisk (IBMVMMRAM) loads in about four minutes. However, slow load times have been observed (15-18 minutes). When the green light on the DVD drive is solid, the load time will be acceptable. When it is intermittently dark more than it is green, long load times can result. This will also balloon the estimated run time of 2 - 2.5 hours of the **INSTDVD** process where it may consume 5-6 hours. PMR 58909,180 was opened to address this issue.

You should now have an in-memory z/VM 5.2 system running.

4.1.2 Copying a vanilla z/VM system to DASD

This section describes the steps to copy z/VM to DASD.

1. You can now get out of Single object operations mode. To do so, log off the primary SE window by closing that window.
2. Use the **Alt-Tab** sequence, move to the Integrated 3270 Console window. The RAMdisk IPLs and the system comes up with the **MAINT** user ID logged on. You should see z/VM boot as shown in Figure 4-5:

```

PELHMC2: Integrated 3270 Console for PELCP01:P21
File Keys Font Help
11:42:23 z/VM V5 R2.0 SERVICE LEVEL 0000 (64-BIT)
11:42:24 SYSTEM NUCLEUS CREATED ON 2005-10-23 AT 11:53:04, LOADED FROM $RAMDISK$
11:42:24 *****
11:42:24 * LICENSED MATERIALS - PROPERTY OF IBM* *
11:42:24 * * *
11:42:24 * 5741-A05 (C) COPYRIGHT IBM CORP. 1983, 2005. ALL RIGHTS *
11:42:24 * RESERVED. US GOVERNMENT USERS RESTRICTED RIGHTS - USE, *
11:42:24 * DUPLICATION OR DISCLOSURE RESTRICTED BY GSA ADP SCHEDULE *
11:42:24 * CONTRACT WITH IBM CORP. *
11:42:24 * *
11:42:24 * * TRADEMARK OF INTERNATIONAL BUSINESS MACHINES. *
11:42:24 *****
11:42:24
11:42:24 HCPZC06718I Using parm disk 1 on volume $RAMDISK$ (device FFFF).
11:42:24 HCPZC06718I Parm disk resides on blocks 18000 through 52992.
11:42:24 The directory on volume $RAMDISK$ at address FFFF has been brought online.
11:42:24 HCPWRS2512I Spooling initialization is complete.
11:42:24 No dump unit - Dump function is SET OFF
11:42:24 HCPAAU2700I System gateway IBMVMRAM identified.
11:42:24 z/VM Version 5 Release 2.0, Service Level 0000 (64-bit),
11:42:24 built on IBM Virtualization Technology
11:42:24 There is no logmsg data
11:42:24 FILES: NO RDR, NO PRT, NO PUM
11:42:24 LOGON AT 11:42:24 EDT MONDAY 07/17/06
11:42:24 SYSG LOGON AS MAINT USERS = 1
11:42:24 HCPIOP952I 1536M system storage
11:42:24 FILES: 0000001 RDR, 0000001 PRT, NO PUM
11:42:24 HCPCRC8082I Accounting records are accumulating for userid OPERACCT.
11:42:24 HCPCRC8082I EREP records are accumulating for userid OPEREREP.
DMSIND2015W Unable to access the Y-disk. Filemode Y (19E) not accessed
DMSWSP327I The installation saved segment could not be loaded
z/VM V5.2.0 2005-10-26 20:00
DMSDCS1083E Saved segment CMSPIPES does not exist
DMSDCS1083E Saved segment CMSPIPES does not exist
DMSDCS1083E Saved segment CMSUMLIB does not exist

```

Figure 4-5 z/VM first boot on Integrated console

3. Invoke the **instplan** command. This will allow you to choose associated z/VM products to install, the language to use and the type of DASD on which to install:

==> **instplan**




Figure 4-6 Installation planning panel

4. You should see the display as shown in Figure 4-6. It is recommended that you leave the M's in the top section alone.
5. Type the letter **X** next to AMENG (or select your language) and 3390 Mod 3 (or the type of DASD you will use) as shown above.
6. Press **F5**. You should see the message HCPINP8392I INSTPLAN EXEC ENDED SUCCESSFULLY.
7. Attach the DASD devices onto which z/VM will be installed defined in your planning worksheet in 2.7.2, "z/VM DASD worksheet" on page 18. In this example, the devices are a700-a704.

```
==> att <a700-a704> *
a700-a704 ATTACHED TO MAINT
```

Important: The angle brackets, <>, in the above example should not be typed. They are used throughout the book to signify that you should replace the example value with the correct value for your site. For example, if you are installing z/VM onto DASD 1200-1204, you would type the following:

```
==> att 1200-1204 *
```

Running INSTDVD

The INSTDVD EXEC copies the z/VM system from DVD to disk.

1. Execute the **INSTDVD EXEC**:

==> instdvd

2. If you are using 3390-3s, you see a panel asking for the five volumes as shown in Figure 4-7.




Figure 4-7 INSTDVD DASD address panel

- a. Enter the addresses of the five volumes that z/VM will be installed on.
 - b. Do *not* select the DO NOT FORMAT DASD check box on the right side of the panel.
 - c. Press **F5** to start the installation.
3. When you see the question DO YOU WANT TO CONTINUE?, type **Y**. You should see the message NOW FORMATTING DASD <A700>.

Important: INSTDVD takes about two and one half hours. Now may be a good time to go to chapter 6 to set up an NFS server.

Also, read errors have been observed resulting in **INSTDVD** failing. If this is the case, you can try the command **instdvd (restart)** and the install process should pick up where the read error occurred. This can be caused by dirt or fingerprints on the DVD.

4. You are asked to place the system RSU in the drive. Insert the **z/VM Stacked Recommended Service Upgrade 5201** DVD into the HMC DVD-ROM drive and type **G0**. You should see a messages of the form DVDLOAD: LOADING FILE CKD5000x IMAGE *. This step takes two to four minutes.
5. Finally, you should see the message HCPIDV8329I INSTDVD EXEC ENDED SUCCESSFULLY.

4.1.3 IPL the vanilla z/VM from DASD

IPL your initial z/VM system now on DASD.

1. From the HMC, **select your LPAR** by clicking it. You may have to first double-click **Groups**.
2. You should see the *CPC Recovery* (sometimes just *Recovery*) menu. Double-click the **Load** icon in the menu at the right side.

3. The Load window opens as shown in Figure 4-8. Follow these steps:
 - a. Check the radio button **Clear**.
 - b. Set the load address to the new system residence (520RES) volume which is **<A700>** in this example.
 - c. Set the load parameter to **SYSG**. This specifies to use the Integrated 3270 console.
 - d. Click **OK** to IPL.

Load

CPC: PELCP01

Image: P21

Load type: ☐ Normal ☒ Clear ☐ SCSI ☐ SCSI dump

☐ Store status

Load address: *A700

Load parameter: SYSG

Time-out value: 60 (60 to 600 seconds)

Worldwide port name: 0

Logical unit number: 0

Boot program selector: 0

Boot record logical block address: 0

Operating system specific load parameters:

OK Reset Cancel Help

Done 129.40.178.71

Figure 4-8 Load window

4. When you see the *Load Task Confirmation* window, click **Yes**.
5. After 1-3 minutes you should see *Success* in the *Load Program* window. Click **OK**.
6. Use the **Alt-Tab** sequence to move back to the Integrated 3270 console window. You should see the *Standalone Program Loader* panel as shown in the following diagram.
 - a. Press the **Tab** key to traverse to the *IPL Parameters* section and enter the value **cons=sysg**. This specifies to use the Integrated 3270 console.

STAND ALONE PROGRAM LOADER: z/VM VERSION 5 RELEASE 2.0

DEVICE NUMBER: A700 MINIDISK OFFSET: 00000000 EXTENT: 1

MODULE NAME: CPLOAD LOAD ORIGIN: 2000

-----IPL PARAMETERS-----

cons=sysg

-----COMMENTS-----

9= FILELIST 10= LOAD 11= TOGGLE EXTENT/OFFSET

b. Press the **F10** key to continue the IPL of your z/VM system. This should take around 2-3 minutes.

7. At the Start (Warm|Force|COLD|CLEAN) prompt, enter the following:

==> **cold drain noautolog**

8. At the Change TOD clock prompt enter:

==> **no**

9. The last message should be HCPCRC8082I EREP records are accumulating for userID EREP. Disconnect from the OPERATOR user ID via the **DISCONNECT** command:

==> **disc**

Press **Enter** to get a new logon screen.

4.1.4 Completing the z/VM installation

Follow these steps to complete the z/VM installation

1. On the z/VM login screen, logon as **MAINT**. The password is **MAINT**. You may receive messages HCPLMN108E or DMSACP113S about disks not linked or attached. This is not a problem. Press **Enter** when you see the VM Read prompt in the lower right corner.

Important: When logging onto a z/VM user ID that runs CMS, you should usually press **Enter** at the VM READ prompt. This will result in a prompt of the form:

Ready; T=0.01/0.01 11:14:20

2. IPL CMS and press **Enter**. You should see the Ready; prompt.

==> **ipl cms**

```
==> Press Enter  
Ready;
```

3. Run the **instvm dvd** command:

```
==> instvm dvd  
...  
HCPPLD8329I POSTLOAD EXEC ENDED SUCCESSFULLY  
...  
HCPIVM8392I INSTVM ENDED SUCCESSFULLY
```

This EXEC continues the installation process. This step should take about 4-8 minutes. The last message should be HCPIVM8392I INSTVM ENDED SUCCESSFULLY

4. Load the recommended service. For z/VM 5.2, the service name is **5201RSU1**. Run the following commands:

```
==> ipl cms  
==> Press Enter  
Ready;  
==> acc 500 c  
DMSACC724I 500 replaces C (2CC)  
==> listfile * * c  
5201RSU1 SERVLINK C1  
==> service all 5201rsu1
```

This step should take about 3-6 minutes. The last message should be VMFSRV2760I SERVICE processing completed successfully.

5. Now IPL CMS and run the **put2prod** command. This puts the service into production:

```
==> ipl cms  
==> Press Enter  
Ready;  
==> put2prod
```

This step should take about 2-4 minutes. The last message should be VMFP2P2760I PUT2PROD processing completed successfully.

A return code of 0 is ideal. You may get a return code of 4 and the message:

```
VMFP2P2760I PUT2PROD process completed with warnings.
```

In general on z/VM, a return code of 4 is acceptable. That means that only warnings were issued. A return code of 8 or greater generally means that errors were encountered.

6. Enter the following command to shutdown and reIPL your system:

```
==> shutdown reipl  
SYSTEM SHUTDOWN STARTED
```

7. You will lose your 3270 session. The system should come back in about 2-4 minutes. After it comes back, the last message should be "Press enter or clear key to continue". **Press Enter** and you should see a z/VM logon screen.

Congratulations! You should now have a vanilla z/VM system installed.

4.2 Configuring TCP/IP

It is recommended that you initially configure TCP/IP via the **IPWIZARD** command which is generally used just once. After **IPWIZARD** creates the initial configuration files, they are typically maintained manually.

From the z/VM logon panel **Logon to MAINT**. The default password for all z/VM user IDs is the same as the user ID. So enter a password of **maint** which will not be echoed on the screen.

```
USERID ==> maint
PASSWORD ==>
```

After entering the user ID and password, press **Enter** when the status area in the lower right reads “VM READ”.

4.2.1 Use the IPWIZARD tool

The **IPWIZARD** command is on the MAINT 193 disk. You will need to access it file mode G via the **ACCESS** command so you will pick up **IPWIZARD** from that minidisk.

1. Access the MAINT 193 disk:

```
==> acc 193 g
```

2. Invoke **IPWIZARD**.

```
==> ipwizard
```

```
*** z/VM TCP/IP Configuration Wizard ***
```

The items that follow describe your z/VM host

User ID of VM TCP/IP Stack Virtual Machine: **TCPIP**__

Host Name: <lat120>_____

Domain Name: <pbm.ihost.com>_____

Gateway IP Address: <129.40.178.254>_____

DNS Addresses:

1) <129.40.106.1>_

2) _____

3) _____

3. The *z/VM TCP/IP Configuration Wizard* opens as shown in the preceding example. The first field, User ID, should always be **TCPIP**. Obtain the remaining values from the 2.7.1, “z/VM resources worksheet” on page 17 and press **F8**.

```
*** General Interface Configuration Panel ***
```

Interface Name: **ETH0**_____ Device Number: <3000>

IP Address: <129.40.178.120>_

Subnet Mask: <255.255.255.0>__

Interface Type (Select one):

<input checked="" type="checkbox"/>	QDIO	<input type="checkbox"/>	LCS	<input type="checkbox"/>	HiperSockets
<input type="checkbox"/>	CLAW	<input type="checkbox"/>	CTC		

4. An *Interface Name* of **ETH0** is arbitrary but recommended. The *Device Number* will be the starting address of the OSA triplet that the z/VM stack will use. The *IP address* which must be routed to the OSA card will become the TCP/IP address of the z/VM system. The *Interface Type* will typically be **QDIO** with modern OSA devices. When completed, press **F8**.

```
*** QDIO Interface Configuration Panel ***
```

```
Network Type (Select one):
```

```
  x  Ethernet          _  Token Ring
```

```
Port Name (optional): _____
```

```
Router Type (Select one):
```

```
  _  Primary          _  Secondary      x  None
```

```
Maximum Transmission Unit (MTU) size: 1500_
```

5. In general a value for the *Port Name* is no longer necessary and a *Router Type* of **None** is recommended. Press **F5** to complete the wizard.

```
DTCIPW2508I DTCIPWIZ EXEC is attempting to create the necessary
DTCIPW2508I configuration files
```

6. Enter **1** to restart the TCP/IP stack:

```
The TCP/IP stack (TCPIP) must be restarted as part of this procedure
Would you like to restart and continue?
```

```
Enter 0 (No), 1 (Yes) 1
```

```
USER DSC  LOGOFF AS  TCPIP    USERS = 2      FORCED BY MAINT
```

```
...
```

```
Successfully PINGed Interface (129.40.178.120)
```

```
Successfully PINGed Gateway (129.40.178.254)
```

```
Ping Level 520: Pinging host 129.40.106.1.
```

```
Enter 'HX' followed by 'BEGIN' to interrupt.
```

Important: If the DNS server cannot be pinged, enter **1** to try it again.

```
PING: Ping #1 timed out
```

```
Not all of the PINGs were successful. Would you like
to try them again?
```

```
Enter 0 (No), 1 (Yes)
```

```
==> 1
```

```
...
```

Watch for the message **IPWIZARD EXEC ENDED SUCCESSFULLY**.

```
...
```

```
Successfully PINGed Interface (129.40.178.120)
```

```
Successfully PINGed Gateway (129.40.178.254)
```

```
Successfully PINGed DNS (129.40.106.1)
```

```
DTCIPW2519I Configuration complete; connectivity has been verified
```

```
DTCIPW2520I File PROFILE TCPIP created on TCPIP 198
DTCIPW2520I File TCPIP DATA created on TCPIP 592
DTCIPW2520I File SYSTEM DTCPARMS created on TCPIP 198
HCPINP8392I IPWIZARD EXEC ENDED SUCCESSFULLY
DMSVML2061I TCPIP 592 released
```

7. At this point your z/VM TCP/IP stack should be up. You should now be able to ping it from another system.

If the **IPWIZARD** fails you must continue debugging it until it succeeds. Double check all values. Verify that the TCP/IP network and OSA information you were given are properly associated.

HMC Integrated 3270 Console or 3270 emulator? At this point z/VM should be accessible over the network. You can continue working at the HMC, or you can access your new system via a 3270 emulator. See 3.2, “3270 emulators” on page 17 for some brief words on that subject.

If you want to switch to 3270 emulator, you can **LOGOFF** of MAINT or **DISConnect**. If you logoff the session is ended - it is analogous to shutting and powering down a PC. If you disconnect, your session remains where it is and is resumed when you log back on. It is analogous to turning a PC's monitor off. In general, you should **LOGOFF** of system administration user IDs such as MAINT. However, you should always **DISCONNECT** from z/VM service machines such as TCPIP and user IDs running Linux. Logging of of them will terminate the service or crash Linux.

4.3 Configuring the XEDIT profile

Logon to MAINT if you are not already.

The **XEDIT** command looks for the file **XEDIT PROFILE** configuration file when it is invoked. Many z/VM user IDs do not have such a file, so all **XEDIT** default values are in effect. The MAINT 191 (A) disk has a **PROFILE XEDIT** so when you are editing files on MAINT, the values in this profile are usually in effect.

One setting that can be dangerous, especially if you use F12 to retrieve commands, is that PF12 is set to the **FILE** subcommand. Sometimes you may not want to save your changes with the stroke of one key. It is recommended that you set PF12 to the **?** subcommand which has the effect of a retrieve key:

```
==> copy profile xedit a profile xediorig a (oldd
==> x profile xedit a
```

Before:

```
SET PF12 FILE
```

After:

```
SET PF12 ?
```

Save your changes with the **FILE** subcommand.

4.4 Customizing the SYSTEM CONFIG file

The first configuration file read when z/VM IPLs is the SYSTEM CONFIG file. The following changes are recommended:

- ▶ Change the system name
- ▶ Increase retrieve key capacity
- ▶ Allow virtual disks (VDISKs) to be created
- ▶ Turn off the Disconnect Timeout. This will prevent idle disconnected users from being forced off the system
- ▶ Define a virtual switch (VSWITCH) that will be used for Linux networking

To make these changes, perform the following steps:

1. To edit the SYSTEM CONFIG file, the MAINT CF1 minidisk must be released as a CP disk via the **CPRELEASE** command. The CP disks are queried via the **QUERY CPDISK** command. Note the MAINT CF1 disk is accessed as CP disk A before it is released but not after.

```
==> q cpdisk
Label  Userid  Vdev Mode Stat Vol-ID Rdev Type  StartLoc  EndLoc
MNTCF1 MAINT  OCF1  A   R/O  MVA740 A740 CKD      39      158
MNTCF2 MAINT  OCF2  B   R/O  MVA740 A740 CKD     159     278
MNTCF3 MAINT  OCF3  C   R/O  MVA740 A740 CKD     279     398
```

```
==> cprel a
CPRELEASE request for disk A scheduled.
HCPZAC6730I CPRELEASE request for disk A completed.
```

```
==> q cpdisk
Label  Userid  Vdev Mode Stat Vol-ID Rdev Type  StartLoc  EndLoc
MNTCF2 MAINT  OCF2  B   R/O  MVA740 A740 CKD     159     278
MNTCF3 MAINT  OCF3  C   R/O  MVA740 A740 CKD     279     398
```

2. Once it is released you are able to access the MAINT CF1 disk read-write. Use the **LINK** command with multi-read (**MR**) parameter and **ACCESS** command to get read-write access to the minidisk.

```
==> link * cf1 cf1 mr
==> acc cf1 f
```

3. Now the MAINT CF1 disk is accessed read-write as your F disk. First make a backup copy of the vanilla SYSTEM CONFIG file using the **COPYFILE** command with the **OLDDATE** parameter so the file's timestamp is not modified, then edit the original copy:

```
==> copy system config f system conforig f (oldd)
==> x system config f
```

4. The system name is set to ZVMV5R20 by default in the System_Identifier_Default statement. You can search for it using the **/XEDIT** subcommand:

```
====> /System_Identifier_D
```

Modify this to the new name of your system:

```
System_Identifier_Default <LNxVM52>
```

5. Next look for the Features statement. You can search for it again or you can use **F8** to page down. The following changes and additions are recommended:

- Increase the number of commands that can be retrieved from 20 to 99.
- Set the Disconnect_Timeout to **off** so disconnected users do not get forced off.
- Allow unlimited VDISKs to be created by users by changing Userlim to **infinite** and by adding the **Syslim infinite** clause:

```
Features ,
  Disable ,                               /* Disable the following features */
  Set_Privclass ,                         /* Disallow SET PRIVCLASS command */
  Auto_Warm_IPL ,                         /* Prompt at IPL always */
```



```

Clear_TDisk ,          /* Don't clear TDisk at IPL time */
Retrieve ,             /* Retrieve options */
Default 99 ,           /* Default... default is 20 */
Maximum 255 ,          /* Maximum... default is 255 */
MaxUsers noLimit ,     /* No limit on number of users */
Passwords_on_Cmds ,    /* What commands allow passwords? */
Autolog yes ,          /* ... AUTOLOG does */
Link yes ,             /* ... LINK does */
Logon yes ,            /* ... and LOGON does, too */
Disconnect_Timeout off , /* Don't force disconnected users */
Vdisk ,               /* Allow VDISKS for Linux swaps */
Syslim infinite ,
Userlim infinite

```

6. Define a VSWITCH:

Use the **BOTTOM** subcommand to go to the bottom of the file. Add some lines (you can use the **XEDIT** add subcommand **a3**). Define a VSWITCH and set the MAC address prefix. If you have multiple z/VM systems, each should have a unique prefix. Modify the two starting addresses of the OSA triplets (3004 and 3008 in this example) to those you specified in 2.7.1, “z/VM resources worksheet” on page 17.

```

====> bot
====> a3
/* define vswitch named vsw1 and set MAC address prefixes to 02-00-01 */
define vswitch vsw1 rdev <3004> <3008>
vlan macprefix 020001

```

7. Save your changes with the **XEDIT FILE** subcommand:

```
====> file
```

8. Test your changes with the **CPSYNTAX** command which is on the MAINT 193 disk:

```

==> acc 193 g
==> cpsyntax system config f
CONFIGURATION FILE PROCESSING COMPLETE -- NO ERRORS ENCOUNTERED.

```

Pay attention to the output. If you get any syntax errors, fix them before proceeding.

9. Release and detach the MAINT CF1 disk with the **RELEASE** command and **DETACH** parameter. Then put it back online with the **CPACCESS** command:

```

==> rel f (det
DASD OCF1 DETACHED
==> cpacc * cf1 a
CPACCESS request for mode A scheduled.
HCPZAC6732I CPACCESS request for MAINT's OCF1 in mode A completed.
==> q cpdisk

```

Label	Userid	Vdev	Mode	Stat	Vol-ID	Rdev	Type	StartLoc	EndLoc
MNTCF1	MAINT	OCF1	A	R/O	MVA740	A740	CKD	39	158
MNTCF2	MAINT	OCF2	B	R/O	MVA740	A740	CKD	159	278
MNTCF3	MAINT	OCF3	C	R/O	MVA740	A740	CKD	279	398

Note that all three CP disks are now accessed.

4.5 Configuring TCP/IP to start at IPL time

Configure the TCP/IP service machine to be started when z/VM IPLs. This is commonly accomplished from AUTOLOG1's **PROFILE EXEC**. If the **noautolog** parameter is *not* specified when z/VM is IPLed, the AUTOLOG1 virtual machine is started. Because this virtual machine IPLs CMS, the **PROFILE EXEC** that is found on its A disk is run. This is analogous to the `/etc/profile` file on Linux and the `autoexec.bat` on DOS systems.

1. Logoff of MAINT.

==> **log**

2. You should see a new logon panel. **Logon to AUTOLOG1**. Again the password is the same as the user ID.
3. At the VM READ prompt enter the command **ACCESS (NOPROF)** so that the PROFILE EXEC is not run.

```
LOGON AUTOLOG1
z/VM Version 5 Release 2.0, Service Level 0501 (64-bit),
built on IBM Virtualization Technology
There is no logmsg data
FILES:  NO RDR,  NO PRT,  NO PUN
LOGON AT 13:30:12 EST THURSDAY 01/19/06
DMSIND2015W Unable to access the Y-disk. Filemode Y (19E) not accessed
z/VM V5.2.0    2005-12-22 09:36
acc (noprof)
```

4. Copy the PROFILE XEDIT from the MAINT 191 disk so XEDIT sessions will have a common interface among user IDs.

- a. Use the **VMLINK** command to both link to the disk read-only and to access it as the highest available file mode. The default read password is **read**:

```
==> vm link maint 191
ENTER READ PASSWORD:
read
DMSVML2060I MAINT 191 linked as 0120 file mode Z
```

- b. Copy the PROFILE XEDIT to your A disk:

```
==> copy profile xedit z = a
```

5. Make a backup copy of the PROFILE EXEC and edit it:

```
==> copy profile exec a = execorig =
==> x profile exec
```

6. You should see the text in the top half of the following example. Modify it as follows.

- a. The z/VM Shared File System (SFS), is not required to run Linux so you can safely delete the three lines that **XAUTOLOG** the user IDs VMSERVS, VMSERVR and VMSERVU.
- b. You can also safely delete the Address Command line.
- c. Add a line to start the TCPIP user ID via the **XAUTOLOG** command and keep two statements that start the VSWITCH controllers.
- d. Add a line to **logoff** of AUTOLOG1 when the EXEC is complete. There is no need to keep that virtual machine running as its sole purpose is to run the PROFILE EXEC.

Before:

```
/*****/
/*  Autolog1 Profile Exec  */
/*****/
```

Address Command

```
'CP XAUTOLOG VMSERVS'
'CP XAUTOLOG VMSERVU'
'CP XAUTOLOG VMSERVR'
'CP XAUTOLOG DTCVSW1'
'CP XAUTOLOG DTCVSW2'
```

After:

```

/*****
/* Autolog1 Profile Exec */
*****/
'cp xautolog tcpip'          /* start up TCPIP */
'CP XAUTOLOG DTCVSW1'        /* start VSWITCH controller 1 */
'CP XAUTOLOG DTCVSW2'        /* start VSWITCH controller 2 */
'cp logoff'                  /* logoff when done */

```

7. Save your changes with the **FILE** subcommand and **logoff of AUTOLOG1**:

```

====> file
==> log

```

When your z/VM system IPLs, the TCP/IP stack should now come up automatically (as long as you do *not* specify the **notautolog** parameter at IPL time).

4.5.1 Renaming the TCPIP configuration file

It is recommended that you change the name of the main TCPIP configuration file from **PROFILE TCPIP** to **<system_ID> TCPIP**, where **<system_ID>** is the name of your new z/VM system. This is to avoid the possibility that the **PROFILE TCPIP** file will be overwritten when applying maintenance.

Logon to TCPMAINT. The **PROFILE TCPIP** file is on the **TCPMAINT 198** disk which is accessed as the **D** disk.

Make a backup copy the original **PROFILE TCPIP**, then rename it to **<SYSTEM_ID> TCPIP** (where **<SYSTEM_ID>** is **LNxVM52** in this example). When the TCPIP service machine starts, it will search for this file before the file **PROFILE TCPIP**.

```

==> copy profile tcpip d = tcpiorig = (oldd
==> rename profile tcpip d <lnxvm52> = =

```

You have now renamed your TCP/IP profile.

4.5.2 Copy the PROFILE XEDIT file

Again copy the **PROFILE XEDIT** from the **MAINT 191** disk so **XEDIT** sessions will have a common interface among user IDs.

- a. Use the **VMLINK** command to both link to the disk read-only and to access it as the highest available file mode. The default read password is **read**:

```

==> vmlink maint 191
ENTER READ PASSWORD:
read
DMSVML2060I MAINT 191 linked as 0120 file mode Z

```

- b. Copy the **PROFILE XEDIT** to your **A** disk:

```

==> copy profile xedit z = = a

```

Now, **XEDIT** sessions on **TCPMAINT** will have the same configuration as on **MAINT**.

4.5.3 Configuring the FTP server

It is recommend that you turn on the FTP server. To do so, edit the newly renamed configuration file and add an **AUTOLOG** statement near the top of the file with **FTPSEVERE** as the only entry. In the **PORT** statement, remove the semicolons to uncomment the lines with **FTPSEVERE** on them (ports 20 and 21). These changes will cause the FTP server to start when TCPIP is started. The important lines before the file is edited and after are shown:

```
==> x <1nxvm52> tcpip d
```

Before:

```
; -----  
OBEY  
OPERATOR TCPMAINT MAINT MPROUTE ROUTED DHCPD REXECD SNMPD SNMPQE  
ENDOBAY  
;  
PORT  
; 20 TCP FTPSERVE NOAUTOLOG ; FTP Server  
; 21 TCP FTPSERVE ; FTP Server  
; 23 TCP INTCLIEN ; TELNET Server  
; 25 TCP SMTP ; SMTP Server  
...
```

After:

```
; -----  
OBEY  
OPERATOR TCPMAINT MAINT MPROUTE ROUTED DHCPD REXECD SNMPD SNMPQE  
ENDOBAY  
;  
AUTOLOG  
FTP SERVE 0  
ENDAUTOLOG  
  
PORT  
20 TCP FTPSERVE NOAUTOLOG ; FTP Server  
21 TCP FTPSERVE ; FTP Server  
23 TCP INTCLIEN ; TELNET Server  
; 25 TCP SMTP ; SMTP Server  
...  
====> file
```

Save your changes with the **FILE** subcommand. You could continue to configure the system, but at this time it is recommended that you test your changes by shutting down and reIPLing the system.

4.5.4 Shutting down and reIPLing the system

It is now time to shutdown and reIPL the system. You will also want to be able to shutdown and reIPL z/VM without having to access the HMC. Often, the HMC will be logged off and thus the Integrated 3270 console (SYSG) will not be available. Because of these factors it is useful to use the *System Console* (SYSC - which has a title of *Operating System Messages* on the HMC) in order to shut down z/VM and reIPL it without needing to use the console. This console is always accessible whether you are logged on to the HMC or not. z/VM messages during both the shutdown and reIPL process will be written to the system console, but often you will be able to ignore them - you just want your system back in a few minutes over the network.

Pass the parameter **IPLPARMS CONS=SYSC** to the **SHUTDOWN REIPL** command:

```
==> shutdown reipl iplparms cons=sysc
```

You will lose your session, but it should come back in a few minutes as described above. You may want to watch the system console as z/VM shuts down and comes back up. When your system is back up, perform the following commands

1. Start a 3270 session and **Logon as MAINT**. This shows that there is TCP/IP access to z/VM.

2. Query the new VSWITCH:

```
==> q vswitch
VSWITCH SYSTEM VSW1      Type: VSWITCH Connected: 0      Maxconn: INFINITE
  PERSISTENT RESTRICTED  NONROUTER                      Accounting: OFF
  VLAN Unaware
  State: Ready
  ITimeout: 5           QueueStorage: 8
  Portname: UNASSIGNED RDEV: 3004 Controller: DTCVSW1 VDEV: 3004
  Portname: UNASSIGNED RDEV: 3008 Controller: DTCVSW2 VDEV: 3008 BACKUP
```

You should see that the VSWITCH exists and that there are two built-in VSWITCH controllers, DTCVSW1 and DTCVSW2. Before z/VM 5.2, these user IDs had to be created manually.

3. Use the **QUERY VDISK** and **QUERY RETRIEVE** commands to see the changes made to the Features statement in the SYSTEM CONFIG file:

```
==> q retrieve
99 buffers available. Maximum of 255 buffers may be selected.
==> q vdisk userlim
VDISK USER LIMIT IS INFINITE
==> q vdisk syslim
VDISK SYSTEM LIMIT IS INFINITE,          0 BLK IN USE
```

This shows that the changes to the SYSTEM CONFIG file have taken effect.

4.6 Adding paging volumes

The z/VM operating system resides on the first three CP volumes (or one volume if installing onto 3390-9s). z/VM 5.2 now also installs with one full paging volume and one full spool volume. A single spool volume is probably adequate for Linux needs, however, a single paging volume is probably not.

It is recommended that you add five paging volumes so you will have a total of six (or one more 3390-9 if installing onto 3390-9s which will give the same total of 20034 cylinders). If you do not have sufficient DASD, this number can be reduced. Having adequate paging space will give you plenty of *headroom* to add more Linux virtual machines. A rule of thumb for the amount of paging space is to have twice as much as the total of all memory for all running Linux user IDs combined.

4.6.1 Formatting the paging volumes

Before adding paging volumes to the system, the DASD volumes to be used for minidisk space (PERM) and paging space (PAGE) must be formatted. Normally this is done one volume at a time via the **CPFMTXA** command. If you have just a few volumes, that is fine, but when you have many volumes to format, the process of running **CPFMTXA** can become time consuming and tedious which can lead to errors.

Therefore, a REXX EXEC named **CPFORMAT** has been provided to allow you to format many volumes with a single command. The source code for this EXEC is in the section B.1.1, “The CPFORMAT EXEC” on page 233. It is a wrapper around **CPFMTXA**. To use this EXEC, each DASD to be formatted must first be attached with the virtual device address the same real device address (using **ATTACH <realDev> ***).

Note: This EXEC will label the volumes according to the convention described in 2.2.1, “Volume labeling convention” on page 11. If you want different volume labels, you can use

the **CPFM TXA** command and manually specify each volume label, or you can modify the REXX EXEC.

Important: At this point, you will need access to the NFS server described in chapter 6, in order to get the files **CPFORMAT EXEC**. If you did not complete that chapter, do it now.

Getting the CPFORMAT EXEC to z/VM

Logoff of MAINT so you will be able to get the MAINT 191 disk in read-write mode via FTP.

Start an SSH (putty) session to the NFS server and change to the `vm/` directory which was created when you untarred the files associated with this book. Verify that the file `CPFORMAT.EXEC` exists. Note that the directory name will be one of the following two depending on the Linux distribution you are working with:

```
# cd /nfs/virt-cookbook-S10/vm    // if you are working with SLES 10
# cd /nfs/virt-cookbook-RH5/vm    // if you are working with RHEL 5
# ls CPFORMAT*
CPFORMAT.EXEC
```

Now start an FTP session to z/VM. If you get a reply from the FTP server it shows that you correctly configured it on the z/VM TCPMAINT user ID.

```
# ftp <129.40.178.120>
220-FTPSERVE IBM VM Level 520 at LAT120.PBM.IHOST.COM, 14:53:44 EST WEDNESDAY 2004-12-08
Name (129.40.178.120:root): maint
Password: maint
...
ftp> put CPFORMAT.EXEC
...
ftp> quit
```

Using the CPFORMAT EXEC

Log back into MAINT. You should now have access to the `CPFORMAT EXEC`. You can get brief help on `CPFORMAT` by using a parameter of `?`:

```
==> cpformat ?
```

Synopsis:

```
Format one or a range of DASD as page, perm, spool or temp disk space
The label written to each DASD is V<t><xxxx> where:
  <t> is type - P (page), M (perm), S (spool) or T (Temp disk)
  <xxxx> is the 4 digit address
```

Syntax is:

```
                .-PAGE-.
>>--CPFORMAT--.-rdev-----.-AS---+-PERM-+-----><
                | <-----< |      |-SPOL-|
                '-rdev1-rdev2-----'  '-TDSK-'
```

The following example shows how to attach five 3390-3 volumes and use **CPFORMAT** to format them as paging space. Refer to the planning work sheets that you filled out in 2.7.2, “z/VM DASD worksheet” on page 18:

For 3390-9 volumes: If you are installing onto 3390-9s only one more paging volume is recommended. This will give you two full volumes, or the same equivalent of six 3390-3s. For example if your z/VM system installed onto DASD at A700-A702 and you plan to put the second volume on A703, you would replace A705-A709 below with **A703**.

This will give you enough page space, but can hit performance if all paging requests go to the same volume.

Rather than using five consecutive DASD addresses, you may consider using DASD from different address ranges in an attempt to locate the paging volumes on different *ranks* in your disk array. This should enable z/VM to page more efficiently:

```
==> att <a705-a709> *
A705-A709 ATTACHED TO MAINT
==> cpformat <a705-a709> as page
```

Format the following DASD:

TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A705	MAINT	A705	3390	MPA705	A705	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A706	MAINT	A706	3390	MPA706	A706	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A707	MAINT	A707	3390	MPA707	A707	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A708	MAINT	A708	3390	MPA708	A708	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A709	MAINT	A709	3390	MPA709	A709	0	3339

WARNING - this will destroy data!

ARE YOU SURE you want to format the DASD as PAGE space (y/n)?

y

...

DASD status after:

TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A705	MAINT	A705	3390	MPA705	A705	0	3339
MAINT	A706	MAINT	A706	3390	MPA706	A706	0	3339
MAINT	A707	MAINT	A707	3390	MPA707	A707	0	3339
MAINT	A708	MAINT	A708	3390	MPA708	A708	0	3339
MAINT	A709	MAINT	A709	3390	MPA709	A709	0	3339

This formatting job should run for about 10-50 minutes depending on many factors. But don't take a break yet! You can format more volumes for PERM (minidisk) space in the next section.

4.6.2 Formatting DASD for minidisks

You could wait until **CPFORMAT** of the five paging volumes completes on MAINT, and then format more volumes for PERM or minidisk space. However, you can also get more format jobs going by using a different user ID.

1. Start a new 3270 session and **logon as SYSMOINT**. Press **Enter** when you get the VM READ prompt:

LOGON SYSMOINT

z/VM Version 5 Release 2.0, Service Level 0601 (64-bit),

```

built on IBM Virtualization Technology
There is no logmsg data
FILES:  NO RDR,  NO PRT,  NO PUN
LOGON AT 06:37:28 EDT MONDAY 11/27/06
z/VM V5.2.0    2006-07-18 08:48

```

```

DMSACP113S A(191) not attached or invalid device address
DMSACP723I D (192) R/O

```

2. Link to the MAINT 191 disk read-only to pick up the CPFORMAT EXEC. This can be done with the **VMLINK** command (**VMLINK** performs the **LINK** and **ACCESS** commands, with a read-only link and accessing the highest free file mode letter).

```

==> vmlink maint 191
DMSVML2060I MAINT 191 linked as 0192 file mode D

```

3. Attach the seven volumes that you will use for the controller user ID and the eighth that will be used for the first Linux clone. In this example it is the DASD at addresses A70A-A711. Invoke the **CPFORMAT** command against these volumes using the parameter **as perm**:

Note: For RHEL5, the example would use DASD addresses A728-A72E.

```

==> att <a70a-a711> *
A70A-A711 ATTACHED TO MAINT
==> cpformat <a70a-a711> as perm

```

Format the following DASD:

TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A70A	MAINT	A70A	3390	MMA70A	A70A	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A70B	MAINT	A70B	3390	MMA70B	A70B	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A70C	MAINT	A70C	3390	MMA70C	A70C	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A70D	MAINT	A70D	3390	MMA70D	A70D	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A70E	MAINT	A70E	3390	MMA70E	A70E	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A70F	MAINT	A70F	3390	MMA70F	A70F	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A710	MAINT	A710	3390	MMA710	A710	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A711	MAINT	A711	3390	MMA711	A711	0	3339

```

WARNING - this will destroy data!
ARE YOU SURE you want to format the DASD as PERM space (y/n)?
y

```

...

DASD status after:

TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A70A	MAINT	A70A	3390	MMA70A	A70A	0	3339
MAINT	A70B	MAINT	A70B	3390	MMA70B	A70B	0	3339
MAINT	A70C	MAINT	A70C	3390	MMA70C	A70C	0	3339
MAINT	A70D	MAINT	A70D	3390	MMA70D	A70D	0	3339
MAINT	A70E	MAINT	A70E	3390	MMA70E	A70E	0	3339
MAINT	A70F	MAINT	A70F	3390	MMA70F	A70F	0	3339
MAINT	A710	MAINT	A710	3390	MMA710	A710	0	3339
MAINT	A711	MAINT	A711	3390	MMA711	A711	0	3339

Now you can take a break! You should now have page volumes being formatted on MAINT and PERM or minidisk volumes being formatted on SYSMaint.

When completed, you should have eight newly formatted volumes that can be used as minidisks.

4.6.3 Updating the SYSTEM CONFIG file

Follow these steps to update the SYSTEM CONFIG file:

1. Now that the PAGE and PERM volumes are ready for use, they must be added to the SYSTEM CONFIG file so z/VM knows about them. The following example uses the same steps to access the MAINT CF1 disk read-write that you used earlier:

```
==> q cpdisk
Label  Userid  Vdev Mode Stat Vol-ID Rdev Type  StartLoc  EndLoc
MNTCF1 MAINT   OCF1  A   R/O  520RES 0200 CKD      39       83
MNTCF2 MAINT   OCF2  B   R/O  520RES 0200 CKD      84      128
MNTCF3 MAINT   OCF3  C   R/O  520RES 0200 CKD     129      188
==> cprel a
CPRELEASE request for disk A scheduled.
HCPZAC6730I CPRELEASE request for disk A completed.
==> link * cf1 cf1 mr
==> acc cf1 f
```

It is good to remember this sequence of steps.

2. Edit the SYSTEM CONFIG file and specify each of the new page volumes (PAGE) by name as CP_Owned. When you system IPLs it will pick up these as paging volumes.

```
==> x system config f
...
/*****
/*                                CP_Owned Volume Statements                                */
/*****

    CP_Owned  Slot   1  520RES
    CP_Owned  Slot   2  520W01
    CP_Owned  Slot   3  520W02
    CP_Owned  Slot   4  520SPL
    CP_Owned  Slot   5  520PAG
    CP_Owned  Slot   6  <MPA705>
    CP_Owned  Slot   7  <MPA706>
    CP_Owned  Slot   8  <MPA707>
    CP_Owned  Slot   9  <MPA708>
    CP_Owned  Slot  10  <MPA709>
    CP_Owned  Slot  11  RESERVED
    CP_Owned  Slot  12  RESERVED
    CP_Owned  Slot  13  RESERVED
...

```

3. Move down to the User_Volume_List section. User volumes (PERM) can be specified individually with the User_Volume_List statement, or with wild cards via the User_Volume_Include statement. If you are using the labelling convention enforced by the CPFORMAT EXEC, then add the following single line to include all PERM space as volume labels all begin with "MM" (the labeling convention used by the CPFORMAT EXEC):

```

/*****
/*                                User_Volume_List                                */
/* These statements are not active at the present time. They are                */
/* examples, and can be activated by removing the comment delimiters            */
/*****

User_Volume_Include MM*
/* User_Volume_List USRP01 */
/* User_Volume_List USRP02 */

```

...

4. Save your changes with the **FILE** subcommand. Verify the integrity of the changes with the **CPSYNTAX** command then put the MAINT CF1 disk back online. The following example shows how you did this previously:

```
==> acc 193 g
==> cpsyntax system config f
CONFIGURATION FILE PROCESSING COMPLETE -- NO ERRORS ENCOUNTERED.
==> rel f (det
DASD OCF1 DETACHED
==> cpacc * cf1 a
CPACCESS request for mode A scheduled.
HCPZAC6732I CPACCESS request for MAINT's OCF1 in mode A completed.
==> q cpdisk
```

Label	Userid	Vdev	Mode	Stat	Vol-ID	Rdev	Type	StartLoc	EndLoc
MNTCF1	MAINT	OCF1	A	R/O	520RES	0200	CKD	39	83
MNTCF2	MAINT	OCF2	B	R/O	520RES	0200	CKD	84	128
MNTCF3	MAINT	OCF3	C	R/O	520RES	0200	CKD	129	188

4.6.4 Testing the changes

It is recommended that you again shutdown and relPL to test the changes. Before you shut down, note that you have only one page volume (520PAG) via the **QUERY ALLOC PAGE** command. Your output should look similar to the following:

```
==> q alloc page
```

EXTENT	EXTENT	TOTAL	PAGES	HIGH	%		
VOLID	RDEV	START	END	PAGES	IN USE	PAGE	USED
520PAG	A702	1	3338	600840	12	12	1%
				-----	-----	-----	
SUMMARY				601020	12		1%
USABLE				601020	12		1%

Now shut the system down again with the command **SHUTDOWN REIPL IPLPARMS CONS=SYSC**. This is analogous to the Linux **reboot** command in that the system attempts to come back up after it shuts down. If you are connected via a 3270 emulator, you will lose your session, but if all goes well, your system will be available again in a couple of minutes.

```
==> shutdown reipl iplparms cons=sysc
```

After the system comes back, **logon as MAINT** and look at the page space again. If you are using 3390-3s, you should see output similar to the following:

```
==> q alloc page
```

EXTENT	EXTENT	TOTAL	PAGES	HIGH	%		
VOLID	RDEV	START	END	PAGES	IN USE	PAGE	USED
520PAG	A702	1	3338	600840	0	0	0%
MPA705	A705	0	3338	601020	0	0	0%
MPA706	A706	0	3338	601020	0	0	0%
MPA707	A707	0	3338	601020	0	0	0%
MPA708	A708	0	3338	601020	0	0	0%
MPA709	A709	0	3338	601020	12	12	1%
				-----	-----	-----	
SUMMARY				3521K	12		1%
USABLE				3521K	12		1%

The output shows there are six paging volumes constituting 3521 KB pages, or about 14 GB of page space (there are 4KB/page).

4.7 Creating a user ID for common files

Now it is time to define your first z/VM user ID, LNXMAINT. It will be used to store files that will be shared by Linux user IDs. Before starting, make a copy of the original USER DIRECT file:

```
==> copy user direct c = direorig = (oldd
```

4.7.1 Define the user in the USER DIRECT file

A small 20 cylinder minidisk is allocated at virtual address 191 and a larger 300 cylinder minidisk (approximately 225MB), to be shared by many guests, is defined at virtual address 192. Use the next free DASD designated as PERM space on your worksheet (2.7.2, “z/VM DASD worksheet” on page 18). Cylinder 0 should always be reserved for the label therefore you should start minidisks at cylinder 1.

1. Edit the USER DIRECT file and add the following user ID definition to the bottom of the file:

Note: For RHEL5, the example would use DASD volume MMA72A, not MMA70C.

```
==> x user direct c
====> bottom
====> a 6
...
USER LNXMAINT LNXMAINT 64M 128M BEG
INCLUDE TCPMSU
LINK TCPMAINT 592 592 RR
MDISK 0191 3390 0001 0020 <MMA70C> MR READ WRITE MULTIPLE
MDISK 0192 3390 0021 0300 <MMA70C> MR ALL WRITE MULTIPLE
*
...
====> file
```

Note the following points for the numbers in black:

- 1** User ID LNXMAINT, same password, default size of 64MB, with class B, E and G privileges
- 2** Include the profile named TCPMSU (defined earlier in the USER DIRECT file)
- 3** Link to the TCPMAINT 592 disk read-only for access to FTP and other TCP/IP commands
- 4** Define a 191 minidisk of size 20 cylinders from volume MMA70C
- 5** Define 192 minidisk of size 300 cylinders (approximately 225MB) from volume MMA70C with the special read password of ALL which allows read access from any user ID without a disk password
- 6** An empty comment line for better readability.

2. Whenever an MDISK statement is added or modified in the USER DIRECT file you should always check for overlapping cylinders and gaps (gaps will only leave empty disk space, however z/VM will allow you to *shoot yourself in the foot* by defining multiple minidisks over the same disk space). This is done with the **DISKMAP** command:

```
==> diskmap user
```

The minidisks with the END option specified in this directory will not be included in the following DISKMAP file.

File USER DISKMAP A has been created.

3. The file created, USER DISKMAP, contains a mapping of all minidisk volumes defined in the USER DIRECT file. It will list any overlaps or gaps found on the volumes. Edit the file and turn off the prefix area with the **XEDIT PREFIX OFF** subcommand to view 80 columns:

```
==> x user diskmap
====> prefix off
```

4. Search for the text **overlap** with the / subcommand:

```
====> /overlap
```

You should see the error message: DMSXDC546E Target not found. This means that no minidisks are overlapping each other.

Now search for gaps. You should also see some gaps:

```
====> /gap
```

```
-----
VOLUME  USERID      CUU  DEVTYPE   START      END      SIZE      GAP
              0        500      501
$$$$$$  DATAMOVE    5F0    3380     00501     00501     00001
          DATAMOVE    5FF    3380     00502     00502     00001
-----
```

```
-----
VOLUME  USERID      CUU  DEVTYPE   START      END      SIZE      GAP
              0        0        1
MMA70C  LNXMAINT    0191   3390     00001     00020     00020
          LNXMAINT    0192   3390     00021     00320     00300
...

```

The two GAPS should be listed on the right side: a gap of 501 cylinders on the \$\$\$\$\$\$ volume and a new gap of 1 cylinder exists on the volume that was just used to create disk space for the LNXMAINT user ID; in this case the MMA70C volume.

Don't worry about the 501 cylinder gap, but to avoid a 1 cylinder gap being reported on each user volume, it is recommended to use the user ID \$ALLOC\$. This user is set to NOLOG which means it can never be logged onto. Thus it is not a conventional user ID, rather, it is a convenient place to put dummy minidisk definitions for cylinder 0 of all PERM volumes.

Look at the rest of the file. You should see the three volumes that z/VM installs onto are already there (520RES, 520W01, 520W02).

5. Get out of the file USER DISKMAP with the **QUIT** command or by pressing **F3**.
6. Edit the USER DIRECT file again and add a new minidisk definition:

```
==> x user direct
====> /user $alloc
USER $ALLOC$ NOLOG
MDISK A01 3390 000 001 520RES R
MDISK A02 3390 000 001 520W01 R
MDISK A03 3390 000 001 520W02 R
MDISK A04 3390 000 001 <MMA70C> R
```

7. Save your changes and run **DISKMAP** again. Edit the USER DISKMAP file. This time you should see just the single 501 cylinder gap and cylinder 0 of the first user volume allocated to the \$ALLOC\$ user ID. When you are done you can quit without saving changes by pressing **F3**.

```
==> diskmap user
==> x user diskmap
====> prefix off
====> /$ALLOC
...
VOLUME  USERID      CUU  DEVTYPE   START      END      SIZE
MMA70C  $ALLOC$      A04    3390     00000     00000     00001
          LNXMAINT    0191   3390     00001     00020     00020
          LNXMAINT    0192   3390     00021     00320     00300
...

```

====> F3

8. Now that you are sure the minidisk layout is correct, the changes to the USER DIRECT file can be brought online via the **DIRECTXA** command:

```
==> directxa user
z/VM USER DIRECTORY CREATION PROGRAM - VERSION 5 RELEASE 2.0
EOJ DIRECTORY UPDATED AND ON LINE
HCPDIR494I User directory occupies 39 disk pages
```

If the **DIRECTXA** command fails, you must correct the problem before proceeding.

You have now defined your first z/VM user ID named LNXMAINT.

4.7.2 Logging and customizing the new user ID

Now you should be able to logon to the new user ID and format its two minidisks.

1. **Logoff of MAINT and logon to LNXMAINT.**

```
LOGON LNXMAINT
z/VM Version 5 Release 2.0, Service Level 0601 (64-bit),
built on IBM Virtualization Technology
There is no logmsg data
FILES: 0003 RDR, NO PRT, NO PUN
LOGON AT 05:41:34 EST THURSDAY 01/04/07
z/VM V5.2.0 2006-07-18 08:48
```

DMSACP112S A(191) **device error**

You should see an error message ending in “device error”. When CMS is started, it tries to access the user’s 191 minidisk as file mode A. The 191 minidisk has been defined to this user ID, however, it has never been formatted as a CMS file system.

2. To format this disk for CMS use the **FORMAT** command. It requires a parameter specifying the file mode to access the disk as, mode **A** in the following example:

```
==> format 191 a
DMSFOR603R FORMAT will erase all files on disk A(191). Do you wish to continue?
Enter 1 (YES) or 0 (NO).
1
DMSFOR605R Enter disk label:
1xm191
DMSFOR733I Formatting disk A
DMSFOR732I 20 cylinders formatted on A(191)
```

3. Format the larger 192 disk as the D minidisk which should take a minute or two:

```
==> format 192 d
DMSFOR603R FORMAT will erase all files on disk D(192). Do you wish to continue?
Enter 1 (YES) or 0 (NO).
1
DMSFOR605R Enter disk label:
1xm192
DMSFOR733I Formatting disk D
DMSFOR732I 300 cylinders formatted on D(192)
```

You have now formatted the two minidisks and accessed them as file modes A and D.

4.7.3 Copying a PROFILE XEDIT

Copy the PROFILE XEDIT from the MAINT 191 disk so XEDIT sessions will have a common interface among user IDs.

1. Use the **VMLINK** command to both link to the disk read-only and to access it as the highest available file mode. The default read password is **read**:

```
==> vmlink maint 191
ENTER READ PASSWORD:
==> read
DMSVML2060I MAINT 191 linked as 0120 file mode Z
```

2. Copy the **PROFILE XEDIT** to your A disk:

```
==> copy profile xedit z = = a
```

4.7.4 Creating a PROFILE EXEC

Create a simple **PROFILE EXEC** that will be run each time this user ID is logged on.

1. Create the new file and add the following lines. REXX EXECs must always begin with a C language-style comment.

```
==> x profile exec a
====> a 5
/* PROFILE EXEC */
'acc 592 e'
'cp set run on'
'cp set pf11 retrieve forward'
'cp set pf12 retrieve'
====> file
```

This **PROFILE EXEC** access the **TCPMAINT 592** disk as file mode **E**, sets **CP** run on, and sets the retrieve keys per the convention.

2. You could test your changes by logging off and logging back on. However, typing the command **PROFILE** will do the same. By default CMS tries to access the 191 disk as **A** and the 192 disk as **D**. Also you should have the **TCPMAINT 592** disk accessed as **E**. To see your minidisks, use the **QUERY DISK** command:

```
==> profile
DMSACP723I E (592) R/O
==> q disk
```

LABEL	VDEV	M	STAT	CYL	TYPE	BLKSZ	FILES	BLKS USED-(%)	BLKS LEFT	BLK TOTAL
LXM191	191	A	R/W	20	3390	4096	2	9-01	3591	3600
LXM192	192	D	R/W	300	3390	4096	0	11-00	53989	54000
TCM592	592	E	R/O	67	3390	4096	877	8167-68	3893	12060
MNT190	190	S	R/O	100	3390	4096	689	14325-80	3675	18000
MNT19E	19E	Y/S	R/O	250	3390	4096	1010	26665-59	18335	45000
MNT191	120	Z	R/O	175	3390	4096	36	224-01	31276	31500

3. Verify that your **F11** and **F12** keys are set to the **RETRIEVE** command:

```
==> q pf11
PF11 RETRIEVE FORWARD
==> q pf12
PF12 RETRIEVE BACKWARD
```

4.7.5 Copying files associated with this book to LNXMAINT

The **z/VM** files associated with this book are in the **vm/** subdirectory of the **NFS** server you set up earlier. These files should be stored on the larger 192 disk which is accessed as your **D** disk. **Log off of LNXMAINT** so that the 192 disk can be accessed read-write.

Start an SSH session on the NFS server and change directory to the **VM** files associated with this book. Note that the directory name will be one of the following two depending on the distribution you are working with:

```
# cd /nfs/virt-cookbook-S10/vm // if you are working with SLES 10
# cd /nfs/virt-cookbook-RH5/vm // if you are working with RHEL 5
```

FTP to z/VM. By default FTP copies files to your 191 disk, so first change directory to the LNXMAINT 192 disk. Then use the **mput *** subcommand to copy all the files from the vm/ subdirectory to LNXMAINT. The files are all in ASCII so the default transfer type of ASCII will cause the files to be converted to EBCDIC.

```
# ftp <129.40.178.120>
220-FTPSERVE IBM VM Level 520 at LAT120.PBM.IHOST.COM, 15:20:32 EDT THURSDAY 2006-11-23
220 Connection will close if idle for more than 5 minutes.
User (129.40.178.120:(none)): lnxmaint
331 Send password please.
Password:
230 LNXMAINT logged in; working directory = LNXMAINT 191
ftp> cd lnxmaint.192
250 Working directory is LNXMAINT 192
ftp> prompt
Interactive mode off
ftp> mput *
...
ftp> quit
```

Logon to LNXMAINT. You should see the following files on your D disk:

```
==> filel * * d
LNXMAINT FILELIST A0 V 169 Trunc=169 Size=8 Line=1 Col=1 Alt=0
Cmd  Filename Filetype Fm Format Lrecl  Records  Blocks  Date  Time
    CHPW52  XEDIT    D1 V      70      180      3 1/04/07 5:50:42
    CPFORMAT EXEC      D1 V      79      231      3 1/04/07 5:50:42
    LABEL520 EXEC      D1 V      75      108      2 1/04/07 5:50:42
    LABEL520 XEDIT    D1 V      71       41      1 1/04/07 5:50:42
    LBL520-9 EXEC      D1 V      75       99      1 1/04/07 5:50:42
    LBL520-9 XEDIT    D1 V      71       43      1 1/04/07 5:50:42
    PROFILE  EXEC      D1 V      63       26      1 1/04/07 5:50:42
    RHEL5    CONF-RH5 D1 V      38       13      1 1/04/07 5:50:42
    RHEL5    EXEC      D1 V      67        9      1 1/04/07 5:50:42
    RHEL5    PARM-RH5 D1 V      80        3      1 1/04/07 5:50:42
    SLES10   EXEC      D1 V      68        9      1 1/04/07 5:50:42
    SLES10   PARM-S10 D1 V      65        9      1 1/04/07 5:50:42
    SLES9X   EXEC      D1 V      74        9      1 1/04/07 5:50:42
    SLES9X   PARMFILE D1 V      73        8      1 1/04/07 5:50:42
    SWAPGEN  EXEC      D1 V      72      358      5 1/04/07 5:50:42
```

4.8 Customizing system startup and shutdown

When your z/VM system is IPLed, it is often desirable to have important Linux systems also start. Conversely, when you shut down z/VM, it is desirable to have all Linux systems shut down first.

4.8.1 Configuring the AUTOLOG1 PROFILE EXEC

It is recommended that the following tasks be accomplished by using AUTOLOG1's **PROFILE EXEC**.

- ▶ Configure Linux to shut down gracefully via the **SET SIGNAL** command
- ▶ Overcommit memory via the **SET SRM STORBUF** command
- ▶ Grant access to the VSWITCH for each Linux user
- ▶ Start user IDs that should be started via the **XAUTOLOG** command

- Limit minidisk cache in central storage and turn it off in expanded storage

1. **Logoff of LNXMAINT and logon to AUTOLOG1.** At the VM READ prompt you have usually been pressing Enter which causes the PROFILE EXEC to be run. If you do not want this EXEC to run, enter the command **ACCESS (NOPROF)**:

```
LOGON AUTOLOG1
z/VM Version 5 Release 2.0, Service Level 0501 (64-bit),
built on IBM Virtualization Technology
There is no logmsg data
FILES: NO RDR, NO PRT, NO PUN
LOGON AT 13:39:10 EST WEDNESDAY 01/18/06
DMSIND2015W Unable to access the Y-disk. Filemode Y (19E) not accessed
z/VM V5.2.0 2005-12-22 09:36
==> acc (noprof
```

2. Make a copy of the working **PROFILE EXEC**

```
==> copy profile exec a = execwrks =
```

3. Edit the file and add the emboldened text.

```
==> x profile exec
/*****/
/* Autolog1 Profile Exec */
/*****/
'cp xautolog tcpip' /* start up TCPIP */
'CP XAUTOLOG DTCVSW1' /* start VSWITCH controller 1 */
'CP XAUTOLOG DTCVSW2' /* start VSWITCH controller 2 */
'cp set pf12 ret' /* set the retrieve key */
'cp set mdc stor 0m 128m' /* Limit minidisk cache in CSTOR */
'cp set mdc xstore 0m 0m' /* Disable minidisk cache in XSTOR */
'cp set srm storbuf 300% 250% 200%' /* Overcommit memory */
'cp set signal shutdown 180' /* Allow guests 3 min to shut down */

/* Grant access to VSWITCH for each Linux user */

/* XAUTOLOG each Linux user that should be started */

'cp logoff' /* logoff when done */
```

Save your changes with the **FILE** subcommand.

Important: The **set mdc** and **set srm** lines are z/VM tuning values. It is believed that these are good starts for Linux systems, but may not be optimal. For more reading on these values see the following Web sites:

<http://www.vm.ibm.com/perf/tips/linuxper.html>
<http://www.vm.ibm.com/perf/tips/prgmdcar.html>
<http://www.zjournal.com/PDF/robinson.pdf>

You may choose to modify or omit some of these settings. Your system should now be configured to start up and send a signal to shut down Linux user IDs.

4.8.2 Testing the changes

To test your changes you must reIPL z/VM again. Perform the following steps:

1. Shutdown and reIPL your system.


```
==> shutdown reipl ipparms cons=sysc
SYSTEM SHUTDOWN STARTED
```

2. When your system comes back **logon as MAINT**.
3. Use the **QUERY NAMES** command to see that TCP/IP, the FTP server and the two VSWITCH controllers have been logged on:

```
==> q n
FTPSEIVE - DSC , DTCVSW2 - DSC , DTCVSW1 - DSC , TCPIP - DSC
OPERSYMP - DSC , DISKACNT - DSC , EREP - DSC , OPERATOR - DSC
MAINT -L0004
VSM - TCPIP
```

4. Query the SRM values to see that the new STORBUF settings is in effect and the SIGNAL SHUTDOWN value is set to 180 seconds:

```
==> q srm
IABIAS : INTENSITY=90%; DURATION=2
LDUBUF : Q1=100% Q2=75% Q3=60%
STORBUF: Q1=300% Q2=250% Q3=200%
DSPBUF : Q1=32767 Q2=32767 Q3=32767
...
==> q signal shutdown
System default shutdown signal timeout: 180 seconds
```

This output shows that your changes have taken effect.

4.9 Addressing z/VM security issues

This section briefly discusses the following security issues.

- ▶ z/VM security products
- ▶ High level z/VM security
- ▶ Linux user ID privilege classes
- ▶ z/VM user ID and minidisk passwords

VM security products

You might want to use a z/VM security product such as IBM RACF or Computer Associates VM:Secure. They allow you to address more security issues such as password aging and the auditing of users/ access attempts.

High level z/VM security

The paper *z/VM Security and Integrity* by Cliff Laking and Alan Altmark discusses the isolation and integrity of virtual servers under z/VM. It is on the Web at:

<http://www-1.ibm.com/servers/eserver/zseries/library/techpapers/pdf/gm130145.pdf>

Linux user ID privilege classes

Another security issue is the privilege class that Linux user IDs are assigned. The IBM redpaper *Running Linux Guests with less than CP Class G Privilege* by Rob van der Heij addresses this issue. It is on the Web at:

<http://www.redbooks.ibm.com/redpapers/pdfs/redp3870.pdf>

z/VM user ID and minidisk passwords

All passwords in a vanilla z/VM system are the same as the user ID. This is a large security hole. The *minimum* you should do is to address this issue.

There are two types of passwords in the USER DIRECT file:

User IDs	The password required to logon with
Minidisks	Separate passwords for read access, write access and multi-write access

Both types of passwords should be modified. This can be done using the CHPW52 XEDIT macro defined in the next section.

4.9.1 Changing passwords in USER DIRECT

Changing the passwords can be done manually in **XEDIT**. However, this is both tedious and error-prone. So a profile named CHPW52 XEDIT has been included with this book. The source code is in Appendix B.1.2, “The CHPW52 XEDIT macro” on page 237.

This macro will change all z/VM passwords to the same value, which may still not be adequate security given the different function of the various user IDs. If you want different passwords, you have to modify the USER DIRECT file manually, either with or without using the CHPW52 XEDIT macro.

To modify all user ID and minidisk passwords to the same value, perform the following steps.

1. Logon to MAINT.

2. Link and access the LNXMAINT 192 disk to pick up the CHPW52 EXEC:

```
==> vmlink lnxmaint 192
DMSVML2060I LNXMAINT 192 linked as 0120 file mode Z
```

3. Make a backup copy of the USER DIRECT file and first be sure the password that you want to use is not a string in the file. For example if you want to change all passwords to lnx4vm, then do the following:

```
==> copy user direct c = direwrks = (oldd
==> x user direct c
====> /lnx4vm
DMSXDC546E Target not found
====> quit
```

The Target not found message shows that the string LNX4VM is not used in the USER DIRECT file, so it is a good candidate for a password.

4. Edit the USER DIRECT file with a parameter of (profile chpw52) followed by the new password. Rather than invoking the default profile of PROFILE XEDIT, this command will invoke the XEDIT macro named CHPW52 XEDIT and pass it the new password. For example, to change all passwords to lnx4vm, enter the following command:

```
==> x user direct c (profile chpw52) lnx4vm
```

Changing all passwords to: LNX4VM

```
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
...
```

5. When the profile finishes you are left in the XEDIT session with all passwords modified. You may wish to first examine the changes. Then save the changes with the FILE subcommand:

```
====> file
```

6. Bring the changes online with the DIRECTXA command:

```
==> directxa user
z/VM USER DIRECTORY CREATION PROGRAM - VERSION 5 RELEASE 2.0
EOJ DIRECTORY UPDATED AND ON LINE
```

HCPDIR494I User directory occupies 39 disk pages

Your new directory is online. Do not forget the new password!

Note that this **XEDIT** macro will only work on a vanilla **USER DIRECT** file because it searches for the original user IDs next to passwords. If you want to change your password again, it should be much easier as you can use the **XEDIT CHANGE** subcommand. For example to change all passwords from **lnx4vm** to **vm51nx**, invoke the following commands:

```
==> x user direct c
====> c/lnx4vm/vm51nx/* *
DMSXCG517I 773 occurrence(s) changed on 328 line(s)
```

Congratulations, your z/VM system is now customized and ready for Linux. It is recommended that you back up your system to tape.

4.10 Backing up your z/VM system to tape

Your system is now customized with a running TCP/IP stack, a highly available VSWITCH, a startup and shutdown process and with a user ID for shared files. You have changed the passwords. This would be a good time to back up the system to tape.

There are five system volumes that should be backed up **520RES**, **520W01**, **520W02**, **520SPL** and **520PAG** (or just the first three if you are using 3390-9s) You also have configured a sixth volume that is important to Linux: that is the first 320 cylinders of the volume with **LNXMaint** on it. Back up that entire volume, because the remainder of it will be used for Linux backup data also.

To backup these volumes to tape, refer to chapter 8. *Load the System Image*, Step 11. *Store a Backup Copy of the z/VM System on Tape* in the manual *The z/VM Guide for Automated Installation and Service*, GC204-6099.

4.11 Relabeling the system volumes

This step is optional, however, it is recommended. There are times when you will want to change the volume labels of the five z/VM system volumes (or three if you installed onto 3390-3s). If there is a possibility that another vanilla z/VM system with the same labels is installed onto volumes accessible by your z/VM system, one of the systems will not IPL correctly.

When installing z/VM it is possible to modify all but one volume label, that of the **520RES** volume. This alleviates the problem that is described next, but it does not alleviate the problem of duplicate volume names.

To understand this possibility, refer to Figure 4-9 on page 62. The z/VM system with the lower device addresses starting at **E340** should IPL fine (though you may see a warning at system startup time about duplicate volume labels). However, if the z/VM system starting at device address **F000** is IPLed, the **520RES** volume will be used, but the remaining volumes in the system are searched for by volume label, not by device address. Because z/VM system 1's addresses are lower than z/VM system 2's, system 2 will be using system 1's volumes. This is not good for either system!




Figure 4-9 The problem with two z/VM systems with identical volume labels

If there is a possibility of another z/VM system being installed on DASD that this system will have access to, it is recommended that you perform the following steps. You will need access to the HMC to perform them:

- ▶ “Modifying labels in the SYSTEM CONFIG file” on page 62
- ▶ “Modifying labels in the USER DIRECT file” on page 64
- ▶ “Changing the labels on the five volumes” on page 65
- ▶ “Shutting down your system and restarting it” on page 66

Important: This process must be done as documented. Making a mistake in one of the steps can easily result in an unusable system. Check your steps carefully and your system will come back with no problems. Try to do all steps in succession in a short amount of time. Close your door, don’t answer your phone or e-mail, turn off instant messaging :))

4.11.1 Modifying labels in the SYSTEM CONFIG file

An HMC 3270 session is needed because z/VM will have to be restarted with a FORCE option.

1. Start an **Integrated 3270 Console** session on the HMC from the *CPC Recovery* (or just *Recovery*) menu.
2. If you have not already done so, **Logon to MAINT** and link and access the LNXMAINT 192 disk to pick up the LABEL520 EXEC and XEDIT macro:

```
==> vmlink lnxmaint 192
DMSVML2060I LNXMAINT 192 linked as 0120 file mode Z
```

3. Note the first five CP-owned volumes via the **QUERY CPOWNED** command:

```
==> q cpowned
Slot Vol-ID Rdev Type Status
  1 520RES A700 Own Online and attached
  2 520SPL A701 Own Online and attached
  3 520PAG A702 Own Online and attached
  4 520W01 A703 Own Online and attached
  5 520W02 A704 Own Online and attached
  6 MPA705 A705 Own Online and attached
  7 MPA706 A706 Own Online and attached
  8 MPA707 A707 Own Online and attached
  9 MPA708 A708 Own Online and attached
 10 MPA709 A709 Own Online and attached
 11 ----- Reserved
 12 ----- Reserved
...
```

For 3390-9s: If z/VM is installed onto 3390-9s, there should only be three system volumes:

```
==> q cpowned
Slot Vol-ID Rdev Type Status
  1 520RES 9300 Own Online and attached
  2 520SPL 9301 Own Online and attached
  3 520PAG 9302 Own Online and attached
...
```

4. The labeling convention described in 2.2.1, "Volume labeling convention" on page 11 suggests using 'M' in the second character of the label. An **XEDIT** macro, LABEL520 XEDIT, is supplied to help make this process more reliable. It can be used on both the SYSTEM CONFIG and USER DIRECT files. To modify the labels in the SYSTEM CONFIG file, release the A CP-disk and access it read-write. Back up the SYSTEM CONFIG file:

```
==> cprel a
CPRELEASE request for disk A scheduled.
HCPZAC6730I CPRELEASE request for disk A completed.
==> link * cfl cfl mr
==> acc cfl f
==> copy system config f = confwrks = (oldd rep
```

5. Edit the SYSTEM CONFIG file with the LABEL520 XEDIT macro passing the five addresses of the z/VM system volumes (a700-a704 in this example):

```
==> x system config f (profile label520) <a700> <a701> <a702> <a703> <a704>
DMSXCG517I 3 occurrence(s) changed on 3 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
```

For 3390-9s: If z/VM is installed onto 3390-9s, there is a macro named **LBL520-9 XEDIT** that takes only three parameters. For example, if the system volumes are 9300-9302, the command to edit the SYSTEM CONFIG file would be as follows:

```
==> x system config f (profile lbl520-9) <9300> <9301> <9302>
DMSXCG517I 3 occurrence(s) changed on 3 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)
```

6. Clear the screen and you will be left in XEDIT editing the file. Search for the string cp_owned and you should see the new labels. Be sure they are correct before saving the file with the **FILE** subcommand:

```
====> /cp_owned
/*                      CP_Owned Volume Statements                      */
/*****
CP_Owned Slot 1 MVA700
CP_Owned Slot 2 MVA701
CP_Owned Slot 3 MVA702
CP_Owned Slot 4 MVA703
CP_Owned Slot 5 MVA704
CP_Owned Slot 6 MPA705
```

```

CP_Owned Slot 7 MPA706
CP_Owned Slot 8 MPA707
CP_Owned Slot 9 MPA708
CP_Owned Slot 10 MPA709
CP_Owned Slot 11 RESERVED
...
====> file

```

7. Verify there are no syntax errors:

```

==> acc 193 g
==> cpsyntax system config f
CONFIGURATION FILE PROCESSING COMPLETE -- NO ERRORS ENCOUNTERED.

```

8. Release and detach the F disk, CPACCESS the A disk and verify:

```

==> rel f (det
DASD OCF1 DETACHED
==> cpacc * cfl a
CPACCESS request for mode A scheduled.
Ready; T=0.01/0.01 09:19:57
HCPZAC6732I CPACCESS request for MAINT's OCF1 in mode A completed.
==> q cpdisk
Label Userid Vdev Mode Stat Vol-ID Rdev Type StartLoc EndLoc
MNTCF1 MAINT OCF1 A R/O 520RES A700 CKD 39 83
MNTCF2 MAINT OCF2 B R/O 520RES A700 CKD 84 128
MNTCF3 MAINT OCF3 C R/O 520RES A700 CKD 129 188

```

You have now changed the labels of the system volumes in the SYSTEM CONFIG file. It is critical that you proceed as your system is now in a state where it will not IPL cleanly.

4.11.2 Modifying labels in the USER DIRECT file

In this section you will modify the system volume labels in the USER DIRECT file.

1. Modify the USER DIRECT file again using the LABEL520 XEDIT macro. You should see many more occurrences of the labels being changed:

```

==> copy user direct c = direwrks = (oldd rep
==> x user direct c (profile label520) <a700> <a701> <a702> <a703> <a704>
DMSXCG517I 84 occurrence(s) changed on 84 line(s)
DMSXCG517I 134 occurrence(s) changed on 134 line(s)
DMSXCG517I 69 occurrence(s) changed on 69 line(s)
DMSXCG517I 2 occurrence(s) changed on 2 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)

```

For 3390-9s: Again the macro named LBL520-9 XEDIT should be used for systems installed onto 3390-9s. For example, if the system volumes are 9300-9302, the command to edit the SYSTEM CONFIG file would be as follows:

```

==> x user direct c (profile lb1520-9) <9300> <9301> <9302>
DMSXCG517I 283 occurrence(s) changed on 283 line(s)
DMSXCG517I 2 occurrence(s) changed on 2 line(s)
DMSXCG517I 1 occurrence(s) changed on 1 line(s)

```

You may choose to traverse the file before saving the changes with the FILE subcommand:

```

====> file

```

You have now changed the labels of the system volumes in the USER DIRECT and SYSTEM CONFIG files. Again, it is critical that you proceed with the remaining steps.

4.11.3 Changing the labels on the five volumes

In this section you will change the labels on the 5 volumes via the **CPFMTXA** command. You could do this one volume at a time with the **CPFMTXA LABEL** command. However, the **LABEL520 EXEC** has been written to make this step easier.

1. Use LABEL520 with the physical addresses of the 5 system volumes:

```
==> label520 <a700> <a701> <a702> <a703> <a704>
The volumes are:
DASD A700 CP OWNED 520RES 50
DASD A701 CP OWNED 520SPL 1
DASD A702 CP OWNED 520PAG 0
DASD A703 CP OWNED 520W01 93
DASD A704 CP OWNED 520W02 1

The system volume labels will become:
MVA700 MVA701 MVA702 MVA703 MVA704

ARE YOU SURE you want to relabel the DASD (y/n)?
y
HCPCCF6209I INVOKING ICKDSF.
...
ICK03000I CPVOL REPORT FOR 0123 FOLLOWS:

          VOLUME SERIAL NUMBER IS NOW = MVA700
...
VOLUME SERIAL NUMBER IS NOW = MVA701
...
VOLUME SERIAL NUMBER IS NOW = MVA702
...
VOLUME SERIAL NUMBER IS NOW = MVA703
...
VOLUME SERIAL NUMBER IS NOW = MVA704
...
ICK00002I ICKDSF PROCESSING COMPLETE. MAXIMUM CONDITION CODE WAS 0
DASD OA03 DETACHED
```

For 3390-9s: The **LBL520-9 EXEC** should be used for systems installed onto 3390-9s. For example, if the system volumes are 9300-9302, the command to relabel the system volumes would be as follows:

```
==> lb1520-9 <9300> <9301> <9302>
The volumes are:
DASD 9300 CP OWNED 520RES 142
DASD 9301 CP OWNED 520SPL 2
DASD 9302 CP OWNED 520PAG 0

The system volume labels will become:
MV9300 MV9301 MV9302

ARE YOU SURE you want to relabel the DASD (y/n)?
y
...
```

2. Now that the five volumes have been relabeled (sometimes called *clipping the volumes*), you can run the **DIRECTXA** command to update the directory:

```
==> directxa user
z/VM USER DIRECTORY CREATION PROGRAM - VERSION 5 RELEASE 2.0
EOJ DIRECTORY UPDATED
HCPDIR494I User directory occupies 41 disk pages
Ready(00005); T=0.01/0.01 14:30:37
```

A return code of 5 is expected because the labels in the USER DIRECT file are different from the spool data in the currently running system.

Finally, you are ready to issue a **SHUTDOWN** command.

4.11.4 Shutting down your system and restarting it

You will need an HMC console session for this step, if you are not already running from there.

To test the changes you must shut your system down and then restart it. You cannot do a SHUTDOWN REIPL in this situation because you will have to do a **FORCE** start

```
==> shutdown
SYSTEM SHUTDOWN STARTED
HCPSHU960I System shutdown may be delayed for up to 210 seconds
```

Perform the following steps to bring the system back up:

1. From the HMC click the **LOAD** icon in the *CPC Recovery* (or just *Recovery*) menu.
2. Select the **Clear** radio button. All the other parameters should be correct from the previous IPL. Click **OK**
3. Click **Yes** on the *Load Task Confirmation* panel.
4. Go back to the Integrated 3270 console. After a few minutes the *Standalone Program Loader* panel should appear. Use the **TAB** key to traverse to the section *IPL Parameters* and enter the value **cons=sysg**
5. Press the **F10** key to continue the IPL of your z/VM system. This takes around 3 minutes.
6. At the Start prompt you have to specify a **FORCE** start, again because the spool volume label has changed. Enter the following:

```
==> force drain
```

7. Do not change the time of day clock:

```
==> no
```

8. When the IPL completes, **DISCONNECT** from the OPERATOR user ID and **logon to MAINT**:

```
==> disc
```

You should now be able to get a 3270 emulator session as the TCPIP service machine should be up. Get a 3270 session as MAINT and verify the volume labels have changed with the **QUERY CPOWNED** command:

```
==> q cpowned
```

Slot	Vol-ID	Rdev	Type	Status
1	MVA700	A700	Own	Online and attached
2	MVA701	A701	Own	Online and attached
3	MVA702	A702	Own	Online and attached
4	MVA703	A703	Own	Online and attached
5	MVA704	A704	Own	Online and attached


```

6 MPA705 A705 Own Online and attached
7 MPA706 A706 Own Online and attached
8 MPA707 A707 Own Online and attached
9 MPA708 A708 Own Online and attached
10 MPA709 A709 Own Online and attached
11 ----- ---- ----- Reserved
...

```

In the event that you IPLed a system with duplicate system volumes, it is possible that you may have destroyed your saved segments. You will know this is the case when you cannot **IPL CMS**. Rather, you will have to **IPL 190**.

Important: Only do this if your saved segments have been destroyed! To rebuild saved segments, try the following commands:

```

==> vmfsetup zvm cms
==> samprss cms
==> i 190 cl parm savesys cms
==> vmfbld ppf segbld esasegs segblist ( all

```

4.12 Restoring your z/VM system from tape

It is good to practice to restore a system. You don't want to be doing your first restore when the pressure is on.

Restoring a z/VM system from tape that has the same set of volume labels as the system that is running is problematic. If there are two z/VM systems on the same LPAR with the same volume labels, both systems cannot be IPLed cleanly. IPLing one of the two will probably find the correct W01, W02, PAG and SPL volumes, but IPLing the other one will probably find the wrong set.

Perform this step only if you successfully completed 4.10, "Backing up your z/VM system to tape" on page 61, and 4.11, "Relabeling the system volumes" on page 61. If you have done both, then the system on tape has volume labels of 520xxx and the system on DASD has volume labels MVyyyy. You can restore this system to five other 3390-3s.

Refer to the Appendix E "Restore the z/VM System Backup Copy from Tape" in the manual *The z/VM Guide for Automated Installation and Service*, GC204-6099.

Servicing z/VM

You cannot solve a problem with the same kind of thinking that created it.

--Albert Einstein

This section describes how to apply:

- ▶ A Programming Temporary Fix (PTF)
- ▶ A Recommended Service Upgrade (RSU) from “envelope files”

Both processes are basically the same.

Important: When applying service, there is always a chance that you may want to back it out. It is recommended that you have a backup of your system before starting this section.

The application of corrective service to z/VM is covered in the *z/VM V5R1 Service Guide and VMSES/E Introduction and Reference*. Both of these documents can be downloaded in PDF format from the following URL:

<http://www.vm.ibm.com/library>

VMSES/E is a component of z/VM that provides the **SERVICE** and **PUT2PROD** EXECs. The **SERVICE** EXEC:

- ▶ Installs an RSU or applies CORrective service for z/VM components, features, or products.
- ▶ Displays either the RSU level of the component specified or whether a particular PTF or APAR has been applied (when used with STATUS).
- ▶ Creates PTF bitmap files (when used with BITMAP).

When **SERVICE** is successfully complete, the **PUT2PROD** EXEC places the z/VM components, features, or products that are installed on the z/VM System DDR into production.

5.1 Applying a PTF

You may determine that you need to apply a specific fix or PTF to your system.

For example, an Authorized Program Analysis Report (APAR), VM63895, was opened to address the problems reported with virtual NIC support. There are three known symptoms addressed by this APAR:

- ▶ Linux guests may lose connectivity after **shutdown -r now** (or any device reset).
- ▶ Using an External Security Manager (ESM) to authorize a VLAN list may lead to an FRF002 abend.
- ▶ Virtual Hipersockets NIC configured with "VLAN nnn" (exploiting Set Global VLAN ID) did not really filter inbound frames.

The APAR was assigned the following PTF numbers:

- ▶ z/VM 5.1.0 VM63895 UM31612
- ▶ **z/VM 5.2.0 VM63895 UM31613**

There are more details on:

<http://www-1.ibm.com/support/docview.wss?uid=isg1VM63895>

So for z/VM 5.2, you will want to apply PTF UM31613. Following is an example of how to do so.

5.1.1 Determining if a PTF has been applied

Check to make sure the PTF has not previously been applied.

1. Logon to MAINT and issue the **VMFSETUP** command to set up minidisks for TCPIP and link to them:

```
==> vmfsetup zvm cp (link
VMFSET2760I VMFSETUP processing started for ZVM CP
VMFUTL2205I Minidisk|Directory Assignments:
      String   Mode  Stat  Vdev  Label/Directory
VMFUTL2205I LOCALMOD  E    R/W  2C4   MNT2C4
VMFUTL2205I LOCALSAM  F    R/W  2C2   MNT2C2
...
VMFSET2760I VMFSETUP processing completed successfully
```

2. Use the **VMFINF0** command to query the Software Inventory files. Move the Tab key to **ZVM** and type **s** to select it on the *PPF Fileid* panel:

```
==> vmfinfo
```

PPF Fileid - Help

Product parameter files (PPFs) define the environment and key variables required to process the queries. The following is a list of all PPFs found on all accessed disks. Select one to continue. The View function can be used to examine one or more PPFs.

Type a "V" next to one or more PPFs to view their contents, or type an "S" next to one PPF to select.

Options: S - select V - view

Option	PPF Fileid
-	\$5654260 PPF D1

—	SEGBLD	PPF	D2
—	SERV2P	PPF	D1
—	UCENG	PPF	D2
s	ZVM	PPF	D2
—	40SASF40	PPF	D1

3. Because the description of the PTF cites a component name of “VM CP”, select **CP** on the *Component Name* panel.
4. Select **PTFs/APARs** on the *VMFINFO Main Panel*
5. Type in the PTF number **UM31613** in the *PTF number* field then select **Status of PTF** on the *PTF/APAR Queries* panel:

PTF/APAR Queries

Enter a PTF or APAR number and type an option code. Then press Enter.

```
PPF fileid ..... ZVM          PPF  D
Component name .. CP              Setup ... NO
Product ID ..... 5VMCPR20        System .. VM
PTF number ..... UM31613
APAR number .....
```

Options: S - select

Option	Query
s	Status of PTF
—	Requisites/supersedes of PTF
—	Dependencies/superseding of PTF
—	User memo of PTF
—	Serviceable parts included by PTF
—	Abstract of APAR(s)

6. If the PTF has not been successfully applied, you should see the message No data found:

Query Output - PTF Status

```
PPF fileid .....: ZVM          PPF  D
Component name .: CP              Setup ...: NO
Product ID .....: 5VMCPR10      System .: VM
-----
WN:VMFSIP2481W No entries match search arguments
WN:          TDATA :PTF UM31198
WN:          in table 5VMCPR10 SRVRECS J
```

No data found

This shows that PTF UM31613 has *not* been successfully applied. The sections that follow describe how to obtain and apply it.

5.1.2 Getting service via Internet FTP

You may get service for z/VM via tapes. However, you may also wish to get service over the Internet. If so, point a Web browser to:

<https://techsupport.services.ibm.com/server/login>

If you have an IBM user ID and password, use that. If you do not, you can fill out the form to create an IBM ID and password. You should then be at the following Web site:

<https://www.ibm.com/account/profile/us>

1. Click on **Support and Downloads** at the top menu.

2. Click on **Downloads and Drivers** on the left frame.
3. Under *Category*, select **zSeries (mainframe)**
4. Under *Operating Systems*, select **z/VM** and click **Software Only**. This should take you to a page entitled *Support for VM*.
5. Click on **Download selective fixes by PTF**. You may be prompted for your IBM ID and password.
6. In the text box *Enter PTF numbers below [e.g: U412345, U467890]*, enter **UM31613**. All other defaults should be correct. Click **Continue**.
7. In the Verify Order page, click **Submit**. You should get a message similar to the following

Your order has been submitted for processing. Email will be sent to nospam@us.ibm.com.

COER NUMBER is <390473266>. This number is used to submit your request. You will receive a confirmation email that contains your ORDER NUMBER.

...

5.1.3 Downloading the service to z/VM

You should receive two e-mails. The first e-mail has your order number. The second e-mail has instructions on how to download the service files. Make sure you have access to these. Following is an example.

```
TEXT = Data sent via "INET". To retrieve your service:
TEXT =   FTP to: ptf.boulder.ibm.com
TEXT =   Log on using userid "owte8a" and password "h2q9nep9"
TEXT =   Enter the following FTP commands:
TEXT =       cd /390268476/c568411202
TEXT =       ascii
TEXT =       get ftp8476.txt
TEXT =       binary f 1024
TEXT =       get rlst1585.bin
TEXT =       get rptf1585.bin
```

1. **Logon to MAINT.**
2. The MAINT 500 disk should have a lot of free space, so it is a good minidisk on which to download the files. By default the FTP client saves files on the A disk, so access the 500 disk as A:


```
==> vmlink tcpmaint 592
DMSVML2060I TCPMAINT 592 linked as 0120 file mode Z
==> acc 500 a
DMSACC724I 500 replaces A (191)
```
3. Now use the FTP client to get the PTF *envelope files* off the Internet. The envelope files can be large so this may take some time. As you are downloading the files, note the file sizes. Following is an example.

```
==> ftp ptf.boulder.ibm.com
ftp> <owte8a>
ftp> <h2q9nep9>
ftp> cd </390268476/c568411202>
ftp> ascii
ftp> get ftp1585.txt
...
ftp> binary f 1024
ftp> get vlst1585.bin
...
150 Opening BINARY mode data connection for vlst1585.bin (7168 bytes).
7168 bytes transferred in 0.231 seconds. Transfer rate 31.03 Kbytes/sec.
```

```
ftp> get vptf1585.bin
...
551936 bytes transferred in 22.272 seconds. Transfer rate 24.78 Kbytes/sec.
ftp> quit
```

4. Use the **BROWSE** command to view the first text file and verify that the correct number of bytes were downloaded for each file. Press the **F3** key to quit.

```
==> browse ftp1585 txt
VM PTF Package Information
-----
This file contains byte counts of files to receive and instructions
for preparing the files for installation. The byte counts listed
below should match the byte counts of the files when they are received
using FTP.

FILE BYTE COUNTS
-----

The vptf1585.bin byte count is: 551936.
The vlst1585.bin byte count is: 7168.

Match these byte counts to that reported during the FTP get.
...
====> F3
```

5. You should now have the service or *envelope files* on your z/VM system. Rename the file type from BIN to SERVLINK as this is the file type that the **SERVICE** command expects.

```
==> rename vlst1585 bin a = servlink =
==> rename vptf1585 bin a = servlink =
```

6. The envelope files arrive in a compressed format to speed downloads. In order to use them they must first be uncompressed with the **DETERSE** command. Use the **(REPLACE** parameter to uncompress them in place and save disk space:

```
==> deterse vlst1585 servlink a = = = (replace
==> deterse vptf1585 servlink a = = = (replace
```

5.1.4 Receiving, applying, and building service

You must receive, apply, and build the PTF. Then it can be put into production. This can be done in a process that is much easier now with the **SERVICE** command.

To prepare to use the **SERVICE** command, you must have a 256MB virtual machine and you must have the minidisk with a lot of free space - that is what the MAINT 500 minidisk is for.

1. Increase the size of the MAINT virtual machine with the **DEFINE STORAGE** command:

```
==> def stor 256M
STORAGE = 256M
Storage cleared - system reset.
```

2. ReIPL CMS:

```
==> ip1 cms
IPL CMS
z/VM V5.2.0 2006-01-24 13:26
==> Press Enter
```

3. The **SERVICE** command will write to the current A disk. Again access minidisk 500 as A:

```
==> acc 500 a
DMSACC724I 500 replaces A (191)
```

- Now use the **SERVICE ALL** command specifying the envelope files you downloaded. Many, many screens of output will scroll by and the screens will automatically be cleared. Important messages will be saved to the A (500) disk. This process may take many minutes. Following is an example:

```
==> service all vptf1585
...
VMFSUT2760I VMFSUFTB processing started
VMFSUT2760I VMFSUFTB processing completed successfully
VMFSRV2760I SERVICE processing completed successfully
```

A return code of 0 is ideal. In general a return code of 4 is acceptable. That means that only warnings were issued. A return code of 8 or greater generally means that errors were encountered.

- The output files written to the A disk are of the form \$VMF* \$MSGNUM. You may wish to inspect these files.

```
==> filel $VMF* $MSGLOG
MAINT      FILELIST A0  V 169  Trunc=169 Size=5 Line=1 Col=1 Alt=0
Cmd  Filename Filetype Fm Format Lrecl  Records  Blocks  Date    Time
$VMFSRV $MSGLOG A1 V      80      132      3 1/31/06 12:58:09
$VMFBLD $MSGLOG A1 V      80       76      2 1/31/06 12:57:34
$VMFAPP $MSGLOG A1 V      80       70      1 1/31/06 12:57:13
$VMFREC $MSGLOG A1 V      80       55      1 1/31/06 12:57:12
$VMFMRD $MSGLOG A1 V      80       30      1 1/31/06 12:57:10
```

- Invoke the **VMFVIEW SERVICE** command to review the results of the previous **SERVICE** command. Press the **F3** key to quit. Following is an example:

```
==> vmfview service
*****
****              SERVICE              USERID: MAINT              ****
*****
****              Date: 01/31/06              Time: 12:57:09              ****
*****
====> F3
```

Ideally there will be no output which as there is in this example. That means the service applied perfectly.

5.1.5 Putting the service into production

Use the **PUT2PROD** command to put the service into production.

Important: If you run **PUT2PROD** from a 3270 emulator session, you may lose your connection as the TCPIP service machine may be recycled. Therefore you may want to run this command from a console.

In this example, applying PTF UM31613 *did not* affect the emulator session.

```
==> put2prod
RDR FILE 0016 SENT FROM MAINT      CON WAS 0016 RECS 0004 CPY  001 T NOHOLD NOKEEP
VMFP2P2760I PUT2PROD processing started
VMFP2P2760I PUT2PROD processing started for VMSES
VMFSET2760I VMFSETUP processing started for SERVP2P VMSESP2P
...
```



```
USER DSC LOGOFF AS BLDGMS USERS = 7 FORCED BY MAINT
VMFP2P2760I PUT2PROD processing completed successfully for SAVECMS
VMFP2P2760I PUT2PROD processing completed successfully
```

Your PTF should now be “put into production”. You may or may not have to reIPL the system, depending on the nature of the PTF applied. It is safest to reIPL via the **SHUTDOWN REIPL** command in order to completely test the changes:

```
==> shutdown reipl ipparms cons=sysc
SYSTEM SHUTDOWN STARTED
...
```

Your z/VM system should come back in a few minutes. You may wish to perform the steps in section 5.1.1, “Determining if a PTF has been applied” on page 70 to verify that this PTF has been applied.

5.2 Applying a Recommended Service Upgrade or RSU

Applying an RSU is very similar to applying a PTF described in the previous section. z/VM service can be preventive (RSU) or corrective (COR). Part 4, *Service Procedure*, in the manual *Guide for Automated Installation and Service* gives a complete description of applying service to z/VM, however it assumes you are starting with the RSU tape. Following is an example of upgrading to a z/VM 5.2 RSU with the medium being files, not tape.

The section that follows is a summary of applying service and also describes how to obtain the service via envelope files over the Internet.

You must first determine if your system needs service. Use the **QUERY CPLEVEL** command:

```
==> q cplevel
z/VM Version 5 Release 2.0, service level 0501 (64-bit)
Generated at 11/18/05 23:44:09 EST
IPL at 12/19/06 13:44:37 EST
```

The service level four digits are split in half, where the first half is the last two digits of the year and the second half is the service level for that year. Therefore, a service level of “0501” means the first service level for the year 2005 has been applied. If you installed from DVD, that was on the second RSU DVD disc.

The overall steps in applying a service level are as follow:

- ▶ Getting service from the Internet
- ▶ Download the service to z/VM
- ▶ Receive, apply and build the service
- ▶ Put the service into production

5.2.1 Getting service from the Internet

The PTF number for the most current RSU for z/VM 5.2.0 is **UM97520** The PTF number for the most current RSU for z/VM 5.1.0 is UM97510. Point a Web browser to:

<https://techsupport.services.ibm.com/server/login>

1. If you have an IBM user ID and password, use that. If you do not, you can fill out the form to create an IBM ID and password. You should then be at the following Web site:

<https://www.ibm.com/account/profile/us>

2. Click on **Support and Downloads** at the top menu.

3. Click on **Downloads and Drivers** on the left frame.
4. Under *Category*, select **zSeries (mainframe)**
5. Under *Operating Systems*, select **z/VM** This should take you to a page entitled Support for VM.
6. Click on **Download selective fixes by PTF**. You may be prompted for your IBM ID and password.
7. In the text box *Enter PTF numbers below [e.g: U412345, U467890]*, enter **UM97520** for the latest z/VM 5.2 service level, **UM97510** for the latest z/VM 5.1 service level, or the appropriate PTF number. All other defaults should be correct.
8. Click **Continue**
9. In the Verify Order page, click **Submit**. You should get a message similar to the following

Your order has been submitted for processing. Email will be sent to
nosspam@us.ibm.com.

COER NUMBER is <390473266>. This number is used to submit your request. You will
receive a confirmation email that contains your ORDER NUMBER.

5.2.2 Downloading the service to z/VM

You should receive two e-mails. The first e-mail has your order number. The second e-mail has instructions on how to download the service files. Make sure you have access to these. Following is an example.

```
TEXT = Data sent via "INET". To retrieve your service:
TEXT = FTP to: ptf.boulder.ibm.com
TEXT = Log on using userid "owte8a" and password "h2q9nep9"
TEXT = Enter the following FTP commands:
TEXT = cd /390268476/c568411202
TEXT = ascii
TEXT = get ftp8476.txt
TEXT = binary f 1024
TEXT = get rlst8476.bin
TEXT = get rptf0176.bin
TEXT = get rptf0276.bin
TEXT = get rptf0376.bin
```

1. Logon to MAINT.
2. The MAINT 500 disk should have a lot of free space, so it is a good minidisk on which to download the files. By default the FTP client saves files on the A disk, so access the 500 disk as A:

```
==> acc 500 a
DMSACC724I 500 replaces A (191)
```

3. Link to the TCPMAINT 592 disk to get access to the FTP client command

```
==> vmlink tcpmaint 592
DMSVML2060I TCPMAINT 592 linked as 0120 file mode Z
```

4. Use the FTP client to get the RSU envelopes off the Internet. The envelope files can be large so this may take some time. It is recommended that you rename the file type from BIN to SERVLINK via FTP because this is the file type that the **SERVICE** command expects. As you are downloading the files, note the file sizes. Following is an example.

```
==> ftp ptf.boulder.ibm.com
ftp> <owte8a>
ftp> <h2q9nep9>
ftp> cd </390268476/c568411202>
```

```

ftp> ascii
ftp> get ftp8476.txt
ftp> binary f 1024
ftp> get rlst8476.bin rlst8476.servlink
...
10240 bytes transferred in 0.523 seconds. Transfer rate 19.58 Kbytes/sec
ftp> get rptf0176.bin rptf0176.servlink
...
36944896 bytes transferred in 191.632 seconds. Transfer rate 192.79 Kbytes/sec.
ftp> get rptf0276.bin rptf0276.servlink
...
26028032 bytes transferred in 132.353 seconds. Transfer rate 196.66 Kbytes/sec.
ftp> get rptf0376.bin rptf0376.servlink
...
52193280 bytes transferred in 269.094 seconds. Transfer rate 193.96 Kbytes/sec.
ftp> quit

```

You should now have the service or *envelope files* on your z/VM system.

5. The envelope files arrive in a compressed format to speed downloads. In order to use them they must first be uncompressed with the **DETERSE** command. Use the **(REPLACE** parameter to uncompress them in place and save disk space:

```

==> deterse rlst8476 servlink a = = = (replace
==> deterse rptf0176 servlink a = = = (replace
==> deterse rptf0276 servlink a = = = (replace
==> deterse rptf0376 servlink a = = = (replace

```

Note: if you did not rename the file names during the FTP session you can use the CMS **RENAME** command. Type **HELP RENAME** for help.

6. Use the **BROWSE** command to read the RSU information. Compare the byte count that you recorded earlier with the values in this file.

```

==> browse ftp8476 txt
VM RSU Package Information
-----
This file contains byte counts of files to receive and instructions
for preparing the files for installation. The byte counts listed
below should match the byte counts of the files when they are received
using FTP.

FILE BYTE COUNTS
-----

The rlst8476.bin byte count is: 10240.
The rptf176.bin byte count is: 36944896.
The rptf276.bin byte count is: 26028032.
The rptf376.bin byte count is: 52193280.
...

```

5.2.3 Receiving, applying, and building the service

You must receive, apply, and build the service. Then it can be put into production.

In the past, this was a cumbersome procedure. For example, to receive, apply and build the CP component, the following steps were needed:

```

vmfmrdsk zvm cp apply (setup
vmfsetup zvm cp
vmfpsu zvm cp
vmfins install ppf zvm cp (nomemo env {filename} nolinek override no
vmfapply ppf zvm cp (setup

```

```
vmfbld ppf zvm cp (status
vmfbld ppf zvm cp (serviced
```

Then the same steps were needed for many other components. The process is much easier now with the **SERVICE** command. On the other hand, the previous method is more granular and better enables the system administrator to know which pieces of service have been applied.

1. To prepare to use the **SERVICE** command, you must have a 256MB virtual machine and you must have the minidisk with a lot of free space - that is what the MAINT 500 minidisk is for. Increase the size of the MAINT virtual machine with the **DEFINE STORAGE** command:

```
==> def stor 256M
STORAGE = 256M
Storage cleared - system reset.
==> ip1 cms
IPL CMS
z/VM V5.2.0    2006-01-24 13:26
==> Press Enter
```

2. The **SERVICE** command will write to the current A disk, so you again want to access 500 as A:

```
==> acc 500 a
DMSACC724I 500 replaces A (191)
```

3. Use the **SERVICE ALL** command specifying the envelope files you downloaded. Many, many screens of output will scroll by and the screens will automatically be cleared. Important messages will be saved to the A (500) disk. This process may take many minutes or tens or tens of minutes. Following is an example:

```
==> service all rptf0176 rptf0276 rptf0376
...
VMFSUT2760I VMFSUFTB processing completed successfully
VMFSRV2760I SERVICE processing completed with warnings
Ready(00004); T=185.66/191.79 11:56:47
```

A return code of 0 is ideal. Note in the last Ready line that this command returned a code of

4. In general a return code of 4 is acceptable. That means that only warnings were issued. A return code of 8 or greater generally means that errors were encountered.

4. The output files written to the A disk are of the form \$VMF* \$MSGNUM:

```
==> filel $VMF* $MSGLOG
$VMFP2P $MSGLOG A1 V      80      1520      28 11/10/05 13:35:43
$VMFBLD $MSGLOG A1 V      80       639       9 11/10/05 13:28:42
$VMFMRD $MSGLOG A1 V      80       499       7 11/10/05 13:28:39
$VMFSRV $MSGLOG A1 V      80      1369      25 11/10/05 11:56:47
$VMFAPP $MSGLOG A1 V      80       682       9 11/10/05 11:54:07
$VMFINS $MSGLOG A1 V      80       381       6 11/10/05 11:54:05
```

5. Invoke the **VMFVIEW SERVICE** command to review the results of the previous **SERVICE** command. Following is an example:

```
==> vmfview service
*****
****              SERVICE              USERID: MAINT              ****
*****
****              Date: 11/10/05              Time: 11:43:15              ****
*****
CK:VMFSUI2104I PTF UM30896 contains user information. Review the :UMEMO
CK:              section in file UM30896 $PTFPART
CK:VMFSUI2104I PTF UM31044 contains user information. Review the :UMEMO
CK:              section in file UM31044 $PTFPART
CK:VMFSUI2104I PTF UM31233 contains user information. Review the :UMEMO
CK:              section in file UM31233 $PTFPART
```

```

CK:VMFSUI2104I PTF UM31275 contains user information. Review the :UMEMO
CK:          section in file UM31275 $PTFPART
WN:VMFBDC2250W The following VMHCD objects have been built on BUILD0 300
WN:          (I) and should be copied to your workstation:
WN:VMFBDC2250W EEQINSTX EXEBIN
WN:VMFSRV1221W The CP Stand-Alone Dump Utility must be rebuilt. Follow
WN:          the instructions in the z/VM Service Guide.

```

Ideally there will be no output which means the service applied perfectly. In this example, the above the following messages are generated. The first four VMFSUI2104I messages are informational. The VMFBDC2250W message is pertinent if you are using the VM HCD tool. The VMFSRV1221W is pertinent if you are using the CP Stand-alone Dump Utility.

You should see that the service was installed successfully.

5.2.4 Putting the service into production

This section describes how to use the **PUT2PROD** command to put the service into production.

Important: If you run **PUT2PROD** from a 3270 emulator session, you may lose your connection as the TCPIP service machine may be recycled. Therefore you may want to run this command from a console. If you do switch to a new session, remember to set the machine size to 256M and access the 500 disk as A.

1. Use the **PUT2PROD** command to put the service into production. Many screens will scroll by. This command can take quite a number of minutes to complete:

```

==> put2prod
RDR FILE 0016 SENT FROM MAINT    CON WAS 0016 RECS 0004 CPY  001 T NOHOLD NOKEEP
VMFP2P2760I PUT2PROD processing started
...
USER DSC  LOGOFF AS  BLDCMS  USERS = 7    FORCED BY MAINT
VMFP2P2760I PUT2PROD processing completed successfully for SAVECMS
VMFP2P2760I PUT2PROD processing completed successfully

```

Even though the service has been “put into production”, the **QUERY CPLEVEL** command should still return the current service level; in this example 0501. This is because the new CP load module (nucleus) has not been invoked:

```

==> q cplevel
z/VM Version 5 Release 2.0, service level 0501 (64-bit)
Generated at 11/18/05 23:44:09 EST
IPL at 12/19/06 13:44:37 EST

```

To invoke the new CP load module, use the **SHUTDOWN REIPL** command. When your system comes back up, it should be at the new CP service level, in this example 0602:

```

==> shutdown reipl iplparms cons=sysc
...
==> q cplevel
z/VM Version 5 Release 2.0, service level 0602 (64-bit)
Generated at 09/18/06 18:39:52 EST
IPL at 12/19/06 14:53:28 EST

```

This shows that the new CP load module is now being used.

5.3 Determining z/VM's service level

Often you will want to be able to query more than just the service level. The following steps were taken from the links **CP Maintenance Levels** and **Virtual Switch TCP/IP Maintenance Levels** starting at the Web site:

<http://www.vm.ibm.com/virtualnetwork/>

Logon as TCPMAINT. Use the **QUERY VMLAN** command to determine the latest APAR applied:

```
==> cp query vmlan
VMLAN maintenance level:
  Latest Service: VM63895
VMLAN MAC address assignment:
  MACADDR Prefix: 020001
  MACIDRANGE SYSTEM: 000001-FFFFFF
  USER: 000000-000000
VMLAN default accounting status:
  SYSTEM Accounting: OFF      USER Accounting: OFF
VMLAN general activity:
  PERSISTENT Limit: INFINITE   Current: 1
  TRANSIENT Limit: INFINITE    Current: 0
```

This shows that the latest APAR applied is VM63895.

The maintenance level of the TCP/IP stack is important to virtual networking. To determine this, first get the active VSWITCH controller:

```
==> q vswitch
VSWITCH SYSTEM VSW1      Type: VSWITCH Connected: 8      Maxconn: INFINITE
PERSISTENT RESTRICTED    NONROUTER                      Accounting: OFF
VLAN Unaware
State: Ready
IPTimeout: 5             QueueStorage: 8
Portname: UNASSIGNED RDEV: 3004 Controller: DTCVSW1 VDEV: 3004
Portname: UNASSIGNED RDEV: 3008 Controller: DTCVSW2 VDEV: 3008 BACKUP
```

This shows the controller is named DTCVSW1. Then use the **NETSTAT** command with the controller name to determine the maintenance of the TCPIP MODULE:

```
==> netstat tcp <dtcvsw1> level
VM TCP/IP Netstat Level 520
IBM 2094; z/VM Version 5 Release 2.0, service level 0601 (64-bit), VM TCP/IP Level 520; RSU 0601 running TCPIP MODULE E2 dated 02/10/06 at 19:00
TCP/IP Module Load Address: 00C44000
```

This shows information about the TCPIP MODULE. Use the **TCPSLVL** command and the complete file specification (TCPIP MODULE E in this example) to get more information. Of particular interest is the latest APAR applied to TCTOOSD

```
==> tcpslvl tcpip module e
SLVL TCPIP      PQ22678
...
SLVL TCTOOSD    PK00905
...
```

Moving on

You should now be done installing, configuring and servicing z/VM. A great attribute of z/VM is that it normally hums along with little maintenance required. It is now time to change your focus to Linux.

Part 2

RHEL 5

This part of the book describes how to set up installation, customization and cloning of RHEL 5 servers. Included is a chapter on using kickstart, Red Hat's automated install procedure.

Configuring an NFS server for RHEL 5

“Anyone who has never made a mistake has never tried anything new.”

— Albert Einstein

A common method of installing Linux on under z/VM is over the network from another server using the Network File System (NFS). To accomplish this, a PC Linux system is recommended. This server supplies both the RHEL 5 distribution and the files associated with this book. The server must have at least 4 GB of free disk space. It can be a Linux PC, but it can also be a UNIX box (Sun™ Solaris™, Hewlett Packard HP-UX, IBM AIX® or other). You can also choose to use a Windows workstation via FTP or HTTP. Often, more problems are encountered when using a Windows workstation than a Linux or Unix workstation to serve the RHEL 5 install tree.

The steps in this chapter explain how to configure a PC Linux box as the NFS server. Red Hat Installation Guide for the IBM S/390 and IBM System z Architectures manual provides additional information about the installation options on the Web at:

<http://www.redhat.com/docs/manuals/enterprise/>

The following tasks will set up a Linux NFS server:

- ▶ “Installing Linux on the PC” on page 83
- ▶ “Downloading files associated with this book” on page 84
- ▶ “Setting up a RHEL 5 install tree” on page 84
- ▶ “Enabling the NFS server” on page 86

6.1 Installing Linux on the PC

If you don’t have a Linux PC then you must get access to one on the network and install Linux onto it. Describing that is outside the scope of this book. However, installing the same distribution onto a PC server that you plan to install on System z is recommended. Doing so will give you practice with the installation process and will give you a reference system that may be helpful in understanding the differences between the Intel (i386, i686) and System z (s390x) architectures. In this chapter, a PC running RHEL 5 is used.

6.2 Downloading files associated with this book

This book has files associated with it to make the task of customizing, cloning and backup up your virtual servers easier. The tar file on the Web at:

<http://linuxvm.org/present/misc/virt-cookbook-RH5.tgz>

The tar file `virt-cookbook-RH5.tgz` is about 124KB. Download the file and untar it. The following example shows this being done from a newly created directory `/nfs/`:

```
# mkdir /nfs
# cd /nfs
... download or copy the file virt-cookbook-RH5.tgz to /nfs/ ...
# tar xzf virt-cookbook-RH5.tgz
```

List the files in the new directory `virt-cookbook-RH5/`:

```
# cd virt-cookbook-RH5
# ls
README.txt      sitar-1.0.7-270.1.noarch.rpm      vm/
rsyncd.conf     virtcook-controller-1-RH5.s390x.rpm
```

The `README.txt` file briefly describes each of the files and the one directory. You may want to briefly view that file. You now have downloaded and uncompressed the files associated with this book.

6.3 Setting up a RHEL 5 install tree

You must have a valid Red Hat entitlement for Linux on IBM System z to access the Red Hat Enterprise Linux 5 ISO images. If you do not have one, you can request a free evaluation copy at:

<http://www.redhat.com/rhel/details/eval/>

Follow the link named Red Hat Enterprise Linux AS for IBM eServer zSeries and IBM S/390 and create an account. You require this login to access the Red Hat Network (RHN), where you can download the installation discs at:

<https://rhn.redhat.com>

RHEL 5 is distributed on physical CDs or files that are ISO images of CDs. This is not new. What is new is that it is also distributed on a single physical DVD disc or a single ISO image. It is easier to work with a single DVD ISO image than to work with multiple CD ISO images, so this approach is recommended

Download the DVD ISO image to a new directory `/nfs/rhel5/`:

```
# cd /nfs
... download the DVD ISO image
```

6.3.1 Copying from physical DVD

In the event that you have a physical DVD, but not an ISO image, it is recommended that you create an ISO image. You could skip creating the ISO image and copy the data directly from the DVD to the install tree, but creating the ISO image is recommended so you have a reference file.

Be sure your PC has a DVD drive, not just a CD drive (if you have a PC that only has a CD drive, you can create ISO images of the CDs, but this is not described). Put the DVD in the

tray and use the **dd** command to create the ISO image. The device file named `/dev/cdrom` is often associated with the CD/DVD drive, however, your device file name may be different. If so, you must determine the correct name.

Perform these steps only if you are starting with a physical DVD disc:

```
# cd /nfs
# dd if=/dev/cdrom of=RHEL5-Server-s390x-DVD.iso
# umount /mnt/cdrom
```

You should now have an ISO image of the DVD.

6.3.2 Verifying the ISO image

An important early step is to verify the integrity of DVD ISO image. This is done by comparing a checksum value which was calculated when the DVD was created against a checksum value calculated against your ISO image. If the two checksum values differ then there was an error somewhere in the copying process.

The **md5sum** command allows you to compare checksum files. The checksum value for the GA version of RHEL 5 for the s390x architecture is as follows:

```
# cat MD5SUM
c15890d1aa9addb285dad89fb8ade1db  RHEL5-Server-s390x-DVD.iso
```

Run the **md5sum** command against the MD5SUM file:

```
# md5sum -c MD5SUM
RHEL5-Server-s390x-DVD.iso: OK
```

Important: Your MD5SUM file may have checksum values for the DVD *and* the CD ISO images. If this is true and you only have one DVD ISO image, the md5sum will generate errors of the form:

```
md5sum: RHEL5-Server-s390x-disc1-ftp.iso: No such file or directory
RHEL5-Server-s390x-disc1-ftp.iso: FAILED open or read
```

This is not a problem, as long as the DVD ISO image is reported as OK.

If the ISO image does not report OK, it must be downloaded or copied again until it does.

6.3.3 Copying the DVD contents

Copy the contents of the ISO image to the file system. Temporarily mount it over a new directory `tmp/` using a loopback device:

```
# cd /nfs
# mkdir tmp
# mount -o loop RHEL5-Server-s390x-DVD.iso tmp
```

List the contents of the mounted ISO image:

```
# ls tmp
EULA          README-pa.html  RELEASE-NOTES-m1.html
eula.en_US    README-pt_BR.html  RELEASE-NOTES-mr.html
generic.ins   README-ru.html    RELEASE-NOTES-or.html
...
```

Make a new directory, `/nfs/rhel5/`, and recursively copy the contents of the DVD to it via the **cp -a** command. This will take a number of minutes to complete:

```
# cp -a tmp/* rhel5/
```

6.3.4 Building the repository directory

For the yum command to work, a common metadata repository must be built via the **createrepo** command. There is a sample repository in the directory `Server/repodata/`. The group XML file named `comps-rhel5-server-core.xml` should be used to create group information i

```
# cd rhel5/Server/
# mv repodata/ repodata.orig
# createrepo -g repodata.orig/comps-rhel5-server-core.xml .
2495/2495 - junit-javadoc-3.8.2-3jpp.1.s390x.rpm
Saving Primary metadata
Saving file lists metadata
Saving other metadata
```

Now the newly created `repodata/` directory contains the correct common metadata:

```
# cd repodata
# ls
comps-rhel5-server-core.xml  other.xml.gz  repomd.xml
```

6.4 Enabling the NFS server

The method of enabling an NFS server will differ depending upon the operating system. However, the steps are basically the same:

- ▶ Export the appropriate directories.
- ▶ Start the NFS server in the current run level.

The directories to export via NFS are set in the `/etc/exports` configuration file. Export the directory `/nfs/rhel5/` to make the install tree available and `/nfs/virt-cookbook-RH5/` to make the files associated with this book available. First make a backup copy of the file. Then edit the original copy and add the two directories as follows:

```
# cd /etc
# cp exports exports.orig
# vi exports      // add two lines
/nfs/rhel5       *(ro,sync)
/nfs/virt-cookbook-RH5 *(ro,sync)
```

The `*(ro,sync)` parameter specifies that any client with access to this server can get the NFS mount read-only. You may want to be more restrictive than allowing any client (via the `“*”`) for security reasons. Type **man exports** for more details.

Set the NFS server to start via the **chkconfig** command and start it on for the current session with the **service nfs start** command:

```
# chkconfig nfs on
# chkconfig --list nfs
nfs          0:off  1:off  2:on   3:on   4:on   5:on   6:off
# service nfs start
Starting NFS services: [ OK ]
Starting NFS quotas: [ OK ]
Starting NFS daemon: [ OK ]
Starting NFS mountd: [ OK ]
```

Your NFS server should now be running with the directory exported. It is recommended that you test this by mounting the exported directory locally. The following example shows that the /mnt/ directory is empty. Then the newly exported /nfs/ directory is mounted and the files are listed.

```
# mkdir /mnt/tmp
# mount localhost:/nfs/rhel5/ /mnt/tmp
# ls -F /mnt/tmp
EULA          README-or.html      RELEASE-NOTES-ja.html
eula.en_US     README-pa.html      RELEASE-NOTES-ko.html
generic.ins    README-pt_BR.html   RELEASE-NOTES-m1.html
GPL            README-ru.html       RELEASE-NOTES-mr.html
images/        README-si.html       RELEASE-NOTES-or.html
...
```

This shows that the RHEL 5 install tree is accessible via NFS. Now unmount it and test the virt-cookbook-RH5/ directory:

```
# umount /mnt/tmp
# mount localhost:/nfs/virt-cookbook-RH5 /mnt/tmp
# ls -F /mnt/tmp
README.txt    sitar-1.0.7-270.1.noarch.rpm      vm/
clone.sh*     virtcook-controller-1-RH5.s390x.rpm
# umount /mnt/tmp
```

You should now be able to use this server as the source of a RHEL 5 mainframe Linux installation. Later you will be able to copy the install tree to a System z Linux virtual server.

Installing and configuring RHEL 5

“The most incomprehensible thing about the world is that it is at all comprehensible.”

— Albert Einstein

In this chapter you will install your first Linux ID, RHEL5. This Linux ID is unique in that it will have two copies of Linux; think of it as a dual-boot Linux PC. You will install the following Linux images onto the RHEL5 user ID:

- | | |
|--------------|---|
| Master image | The copy of Linux that will be cloned. This has also been referred to as the <i>Golden image</i> . This should be as lean as possible so as to be a generic virtual server and to fit comfortably in one 3390-3 DASD. |
| Controller | The copy of Linux that will normally be running and one that does the cloning. This has also been referred to as <i>the cloner</i> . |
- In addition to being *the cloner*, the RHEL5 user ID serves as the administration point for current and future Linux IDs
 - RHEL 5 install server - a tree of RPMs and other files needed for installation
 - NFS server - to export the *install tree* and possibly other data and directories
 - Kickstart server: This hosts files necessary for automated installations.
 - Backup server - for incremental backup of key virtual server configuration files
 - Time server - for time synchronization of all other Linux virtual servers

In this section, you will perform following tasks:

- ▶ “Creating the user ID RHEL5” on page 90
- ▶ “Adding RHEL5 to AUTOLOG1’s PROFILE EXEC” on page 92
- ▶ “Preparing RHEL5 bootstrap files” on page 93
- ▶ “Installing the master image” on page 95
- ▶ “Configuring the master image” on page 105
- ▶ “Installing the controller” on page 116
- ▶ “Configuring the controller” on page 121

Chapters 4, 5 and 6 must be completed before proceeding.

7.1 Creating the user ID RHEL5

In this section you will define the RHEL5 user ID to z/VM.

1. **Logon to MAINT** and edit the USER DIRECT file:

```
==> x user direct c
```

In the USER DIRECT file you can group statements that will be common to many user definitions in a construct called a *profile*. This profile can then become part of the user definitions via the INCLUDE statement. You used the existing profile TCPCMSU when you defined the LNXMAINT user.

2. Create a new profile named LNXDFLT. This will contain the user directory statements that will be common to all Linux user IDs. To save typing, you can use the "" prefix commands to duplicate the IBMDFLT profile that should be on lines 37-50:

```
""037 *****
00038 *
00039 PROFILE IBMDFLT
00040   SPOOL 000C 2540 READER *
00041   SPOOL 000D 2540 PUNCH A
00042   SPOOL 000E 1403 A
00043   CONSOLE 009 3215 T
00044   LINK MAINT 0190 0190 RR
00045   LINK MAINT 019D 019D RR
00046   LINK MAINT 019E 019E RR
00047   LINK MAINT 0402 0402 RR
00048   LINK MAINT 0401 0401 RR
00049   LINK MAINT 0405 0405 RR
""050 *****
```

3. Edit the duplicated profile by deleting the three LINK MAINT 040x lines, and inserting the lines that are emboldened:

```
PROFILE LNXDFLT
  IPL CMS
  MACHINE ESA 4
  CPU 00 BASE
  CPU 01
  NICDEF 600 TYPE QDIO LAN SYSTEM VSW1
  SPOOL 000C 2540 READER *
  SPOOL 000D 2540 PUNCH A
  SPOOL 000E 1403 A
  CONSOLE 009 3215 T
  LINK MAINT 0190 0190 RR
  LINK MAINT 019D 019D RR
  LINK MAINT 019E 019E RR
  LINK LNXMAINT 192 191 RR
  LINK TCPMAINT 592 592 RR
```

Notes:

- 1 CMS will be IPLed when the user ID is logged onto
- 2 Machine will of type ESA with a maximum of 4 CPUs that can be defined
- 3 Defines the base CPU
- 4 Defines a second CPU - **don't include this** if your LPAR has only a single IFL/CP
- 5 Defines a virtual NIC connected to the VSWITCH starting at virtual address 600
- 6 Provides read access to LNXMAINT 192 disk as the user's 191 disk
- 7 Provides read access to TCPMAINT 592 disk, so that the user has access to TCPIP services such as FTP

- Go to the bottom of the file and add the definition for a new user ID named RHEL5. This user ID is given class B privilege, aside from the typical class G, in order to run the **FLASHCOPY** command, class D privilege to run the **QUERY ALLOC MAP** command, and class E privilege to run the **QUERY NSS** command. Be sure to replace the volume labels (MMA728-MMA72E in this example) with the labels of your DASD:

```

USER RHEL5 LNX4VM 256M 1G BDEG
  INCLUDE LNXDFLT
  OPTION LKNOPAS APPLMON
  MDISK 100 3390 0001 3338 <MMA728> MR LNX4VM LNX4VM LNX4VM
  MDISK 200 3390 0001 3338 <MMA729> MR LNX4VM LNX4VM LNX4VM
  MDISK 203 3390 0321 3018 <MMA72A> MR LNX4VM LNX4VM LNX4VM
  MDISK 204 3390 0001 3338 <MMA72B> MR LNX4VM LNX4VM LNX4VM
  MDISK 205 3390 0001 3338 <MMA72C> MR LNX4VM LNX4VM LNX4VM
  MDISK 206 3390 0001 3338 <MMA72D> MR LNX4VM LNX4VM LNX4VM
  MDISK 207 3390 0001 3338 <MMA72E> MR LNX4VM LNX4VM LNX4VM

```

*

This Linux user ID will have the following minidisks and virtual disks (VDISKS):

Table 7-1 Minidisks to be defined

Minidisk	Description
100	The root file system of the master image - this is the copy that will be cloned.
101-102	These are virtual disk (VDISK) swap spaces that are not defined in USER DIRECT file, but defined by calls to the SWAPGEN EXEC in the user's PROFILE EXEC so that when the user ID logs on the VDISKS are created.
200	The root file system of the Linux controller. This will serve as the administration point for all your Linux virtual servers.
203	The /backup/ file system for backing up. Note that the first 320 cylinders of the volume used for this disk were used for the LNXMAINT 191 and 192 minidisks.
204-207	Minidisks used to create a logical volume mounted over /nfs/ for making the RHEL5 installation tree and the files associated with this book available via NFS.

- Go back to the top of the file and search for string **USER \$ALLOC\$**. Add cylinder 0 of each of the six new volumes to this dummy user ID so they don't show up as gaps in the **USER DISKMAP** report file (in this example MMA72A was added earlier)

```

====> top
====> /user $alloc$
USER $ALLOC$ NOLOG
  MDISK A01 3390 000 001 <MVA700> R
  MDISK A02 3390 000 001 <MVA703> R
  MDISK A03 3390 000 001 <MVA704> R
  MDISK A01 3390 000 001 <MVA700> R
  MDISK A02 3390 000 001 <MVA703> R
  MDISK A03 3390 000 001 <MVA704> R
  MDISK A04 3390 000 001 <MMA72A> R
  MDISK A05 3390 000 001 <MMA728> R
  MDISK A06 3390 000 001 <MMA729> R
  MDISK A07 3390 000 001 <MMA72B> R
  MDISK A08 3390 000 001 <MMA72C> R

```

```
MDISK A09 3390 000 001 <MMA72D> R
MDISK A0A 3390 000 001 <MMA72E> R
...
====> file
```

6. Run **DISKMAP** to check for overlaps and gaps. You should only see the single 501 cylinder gap.

```
==> diskmap user
==> x user diskmap
====> all /gap/|/overlap/
----- 4 line(s) not displayed -----
                                0        500        501    GAP
----- 322 line(s) not displayed -----
====> quit
```

7. When the disk layout is correct run **DIRECTXA** to bring the changes online:

```
==> directxa user
z/VM USER DIRECTORY CREATION PROGRAM - VERSION 5 RELEASE 2.0
EOJ DIRECTORY UPDATED AND ON LINE
```

You have now defined the user ID that will be both the master Linux image and the controller.

7.2 Adding RHEL5 to AUTOLOG1's PROFILE EXEC

The new Linux ID you defined needs access to the VSWITCH. A **SET VSWITCH** command with the **GRANT** parameter can be added to AUTOLOG1's **PROFILE EXEC** to do this. Also, an **XAUTOLOG** statement can be added if the user ID is automatically logged on at z/VM IPL time:

Link and access the AUTOLOG1 191 disk read/write and edit the file **PROFILE EXEC**. Add the RHEL5 user ID to the sections that grant access to the VSWITCH and that **XAUTOLOG** the Linux user IDs:

```
==> link autolog1 191 1191 mr
==> acc 1191 f
==> x profile exec f // add two lines
/*****/
/* Autolog1 Profile Exec */
/*****/
'cp xautolog tcpip' /* start up TCPIP */
'CP XAUTOLOG DTCVSW1' /* start VSWITCH controller 1 */
'CP XAUTOLOG DTCVSW2' /* start VSWITCH controller 2 */
'cp set pf12 ret' /* set the retrieve key */
'cp set mdc stor 0m 128m' /* Limit minidisk cache in CSTORE */
'cp set mdc xstore 0m 0m' /* Disable minidisk cache in XSTORE */
'cp set srm storbuf 300% 250% 200%' /* Overcommit memory */
'cp set signal shutdown 180' /* Allow guests 3 min to shut down */

/* Grant access to VSWITCH for each Linux user */
'cp set vswitch vsw1 grant rhel5'

/* XAUTOLOG each Linux user that should be started */
'cp xautolog rhel5'

'cp logoff' /* logoff when done */
====> file
```

These changes will not take effect until the next IPL, so you must grant this user ID access to the VSWITCH for this z/VM session. This is done as follows:

```
==> set vswitch vsw1 grant rhel5
Command complete
```

7.3 Preparing RHEL5 bootstrap files

To IPL a RHEL5 installation system, four bootstrap files must be prepared. Three are punched to z/VM reader and then IPLed. These three files IPLed are a kernel, a parameter file and an initial RAMdisk. The fourth file is a configuration file stored on a CMS disk that the parameter file points to.

Think of these as the files that are on as a PC Linux boot CD (or floppy disk). Also, a small REXX EXEC is commonly used to clean out the reader, punch the three files and IPL the reader. A sample RHEL5 parameter file, configuration file and RHEL5 EXEC are supplied and should be on the LNXMAINT 192 disk. This is described in section 7.1, “Creating the user ID RHEL5” on page 90. Therefore, only the kernel and RAMdisk should need to be copied.

1. Start an SSH session as root on the NFS server.
2. Use the **ftp** command to copy the RHEL 5 kernel and initial RAMdisk to LNXMAINT's D disk. These files must have a record format of fixed 80 byte records. This format can be set with the **site fix 80** FTP subcommand (if this subcommand fails, try **quote site fix 80**). Following is an example:

```
# cd /nfs/rhel5/images
# ftp <129.40.178.120>
Name (129.40.178.120:root): lnxmaint
Password:
230 LNXMAINT logged in; working directory = LNXMAINT 191
Remote system type is z/VM.
ftp> cd lnxmaint.192
250 Working directory is LNXMAINT 192
ftp> site fix 80
200 Site command was accepted.
ftp> bin
200 Representation type is IMAGE.
ftp> put initrd.img rhel5.initrd
12237790 bytes sent in 01:28 (135.35 KB/s)
ftp> put kernel.img rhel5.kernel
local: kernel.img remote: rhel5.kernel
3629384 bytes sent in 00:25 (138.96 KB/s)
ftp> quit
```

3. Go back to your 3270 session. **Logoff of MAINT and logon to LNXMAINT.**
4. The files RHEL5 EXEC, RHEL5 PARM-RH5 and RHEL5 CONF-RH5 should exist on the LNXMAINT 192 disk (D) as they were copied in 7.1, “Creating the user ID RHEL5” on page 90. Use the **FILELIST** command to verify that they were copied in Fixed 80 byte record format. You should see the following files (the number of records and blocks may vary):

```
==> filel rhel5 * d
LNXMAINT FILELIST A0 V 169 Trunc=169 Size=5 Line=1 Col=1 Alt=0
```

Cmd	Filename	Filetype	Fm	Format	Lrec1	Records	Blocks	Date	Time
	RHEL5	KERNEL	D1	F	80	45368	832	1/15/07	10:25:20
	RHEL5	INITRD	D1	F	80	153196	2993	1/15/07	10:24:47
	RHEL5	CONF-RH5	D1	V	38	13	1	1/15/07	9:45:41
	RHEL5	EXEC	D1	V	67	9	1	1/15/07	9:45:41
	RHEL5	PARM-RH5	D1	V	80	3	1	1/15/07	9:45:41

5. Quit by pressing **F3**.

6. Verify that the file **RHEL5 EXEC** has the correct information. Note the kernel and RAMdisk have hard coded file names, but the file name of the parameter file will be the user ID (**userid()** function) of the user running the EXEC:

```
==> type rhel5 exec d
/* EXEC to punch RHEL5 install system to reader and IPL from it */
'CP SPOOL PUN *'
'CP CLOSE RDR'
'PUR RDR ALL'
'PUN RHEL5      KERNEL * (NOH'
'PUN' userid() 'PARM-RH5 * (NOH'
'PUN RHEL5      INITRD * (NOH'
'CH RDR ALL KEEP'
'IPL OOC CLEAR'
```

7. There are two text files needed to install RHEL5: a parameter file and a configuration file. The parameter file is named **RHEL5 PARM-RH5** and is punched to the reader. It has some values, the most important value, the **CMSCONFFILE** variable, points to the configuration file which remains on a CMS minidisk. The sample parameter file should not need to be modified:

```
==> type rhel5 parm-rh5 d
ramdisk_size=40000 root=/dev/ram0 ro ip=off
CMSDASD=191 CMSCONFFILE=RHEL5.CONF-RH5
vnc vncpassword=lnx4vm
```

8. Enter the appropriate networking values in the configuration file, in this case **RHEL5 CONF-RH5**. The sample configuration file contains some fields that should be correct and many fields that will have to be modified. Modify at least the fields shown in **<bold>** and perhaps others. Refer to the worksheet in section 2.7.3, “Linux resources worksheet” on page 19.

Before:

```
DASD=100-102,200,203-207
HOSTNAME=hostName.DNSname.com
NETTYPE=qeth
IPADDR=n.n.n.n
SUBCHANNELS=0.0.0600,0.0.0601,0.0.0602
NETWORK=n.n.n.n
NETMASK=255.255.255.0
SEARCHDNS=DNSname.com
BROADCAST=n.n.n.n
GATEWAY=n.n.n.n
DNS=n.n.n.n
MTU=1500
PORTNAME=DONT CARE
```

After:

```
==> x rhel5 conf-rh5
DASD=100-102,200,203-207
HOSTNAME=<lat128.pbm.ihost.com>
NETTYPE=qeth
IPADDR=<129.40.178.128>
SUBCHANNELS=0.0.0600,0.0.0601,0.0.0602
NETWORK=<129.40.178.0>
NETMASK=255.255.255.0
SEARCHDNS=<pbm.ihost.com>
BROADCAST=<129.40.178.255>
GATEWAY=<129.40.178.254>
DNS=<129.40.106.1>
MTU=1500
```

PORTNAME=DONTCARE

9. Save your changes with the **FILE** subcommand.

Now you are ready to start the master image installation.

7.4 Installing the master image

The master or golden image will be installed onto the RHEL5 100 disk. Again, this is the image of Linux that will be cloned.

You should still be logged onto LNXMAINT. When you logon to the new RHEL5 user ID, you will pick up a **PROFILE EXEC** from LNXMAINT 192. This file runs when you press **Enter** at the VM READ prompt and creates two **VDISKs** via the **SWAPGEN EXEC** to later be used as swap spaces. View the contents of the **PROFILE EXEC** via the **CMS TYPE** command:

```
==> type profile exec d
/* PROFILE EXEC for Linux virtual servers */
'CP SET RUN ON'
'CP SET PF11 RETRIEVE FORWARD'
'CP SET PF12 RETRIEVE'
'ACC 592 C'
'SWAPGEN 101 524288' /* create a 256M VDISK disk swap space */
'SWAPGEN 102 1048576' /* create a 512M VDISK disk swap space */
'PIPE CP QUERY' userid() '| var user'
parse value user with id . dsc .
if (id = 'SLES9'|id = 'SLES9X'|id = 'SLES10'|id = 'RHEL5') then
do
    iplDisk = 200
end
else /* this is a Linux clone */
do
    iplDisk = 100
end
if (dsc = 'DSC') then /* user is disconnected */
    'CP IPL' iplDisk
else /* user is interactive -> prompt */
do
    say 'Do you want to IPL Linux from DASD' iplDisk'? y/n'
    parse upper pull answer .
    if (answer = 'Y') then
        'CP IPL' iplDisk
    end /* else */
end
```

Perform the following steps to prepare for installing Linux:

1. **Logoff of LNXMAINT and logon to RHEL5.** When you logon, you should see message indicating that a virtual NIC has been created at addresses 600-602 (via the **NICDEF** statement in the **USER DIRECT** file) and that two **VDISKs** have been created at virtual addresses 101 and 102 (via the **SWAPGEN EXEC** called from the **PROFILE EXEC**):

```
LOGON RHEL5
00: NIC 0600 is created; devices 0600-0602 defined
00: z/VM Version 5 Release 2.0, Service Level 0602 (64-bit),
00: built on IBM Virtualization Technology
00: There is no logmsg data
00: FILES: NO RDR, NO PRT, NO PUN
00: LOGON AT 10:00:35 EST WEDNESDAY 12/20/06
z/VM V5.2.0 2006-12-19 14:40
```

```

DMSACP723I A (191) R/O
DMSACP723I C (592) R/O
DIAG swap disk defined at virtual address 101 (64989 4K pages of swap space)
DIAG swap disk defined at virtual address 102 (129981 4K pages of swap space)

```

2. You are prompted to IPL Linux, but since you have not installed Linux yet, answer **n**:

```

Do you want to IPL Linux from DASD 200? y/n
==> n

```

3. Before you install Linux, it is good to verify the resources. Verify that you have DASD (minidisks) at virtual addresses 100-102 with the **QUERY VIRTUAL** command (other Linux IDs without class B privilege will just use the **QUERY** command):

```

==> q v 100-102
q v 100-102
00: DASD 0100 3390 MMA728 R/W      3338 CYL ON DASD  A728 SUBCHANNEL = 0000
00: DASD 0101 9336 (VDSK) R/W     524288 BLK ON DASD  VDSK SUBCHANNEL = 0013
00: DASD 0102 9336 (VDSK) R/W     1048576 BLK ON DASD  VDSK SUBCHANNEL = 0014

```

4. Verify that you have a virtual OSA at addresses 600-602 with the **QUERY VIRTUAL OSA** command:

```

==> q v osa
00: OSA 0600 ON NIC 0600 UNIT 000 SUBCHANNEL = 0007
00:      0600 DEVTYPE OSA          CHPID 0E OSD
00:      0600 QDIO-ELIGIBLE        QIOASSIST-ELIGIBLE
00: OSA 0601 ON NIC 0600 UNIT 001 SUBCHANNEL = 0008
00:      0601 DEVTYPE OSA          CHPID 0E OSD
00:      0601 QDIO-ELIGIBLE        QIOASSIST-ELIGIBLE
00: OSA 0602 ON NIC 0600 UNIT 002 SUBCHANNEL = 0009
00:      0602 DEVTYPE OSA          CHPID 0E OSD
00:      0602 QDIO-ELIGIBLE        QIOASSIST-ELIGIBLE

```

5. Use the **QUERY VIRTUAL STORAGE** command to show that you have a 256MB machine:

```

==> q v stor
00: STORAGE = 256M

```

6. This is adequate memory to run a RHEL5 Linux image, however it is often too small in which to install Linux. Temporarily modify the storage up to 512MB with the **DEFINE STORAGE** command. Then **IPL CMS** and again answer **n** to the question of IPLing Linux:

```

==> def stor 512m
00: STORAGE = 512M
00: Storage cleared - system reset.
==> ip1 cms
z/VM V5.2.0    2006-07-18 08:48

```

```

DMSACP723I A (191) R/O
DMSACP723I C (592) R/O
DIAG swap disk defined at virtual address 101 (64989 4K pages of swap space)
DIAG swap disk defined at virtual address 101 (64989 4K pages of swap space)
DIAG swap disk defined at virtual address 102 (129981 4K pages of swap space)
Do you want to IPL Linux from DASD 200? y/n
n

```

7. Verify that you have a 512MB virtual machine:

```

==> q v stor
00: STORAGE = 512M

```

This change is for the duration of the user ID session. When you logoff and log back on this user ID, the storage will go back to 256MB.

7.4.1 Stage 1 of the RHEL 5 installation

Follow these steps to begin the installation of RHEL5.

1. Run the **RHEL5 EXEC**. You should see many screens of questions and answers scrolling by. If you had used the default parameter file shipped with RHEL5, you would have had to answer all the networking questions manually. With the proper parameters set in RHEL5 CONF-RH5, the install process should proceed to where you have to use a browser to VNC client get into the installation program:

```
==> RHEL5
00: RDR FILE 0019 SENT FROM RHEL5    PUN WAS 0019 RECS 045K CPY  001 A NOHOLD NO
KEEP
00: RDR FILE 0020 SENT FROM RHEL5    PUN WAS 0020 RECS 0003 CPY  001 A NOHOLD NO
KEEP
00: RDR FILE 0021 SENT FROM RHEL5    PUN WAS 0021 RECS 153K CPY  001 A NOHOLD NO
KEEP
00: 0000003 FILES CHANGED
Linux version 2.6.18-1.2839.el5 (brewbuilder@devel8.z900.redhat.com) (gcc versio
n 4.1.1 20061130 (Red Hat 4.1.1-43)) #1 SMP Tue Dec 5 22:58:42 EST 2006
We are running under VM (64 bit mode)
Detected 2 CPU's
Boot cpu address  0
Built 1 zonelists. Total pages: 131072
Kernel command line: ramdisk_size=40000 root=/dev/ram0 ro ip=off
                      CMSDASD=191 CMSCONFFILE=RHEL5.CONF-RH5
                      vnc vncpassword=lnx4vm
...
```

The kernel should continue to boot until you see the following messages:

```
...
Starting telnetd and sshd to allow login over the network.
```

Connect now to 129.40.178.128 to start the installation.

2. From your workstation, use your SSH client (e.g. PuTTY) to connect to the IP address and begin the installation. When prompted for a user name, enter **root**: a password will not be required. Figure 7-1 shows the initial screen of the installer. Use the **Tab** key to move between fields. Use the arrow keys to move among choices and **Enter** to select a choice.

Important: If the DASD you are using has never been formatted for Linux, you may get many screens of warning messages similar to the following on your 3270 session:

```
dasd(eckd): I/O status report for device 0.0.0100:
dasd(eckd): in req: 000000000e027ee8 CS: 0x40 DS: 0x0E
dasd(eckd): device 0.0.0100: Failing CCW: 000000000e027fd0
dasd(eckd): Sense(hex) 0- 7: 00 08 00 00 04 ff ff 00
```

This is not a problem, you just have to clear the screen many times or the install process will freeze. An alternative to clearing the screen many times is to issue the following CP **TERM** command:

```
#cp term more 0 0
```

Press **Enter** and the screen should scroll freely. The downside of this option is that you may miss some messages that are important. You may later want to set the value back to the default of waiting 50 seconds to beep then another 10 seconds to clear the screen via the following command:

```
#cp term more 50 10
```



Figure 7-1 Initial screen of installer

3. The Choose a Language screen should appear. Select your language, Tab to **OK** and press **Enter**.
4. The *Installation Method* screen should appear. Choose **NFS image** for the install method, and select **OK**.
5. The *NFS Setup* screen should appear. Enter the IP address of the PC NFS server on the first line, then the path to the installation tree on the second line, and select **OK**. See the example in Figure 7-2 which uses the NFS server at IP address 129.40.46.206:




Figure 7-2 NFS setup screen

6. Now the curses Windows should end and the install program (anaconda) should start a VNC server. You should see messages similar to the following:

```
Welcome to the anaconda install environment 1.1 for zSeries
```

```
Running anaconda, the Red Hat Enterprise Linux Server system installer - please wait...
```

```
Starting VNC...
```

```
The VNC server is now running.
```

```
Please connect to 129.40.178.128:1 to begin the install...
```

```
Starting graphical installation...
```


Press <enter> for a shell
XKB extension not present on :1

7. Start a VNC client (e.g. RealVNC) and connect to the server with your IP address with a :1 appended to the end as shown in Figure 7-3. When prompted for a password, enter the password specified in the RHEL5 PARM-RH5 file (**lnx4vm** in the sample file). In the following example, Linux is being installed with the IP address 129.40.178.128:




Figure 7-3 Connecting with VNC client

7.4.2 Stage 2 of the RHEL 5 installation

After you have connected using VNC, perform the following steps:

1. The welcome screen opens. Click **Next**.
2. The installer prompts for an installation number as shown in Figure 7-4, which determines the packages that are available for installation. This information should have come with the details of your subscription. If you select **Skip**, this will result in a core server installation, and additional functionality can be added manually after installation.

At the time of this writing, the installation number is listed in the *Installation-Related Notes* section of the release notes in the install tree. For English, see `/nfs/rhe15/RELEASE-NOTES-en` on the PC NFS server.




Figure 7-4 Enter installation number

3. Because the disks were just formatted by CPFMTXA (with the CPFORMAT EXEC wrapper), you will be prompted to format each of them. Click **yes** to format dasda (minidisk 100) as shown in Figure 7-5 on page 101. A progress indicator will be shown. You will not be asked to format disks 101 and 102 because they are the VDISK swap spaces and are not recognized by the installer.



Figure 7-5 Formatting DASD for Linux use

4. You have the choice of formatting the dasdd-dasdh disks (203-207 minidisks) now or when you later install the controller. When the installer prompts you to initialize the drive, select **Yes** :
5. The installer now searches for a previous installation. If this is the first installation, nothing will be found. If a previous installation is found, the installer prompts you whether to **Upgrade** or **Install**. Choose **Install** here.
6. At the disk partitioning setup screen, choose **Create Custom Layout** as shown in Figure 7-6 on page 102. Click **Next** to proceed to the Disk Setup screen.




Figure 7-6 Choosing custom disk partitioning

7. Disks 100 should show free space. Click the **New** button to add a root file system to the 100 disk. Enter `/` in the field *Mount Point*, choose to format the file system as `ext3` and deselect all drives *except* `dasda` as Figure 7-7 shows. Finally, select **Fill to maximum allowable size** and click **OK**.




Figure 7-7 Adding the root file system

8. Click **Next**. You will see a warning about missing swap partitions. You can ignore it because there will be swap disk defined later on. Click **Yes**.
9. At the Network Configuration screen, enter a host name for the master image as Figure 7-8 shows. Other network settings have been automatically taken from the RHEL5 CONF-RH5 file. Click **Next**.

The screenshot shows the 'Network Devices' configuration window for Red Hat Enterprise Linux 5. The window title is 'Red Hat Enterprise Linux Server 4.92 installation on host 129.40.178.128'. The main header is 'RED HAT ENTERPRISE LINUX 5'. Under 'Network Devices', there is a table with columns: 'Active on Boot', 'Device', 'IPv4/Netmask', and 'IPv6/Prefix'. The first row shows 'eth0' with '129.40.178.128/24' and an 'Edit' button. Below the table is a 'Hostname' section with the instruction 'Set the hostname:'. It has two radio buttons: 'automatically via DHCP' (unselected) and 'manually' (selected). The 'manually' option has a text input field containing 'lat128.pbm.ihost.com' and a hint '(e.g., host.domain.com)'. Below this is the 'Miscellaneous Settings' section with three text input fields: 'Gateway:' (129.40.178.254), 'Primary DNS:' (129.40.106.1), and 'Secondary DNS:'. At the bottom left is a 'Release Notes' button, and at the bottom right are 'Back' and 'Next' buttons.

Active on Boot	Device	IPv4/Netmask	IPv6/Prefix
<input checked="" type="checkbox"/>	eth0	129.40.178.128/24	

Hostname
Set the hostname:
☐ automatically via DHCP
☒ manually (e.g., host.domain.com)

Miscellaneous Settings
Gateway:
Primary DNS:
Secondary DNS:

Figure 7-8 Configuring the network device

10. At the Time Zone Selection screen, highlight the nearest city in your time zone. Deselect **System clock uses UTC** and click **Next**.
11. Set the Root Password, then click **Next**.

12. At the package selection screen, deselect all package groups, select **Customize Now** and click **Next**.



Figure 7-9 Customizing software packages

13. Remove the majority of the package groups as follows:
- Under **Desktop Environments**, deselect **Gnome** so nothing is selected
 - Under **Applications**, deselect all package groups
 - Under **Development**, nothing should be selected
 - Under **Servers**, deselect **Printing Support** so nothing is selected
 - Under **Base System**, leave **Base** and **X Window System** selected and deselect everything else, as shown in Figure 7-10.
 - Under **Languages**, select a package group if you need specific language support.
 - Click **Next** and package dependencies will be determined.




Figure 7-10 Customizing packages

14. Finally, click **Next** to begin the installation. This lasts from five to ten minutes, depending on network speeds.
15. When the installation is complete, click **Reboot**. The VNC session will end, but your system will not reboot.

7.4.3 Booting your new Linux system from disk

A minimal system should now be installed onto minidisk 100. Return to your z/VM 3270 session and IPL the newly installed system via the command **#CP IPL 100**.

```
/mnt/sysimage/dev done
/mnt/sysimage done
you may safely reboot your system
==> #cp ipl 100
CP IPL 100
zIPL v1.3.2 interactive boot menu
  0. default (linux)
  1. linux
Note: VM users please use '#cp vi vmmsg <input>'
Please choose (default will boot in 15 seconds):
...
```

Linux will boot after 15 seconds if you take no action. To boot immediately, issue the following command:

```
==> #cp vi vmmsg 0
```

Your system should continue to boot until a login prompt is presented.

Important: Due to a known issue when connecting to a layer 3 VSWITCH, you must log in through the console and change one networking parameter before the system will come up on the network. The need to do this is explained in the following Web page:

http://kbase.redhat.com/faq/FAQ_85_6247.shtml

Login as root. Invoke the **echo** command to append the **ARP=no** directive to the end of the **eth0** interface configuration file, then reboot the Linux server.

```
Red Hat Enterprise Linux Server release 4.92 (Tikanga)
Kernel 2.6.18-1.2839.el5 on an s390x
```

```
lat128 login: root
Password:
```

```
Last login: Tue Dec 12 11:19:47 from 9.56.60.217
# echo ARP=no >> /etc/sysconfig/network-scripts/ifcfg-eth0
# reboot
```

When your system comes back up, it should be on the network. Disconnect from the 3270 session with the following command:

```
==> #cp disc
```

Start an SSH session into the master image as root.

7.5 Configuring the master image

Now you want to customize the master image as much as possible before cloning. The following high level steps are recommended though you may add or omit some steps:

- ▶ “Configuring VDISK swap” on page 106
- ▶ “Configuring automount of install tree” on page 107
- ▶ “Configuring yum for online updates” on page 107
- ▶ “Adding additional RPMs” on page 108
- ▶ “Changing automount to point to controller” on page 109
- ▶ “Turning off unneeded services” on page 109
- ▶ “Configuring the VNC server” on page 110
- ▶ “Configuring rsyncd” on page 111
- ▶ “Creating the script nightly.sh” on page 112
- ▶ “Setting the software clock accurately” on page 112
- ▶ “Setting system to halt on SIGNAL SHUTDOWN” on page 113
- ▶ “Modifying modprobe.conf” on page 113

7.5.1 Configuring VDISK swap

Recall that you were warned during the installation that you were not using any swap spaces. This can be confirmed with the **swapon -s** command which lists swap spaces:

```
# swapon -s
```

No output means there are no swap spaces. Linux must now be configured to use the VDISK swap spaces. Observe the first three DASD devices via the following **head** command:

```
# head -3 /proc/dasd/devices
0.0.0100(ECKD) at ( 94: 0) is dasda : active at blocksize: 4096, 600840 blocks, 2347 MB
0.0.0101(FBA ) at ( 94: 4) is dasdb : active at blocksize: 512, 524288 blocks, 256 MB
0.0.0102(FBA ) at ( 94: 8) is dasdc : active at blocksize: 512, 1048576 blocks, 512 MB
```

Of course /dev/dasda is your 100 minidisk and /dev/dasda1 is the first partition which is mounted over the root file system. You should also see that /dev/dasdb and /dev/dasdc are FBA devices which signifies VDISKs. The **SWAPGEN EXEC** creates a single partition with a swap signature on each of the two VDISKs. Therefore, you can use /dev/dasdb1 and /dev/dasdc1 as swap devices. Make a backup copy of the file system table, /etc/fstab, then add the two swap spaces as follows:

```
# cd /etc
# cp fstab fstab.orig
# vi /etc/fstab
LABEL=/1          /                ext3    defaults    1 1
/dev/dasdb1       swap             swap    defaults    0 0
/dev/dasdc1       swap             swap    defaults    0 0
LABEL=/backup     /backup          ext3    defaults    1 2
devpts            /dev/pts         devpts  gid=5,mode=620 0 0
tmpfs             /dev/shm         tmpfs   defaults    0 0
/dev/Vo1Group00/LogVo100 /nfs             ext3    defaults    1 2
proc              /proc            proc    defaults    0 0
LABEL=/           /rhel5master     ext3    defaults    1 2
sysfs             /sys             sysfs   defaults    0 0
```

Save the file and turn on the swap spaces via the **swapon -a** command which will read the /etc/fstab file and then verify that the swap spaces have been activated:

```
# swapon -a
# swapon -s
```

Filename	Type	Size	Used	Priority
/dev/dasdb1	partition	259956	0	-1
/dev/dasdc1	partition	519924	0	-2

7.5.2 Configuring automount of install tree

You will now configure the Linux automount service to mount the installation tree on demand. The automounter will automatically mount a remote directory when it is accessed, and automatically unmount it after a period of inactivity.

Make a backup copy of the file `/etc/auto.master`, then add the following line at the bottom:

```
# cd /etc
# cp auto.master auto.master.orig
# vi /etc/auto.master // add one line at the bottom
...
#
+auto.master
/nfs /etc/auto.controller
```

The new line specifies that the file system mounted beneath the directory `/nfs/` will be configured in the file `/etc/auto.controller`. Now create the file `/etc/auto.controller`, and add one line which points to the RHEL 5 install tree that is exported:

```
# vi /etc/auto.controller
rhe15 -ro,hard,intr <129.40.46.206>:/nfs/rhe15
```

This line specifies that beneath `/nfs/` (in `auto.master`) when the directory `rhe15/` (field 1) is accessed, automatically used the specified options (in field 2) to mount the specified directory (in field 3).

Now, create the `/nfs/` directory. Restart the **autofs** service to pick up the new configuration. Then list the contents of the `/nfs/rhe15/` directory. Even though it does not exist as a local file system, it is automatically mounted when referenced:

```
# mkdir /nfs
# service autofs restart
Stopping automount: [ OK ]
Starting automount: [ OK ]
# ls /nfs/rhe15
EULA README-or.html RELEASE-NOTES-ja.html
eula.en_US README-pa.html RELEASE-NOTES-ko.html
...
```

7.5.3 Configuring yum for online updates

You will now configure **yum** so it can install RPMs from automounted install tree. Later you will move the install tree from the PC server to the System z controller. Create a file named `rhe15.repo` in the `/etc/yum.repos.d` directory:

```
# cd /etc/yum.repos.d
# vi rhe15.repo
[RHEL5]
name=Red Hat Enterprise Linux 5
baseurl=file:///nfs/rhe15/Server
```

You must import the RPM GPG key so that **yum** knows you are installing official Red Hat packages. The Red Hat GPG key is located in the install tree. Import the key with the following command:

```
# rpm --import /nfs/rhe15/RPM-GPG-KEY
Note: for RHEL5 beta distributions, use the file RPM-GPG-KEY-redhat-beta
```

Note: Red Hat signs each RPM with a private GPG key, which is compared to your public key each time a package is installed. This method ensures that the RPM is a genuine, unaltered package. When installing an RPM, if you ever see a message similar to:

```
Header V3 DSA signature: NOKEY, key ID 897da07a
```

Either the correct GPG key has not been imported, or the package itself has been altered by a third party.

You are now ready to use `yum` to install or upgrade an RPM package. To install a package, use `yum install <packagename>`. Yum will conveniently install the packages specified and automatically resolve dependencies for you. Note that you should not specify the package version on the command line, only the package name.

7.5.4 Adding additional RPMs

Now that `yum` is configured, you will install some additional RPM packages onto the master image. You may choose to add additional RPMs, or may choose to omit some of the following:

openmotif A window manager used in conjunction with VNC that is more usable than the default window manager

xinetd This is a service that controls access to other services. It is recommended for `rsync` configuration in “Configuring `rsyncd`” on page 111.

sitar A tool to generate an HTML file describing the Linux system in great detail.

To add the first two RPMs described above you can use `yum -y install` command packages. Notice that `yum` has added multiple dependencies to the package list:

```
# yum -y install openmotif xinetd
Loading "rhnpplugin" plugin
Loading "installonlyn" plugin
...
Installed: openmotif.s390x 0:2.3.0-0.3.e15 openmotif.s390 0:2.3.0-0.3.e15 xinetd.s390x
2:2.3.14-10.e15
Dependency Installed: expat.s390 0:1.95.8-8.2.1 fontconfig.s390 0:2.4.1-5.e15
freetype.s390 0:2.2.1-16.e15 libXft.s390 0:2.1.10-1.1 libXmu.s390 0:1.0.2-5 libXp.s390
0:1.0.0-8 libXp.s390x 0:1.0.0-8 libXrender.s390 0:0.9.1-3.1 libjpeg.s390 0:6b-37
libpng.s390 2:1.2.10-7
Complete!
```

Adding the Sitar package

The `sitar` package is not part of RHEL 5, but is an important of the backup and monitoring sections of this book. Therefore it is included in the tar file which is associated with this book. That file should be untarred on the PC NFS server. First mount the directory over `/mnt/`:

```
# mount <129.40.46.206>:/nfs/virt-cookbook-RH5 /mnt
# cd /mnt
# rpm -Uvh sitar-1.0.7-270.1.noarch.rpm
Preparing... ##### [100%]
1:sitar ##### [100%]
```

Now you have a good set of packages in the master image that will be cloned into virtual servers. You may choose to add more or remove some packages.

7.5.5 Changing automount to point to controller

Now that you have installed the necessary additional RPMs, you will configure the master image to automatically mount the controller's NFS share, so that **yum** will use this instead of the PC NFS server. Although the controller has not yet been installed, you will make the change now so that this change is reflected when you clone new virtual servers based on this master image. Edit the file `/etc/auto.controller`, and change the IP address from the PC NFS server to the controller. In this example, the IP address was changed from 129.40.46.206 to 129.40.178.128

```
# vi /etc/auto.controller
rhe15          -ro,hard,intr  <129.40.178.128>:/nfs/rhe15
```

7.5.6 Turning off unneeded services

There are a number of services which are started in a RHEL 5 minimum system. In order to keep the master image as lean as possible, some of these can be turned off:

Turn off the following services via the **chkconfig** command:

```
# chkconfig cups off
# chkconfig iptables off
# chkconfig ip6tables off
# chkconfig auditd off
# chkconfig haldaemon off
# chkconfig atd off
# chkconfig kudzu off
# chkconfig mdmonitor off
# chkconfig rpcgssd off
# chkconfig rpcidmapd off
# chkconfig anacron off
# chkconfig mcstrans off
# chkconfig yum-updatesd off
```

Note: You should only disable the **iptables** service if you are on a trusted network. Otherwise, you will need to configure **iptables** to allow network traffic for the VNC server and NFS, as well as any other services that require network access.

For more information on configuring **iptables** for NFS traffic, see the article located at:

http://www.redhat.com/magazine/010aug05/departments/tips_tricks/

You may choose to leave these services on, or turn others off. You can review which services are now configured to start in run level 3 with the following command:

```
# chkconfig --list | grep 3:on
autofs          0:off  1:off  2:off  3:on   4:on   5:on   6:off
avahi-daemon    0:off  1:off  2:off  3:on   4:on   5:on   6:off
crond           0:off  1:off  2:on   3:on   4:on   5:on   6:off
httpd           0:off  1:off  2:on   3:on   4:on   5:on   6:off
messagebus      0:off  1:off  2:on   3:on   4:on   5:on   6:off
netfs           0:off  1:off  2:off  3:on   4:on   5:on   6:off
network         0:off  1:off  2:on   3:on   4:on   5:on   6:off
nfs             0:off  1:off  2:on   3:on   4:on   5:on   6:off
nfslock         0:off  1:off  2:off  3:on   4:on   5:on   6:off
ntpd            0:off  1:off  2:on   3:on   4:on   5:on   6:off
portmap         0:off  1:off  2:off  3:on   4:on   5:on   6:off
readahead_early 0:off  1:off  2:on   3:on   4:on   5:on   6:off
restorecond     0:off  1:off  2:on   3:on   4:on   5:on   6:off
rhnssd          0:off  1:off  2:off  3:on   4:on   5:on   6:off
```

sendmail	0:off	1:off	2:on	3:on	4:on	5:on	6:off
sshd	0:off	1:off	2:on	3:on	4:on	5:on	6:off
syslog	0:off	1:off	2:on	3:on	4:on	5:on	6:off
xfs	0:off	1:off	2:on	3:on	4:on	5:on	6:off
xinetd	0:off	1:off	2:off	3:on	4:on	5:on	6:off
yum-updatesd	0:off	1:off	2:off	3:on	4:on	5:on	6:off

7.5.7 Configuring the VNC server

Often applications require a graphical environment. The Virtual Network Computing (VNC) server allows for a graphical environment to be set up easily by starting the **vncserver** service. RHEL 5 configures the VNC server via the `/etc/sysconfig/vncservers` configuration file. Add a line at the bottom of this file to specify the VNC user:

```
# vi /etc/sysconfig/vncservers
...
VNCSERVERS="1:root"
```

Set a VNC password via the **vncpasswd** command. This password will be needed to connect to the VNC server:

```
# vncpasswd
Password: <1nx4vm>
Verify: <1nx4vm>
```

Now start the VNC server with the **service** command:

```
# service vncserver start
Starting VNC server: 1:root xauth: creating new authority file /root/.Xauthority
New 'lat128.pbm.ihost.com:1 (root)' desktop is lat128.pbm.ihost.com:1
Creating default startup script /root/.vnc/xstartup
Starting applications specified in /root/.vnc/xstartup
Log file is /root/.vnc/lat128.pbm.ihost.com:1.log
[ OK ]
```

There is one more configuration to be done. Stop the VNC server and change from the Tiny window manger, **twm**, to the Motif window manager, **mwm**:

```
# cd /root/.vnc
# vi xstartup // change last line
...
xsetroot -solid grey
vncconfig -iconic &
xterm -geometry 80x24+10+10 -ls -title "$VNCDESKTOP Desktop" &
mwm &
```

You can now use the VNC client to connect to the IP address of the master image with a **:1** appended. A sample session is shown in Figure 7-11.




Figure 7-11 VNC client session to the VNC server

Note that the VNC server will not be started across reboots. When you need a graphical environment, you can either to start the **vncserver** process manually (recommended), or you can use **chkconfig** to enable automatic startup.

7.5.8 Configuring rsyncd

There are many ways to backup files and one of them is **rsync**. Rather than copying entire files as with the **scp -rp** command, **rsync** just copies the differences or deltas of changed files. For this reason it is an efficient tool for backups.

First use the **chkconfig** command to enable **rsync** startup at boot time:

```
# chkconfig rsync on
```

You will configure two files: the main configuration file `/etc/rsyncd.conf`, and a file to allow only the controller to connect, `/etc/trusted.hosts`.

For convenience, a copy of `rsyncd.conf` has been included in the tar file associated with this book. You can either create the `rsyncd.conf` file manually or you can copy it. The following example shows it being copied from the PC NFS server which should still be mounted over `/mnt`:

```
# cd /etc
# cp /mnt/rsyncd.conf .
# cat rsyncd.conf
gid = users
read only = yes
transfer logging = true
log format = %h %o %f %l %b
hosts allow = /etc/trusted.hosts
max connections = 1
log file = /var/log/rsync.log
timeout = 300

[etc]
path = /etc
read only = yes
list = yes
```

The file `/etc/trusted.hosts` needs a single entry which is the TCP/IP address of the controller. This will allow only the controller to get an **rsync** session to the virtual servers. Create the file as follows:

```
# vi trusted.hosts // add one line - the TCP/IP address of the controller
<129.40.178.128>
```

Now **rsync** should be configured to allow the `/etc/` directory to be copied by the controller.

7.5.9 Creating the script `nightly.sh`

Create a small script named **nightly.sh** in the `/etc/cron.daily/` directory that will be run each night.

```
# cd /etc/cron.daily
# vi nightly.sh
let secs=$RANDOM/9                # number of seconds between 0 and 1 hour
sleep $secs                       # sleep so cron load is dispersed
sitar --format=html --outfile=/etc/sitar.html # create sitar report in /etc
/usr/sbin/ntpdate -q              # Adjust the clock
# chmod +x nightly.sh
```

The first line creates a random number between 0 and 3640 - approximately the number of seconds in one hour. The second line puts the script to sleep for that long so the cron workload across the LPAR does not all start at once.

The third line creates an HTML report about the virtual server in the `/etc/` directory via **sitar**. This report will be copied to the controller each night via its cron script, and then will be referenced by the DAZL Web application

The last line adjusts the clock accurately. In the next section you will set up NTP to point to the controller as a software clock reference.

7.5.10 Setting the software clock accurately

It is important to have the Linux software clock set properly. This is commonly accomplished by running the **ntpd** daemon against some accurate time sources. However, this is expensive in terms of CPU costs. A compromise between an extremely accurate clock (running **ntpd** as a service) and using fewer CPU cycles (not running it) is to reset the clock once a day. This can be done with a script that runs the **ntpdate -q** command from the `/etc/cron.daily/` directory. NTP will be configured so the controller will be the external clock. In 7.7.9, “Turning on the NTP server” on page 125, the controller will be configured to point to external clocks on the Internet.

Modify the `/etc/ntp.conf` file to comment out the NTP servers on the Internet and add a pointer to the controller as follows:

```
# cd /etc
# vi ntp.conf // comment 3 servers and add controller
...

# Use public servers from the pool.ntp.org project.
# Please consider joining the pool (http://www.pool.ntp.org/join.html).
# server 0.rhel.pool.ntp.org
# server 1.rhel.pool.ntp.org
# server 2.rhel.pool.ntp.org
server 129.40.178.128
...
```

Now you should have the configuration file `/etc/ntp.conf` pointing to the controller, and a script in the directory `/etc/cron.daily/`. This configuration will allow the virtual servers to set the software clock accurately once a day, yet not have the overhead of the chatty Network Time Protocol (NTP).

7.5.11 Setting system to halt on SIGNAL SHUTDOWN

By default, RHEL 5 reboots when a Ctrl-Alt-Del key sequence is trapped. This key sequence is simulated by z/VM when it issues a **SIGNAL SHUTDOWN** command. Rather than rebooting, you want your system to halt (shutdown).

Change this setting by changing **shutdown -r** to **shutdown -h** in the `/etc/inittab` file:

```
# cd /etc
# vi inittab    // change shutdown -r to shutdown -h
...
# Trap CTRL-ALT-DELETE
ca::ctrlaltdel:/sbin/shutdown -t3 -h now
...
```

This change will be picked up when the system is rebooted.

7.5.12 Modifying modprobe.conf

When a RHEL 5 system boots it determines which disks to bring online by the device addresses built into the initial RAMdisk. Change the DASD range and rebuild the RAMdisk to pick up that change.

First, edit the `dasd=` parameter in `/etc/modprobe.conf`. When specifying it you must maintain the ordering of the existing minidisks (`/dev/dasda = 100`, `/dev/dasdb = 101` and `/dev/dasdc = 102`). Make a backup copy of the file and add the string **dasd=100-102** to the parameter line:

```
# cd /etc
# cp modprobe.conf modprobe.conf.orig
# vi modprobe.conf    // modify the dasd= string
alias eth0 qeth
options dasd_mod dasd=100-102
```

Next, backup the initial RAMdisk and rebuild with **mkinitrd**. This will read `modprobe.conf` and incorporate the new DASD range.

```
# cd /boot
# cp initrd-2.6.18-1.2839.el5.img initrd-2.6.18-1.2839.el5.img.orig
# mkinitrd -f initrd-2.6.18-1.2839.el5.img $(uname -r)
```

Finally, run the **zipl** command so the changes are written to the boot record:

```
# zipl
Using config file '/etc/zipl.conf'
Building bootmap in '/boot/'
Building menu 'rh-automatic-menu'
Adding #1: IPL section 'linux' (default)
Preparing boot device: dasda (0100).
Done.
```

7.5.13 Rebooting the system

Now **reboot** to test your changes:

```
# reboot
Broadcast message from root (pts/0) (Sun Nov 19 08:57:32 2006):

The system is going down for reboot NOW!
```

7.5.14 Verifying the changes

You are now done customizing the master Linux image. When the system comes back up you should verify the changes that you made.

1. **SSH back into the master image** and check a few settings.
2. Use the **df** command to display your file systems. Note that out of a 2GB root file system you are using about a third of it (your output may differ):

```
# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/dasda1     2.3G  900M  1.3G  42% /
udev            247M   72K  247M   1% /dev
```

3. Confirm that both of your swap spaces are operational:

```
# swapon -s
Filename                                Type      Size      Used      Priority
/dev/dasdb1                             partition 259956    0         -1
/dev/dasdc1                             partition 519924    0         -2
```

Device with higher priority will be used first, if full, device next in priority is used. If using defaults, the first VDISK (101, **/dev/dasdb1**) gets priority -1 and second VDISK (102, **/dev/dasdc1**) with priority -2 is used after the first is full. You can also specify **pri=nn** in **/etc/fstab** for swap devices.

4. Shutdown your master image from the SSH session. Next you will install the controller image.

```
# shutdown -h now
```

Congratulations! You have now successfully installed the master image. This image will normally be shut down or quiesced. It is now time to install the controller Linux image which will normally be running.

7.5.15 Red Hat bug 224257 workaround

There is a significant bug in the RHEL 5 installer whereby the root file system does not get properly identified as Linux native. For details, see the Red Hat Bugzilla bug 224257:

https://bugzilla.redhat.com/bugzilla/show_bug.cgi?id=224257

Use the **fdasd** command against the root file system. You will get a warning that you can heavily damage your system. This is true, but modifying just the partition type will not cause damage. The partition needs to be set to Linux native for installation of the controller to be successful:

```
# fdasd /dev/dasda
```

```
WARNING: Your DASD '/dev/dasda' is in use.
        If you proceed, you can heavily damage your system.
        If possible exit all applications using this disk
        and/or unmount it.
```

```
reading volume label ...: VOL1
reading vtoc .....: ok
```

Use the **p** subcommand to print the partition table of /dev/dasda:

```
Command action
m  print this menu
p  print the partition table
n  add a new partition
d  delete a partition
v  change volume serial
t  change partition type
r  re-create VTOC and delete all partitions
u  re-create VTOC re-using existing partition sizes
s  show mapping (partition number - data set name)
q  quit without saving changes
w  write table to disk and exit
```

Command (m for help): **p**

```
Disk /dev/dasda:
cylinders .....: 3338
tracks per cylinder ..: 15
blocks per track .....: 12
bytes per block .....: 4096
volume label .....: VOL1
volume serial .....: 0X0100
max partitions .....: 3
```

```
----- tracks -----
      Device      start    end  length  Id  System
/dev/dasda1        2    50069   50068   1  unknown
```

If the bug exists in the installer, /dev/dasda1 will be of type unknown. If you see a type of Linux native, you can type **q** to quit and proceed with the next section.

Use the **t** subcommand to change the file system type of /dev/dasda1:

Command (m for help): **t**

```
Disk /dev/dasda:
cylinders .....: 3338
tracks per cylinder ..: 15
```

```

blocks per track .....: 12
bytes per block .....: 4096
volume label .....: VOL1
volume serial .....: 0X0100
max partitions .....: 3

```

```

----- tracks -----
      Device      start      end  length  Id  System
      /dev/dasda1      2    50069   50068   1  unknown

```

Type **1** to choose the only partition, then type **1** again to set the type to Linux native:

```

change partition type
partition id (use 0 to exit): 1

current partition type is: unknown

  1  Linux native
  2  Linux swap
  3  Linux raid

```

```

new partition type: 1

```

Type **w** to write the modified partition table. This will not damage the master image file system, but will allow it to be properly mounted over `/rhe15master/` when installing the controller:

```

Command (m for help): w
writing VTOC...
rereading partition table...

fdasd error: IOCTL error
Error while rereading partition table.
Please reboot!

```

You can now shutdown the master image:

```

# shutdown -h now
...

```

The partition type of `/dev/dasda1` should now be correct.

7.6 Installing the controller

In this section you will install the controller Linux image.

1. **Logon to RHEL5** or resume your 3270 session. You should see messages as a result of the master image being shut down.

```

...
Power down.
01: HCPGSP2629I The virtual machine is placed in CP mode due to a SIGP stop fro
CPU 00.
00: HCPGSP2630I The virtual machine is placed in CP mode due to a SIGP stop and
store status from CPU 00.

```

2. At this point you could IPL CMS to run the **RHEL5 EXEC** again. To review, this EXEC purges the reader, punches the three bootstrap files and IPLs from the reader. Since the same three files should be in your reader, you can save some time by simply IPLing from the reader at virtual address 00C. Think of it as booting your PC from a floppy disk:

```

==> #cp def stor 512m

```

```
==> #cp ip1 00c
00: 0000003 FILES CHANGED
```

```
Linux version 2.6.18-8.el5 (brewbuilder@spark.z900.redhat.com) (gcc version 4.1.
1 20070105 (Red Hat 4.1.1-52)) #1 SMP Fri Jan 26 14:16:44 EST 2007
We are running under VM (64 bit mode)
...
```

3. **Install Linux again** as described in “Installing the master image” on page 95. However, more disks will be used. The root file system of the master image is /dev/dasda1 (minidisk 100). For the controller install, you will set the master image to be mounted as a file system over the directory /rhe15master/. In addition to a root file system, a separate minidisk for /backup/ and a logical volume for /nfs/ are recommended. The following table is a summary:

Table 7-2 Controller disk partitioning

minidisk	Linux device	Format	Mount Point	Notes
100	/dev/dasda1	No!!	/rhe15master	master image - don't format!
101	/dev/dasdb1	N/A	swap	Swap space - set after install
102	/dev/dasdc1	N/A	swap	Swap space - set after install
200	/dev/dasdd1	As ext3	/	Controller root file system
203	/dev/dasde1	As ext3	/backup	For backup of z/VM and Linux files
204	/dev/dasdf1		/nfs	Physical volume 1/4 for logical volume
205	/dev/dasdg1		/nfs	Physical volume 2/4 for logical volume
206	/dev/dasdh1		/nfs	Physical volume 3/4 for logical volume
207	/dev/dasdi1		/nfs	Physical volume 4/4 for logical volume

4. You should see the window that allows you to partition disks as shown in Figure 7-12 on page 118.




Figure 7-12 Choosing custom layout

5. select **Choose Custom Layout** from the dropdown menu, then click **Next**.
6. The next window should show your disks as shown in Figure 7-13 on page 119.




Figure 7-13 Disk partitioning window

7. You should see /dev/dasda1 as an ext3 file system (Important: if this shows that /dev/dasda is a Physical Volume (PV), this is due to a bug in the installer. You must end this install and set the partition type of /dev/dasda1 to be Linux Native as described in section 7.5.15, “Red Hat bug 224257 workaround” on page 115).
8. Double-click /dev/dasda1, set the *Mount Point* to **/rhel5master**, accept the default of Leave Unchanged (preserve data) and click **OK**. This will mount the master image’s root file system.
9. Double-click **Free** under /dev/dasdd, set the *Mount Point* to **/**, accept the default *File Sytem Type* of ext3 and click **OK**. This will be the root file system of the controller.
10. Double-click **Free** under /dev/dasde, set the *Mount Point* to **/backup**, accept the default *File Sytem Type* of ext3 and click **OK**.
11. Double-click **Free** under /dev/dasdf, set the *File Sytem Type* to **Physical Volume (LVM)** and click **OK**.
12. Repeat the previous step for /dev/dasdg, /dev/dasdh and /dev/dasdi. This will give you four volumes to create a logical volume.
13. Click the **LVM** button in the upper right. The *Make LVM Volume Group* window should appear.
14. Accept the default *Volume Group Name* of VolGroup00. Click the **Add** button on the right. The *Make Logical Volume* window should appear as shown in Figure 7-13 on page 119.




Figure 7-14 Configuring a logical volume

15. Back in the *Make LVM Volume Group* window, click **OK**.
16. Back in the partitioning window, click **Next**. You will be warned about not having a swap space. Click **Yes**.
17. In the window that follows, set the fully qualified DNS host name and click **Next**.
18. Set the time zone information and click **Next**.
19. Set the root password and click **Next**.
20. In the Software window, click the **Customize Now** radio button and click Next.
21. To install a minimal image, choose only **Base** and **X Window System** as you did on the controller, and click **Next**.
22. Click **Next** to begin the installation. The installation will continue for a number of minutes. When it is complete, click **Next** and the VNC viewer session will end.
23. Back on you 3270 session, reboot (reIPL) minidisk 200 (the controller), not 100 (the master).

After the system has booted, **login as root** and add the **ARP=no** parameter to the eth0 config file as follows:

```
# echo ARP=no >> /etc/sysconfig/network-scripts/ifcfg-eth0
```

Bring the interface down with the **ifdown** command and back up with the **ifup** command:

```
# ifdown eth0
# ifup eth0
```

Now the network should be available. **Start an SSH session** to confirm. You may see a warning from PuTTY about a “POTENTIAL SECURITY BREACH”. This is expected because a new set of SSH keys were generated for the same IP address the second time you installed. Click **Yes** to begin the session.

7.6.1 Verifying the installation

Verify some settings via the **mount** and **df -h** commands. You should see output similar to the following:

```
# mount
/dev/dasdd1 on / type ext3 (rw)
proc on /proc type proc (rw)
sysfs on /sys type sysfs (rw)
devpts on /dev/pts type devpts (rw,gid=5,mode=620)
/dev/dasdg1 on /backup type ext3 (rw)
tmpfs on /dev/shm type tmpfs (rw)
/dev/mapper/VolGroup00-LogVol100 on /nfs type ext3 (rw)
none on /proc/sys/fs/binfmt_misc type binfmt_misc (rw)
sunrpc on /var/lib/nfs/rpc_pipefs type rpc_pipefs (rw)
/dev/dasda1 on /rhel5master type ext3 (rw)
```

This shows file systems mounted over /, /backup/, /nfs/ and /rhel5master/.

```
# df -h
Filesystem              Size  Used Avail Use% Mounted on
/dev/dasdd1              2.3G  1.1G  1.1G  49% /
/dev/dasdel              2.1G   68M  1.9G   4% /backup
tmpfs                   250M     0  250M   0% /dev/shm
/dev/mapper/VolGroup00-LogVol100
                        8.9G  149M  8.3G   2% /nfs
/dev/dasda1              2.3G  1.1G  1.1G  50% /rhel5master
```

This shows that the root file system is about half full.

7.7 Configuring the controller

Now that your controller is installed, it must be configured. The following steps are involved:

- ▶ “Copying files to the controller” on page 122
- ▶ “Retire the PC NFS server” on page 123
- ▶ “Configuring swap spaces” on page 123
- ▶ “Configuring yum” on page 123
- ▶ “Adding additional RPMs” on page 123
- ▶ “Turning off unneeded services” on page 124
- ▶ “Configuring the VNC server” on page 125
- ▶ “Turning on the NFS server” on page 125
- ▶ “Turning on the NTP server” on page 125
- ▶ “Setting system to halt on SIGNAL SHUTDOWN” on page 126
- ▶ “Configuring SSH keys” on page 126
- ▶ “Inserting the vmcp module” on page 127
- ▶ “Configuring Apache for DAZL” on page 127
- ▶ “Rebooting the system” on page 130

7.7.1 Copying files to the controller

It is now time to copy the RHEL 5 install tree to the controller, along with other files associated with this book. First mount the directory `/nfs/rhe15/` on the PC NFS server over the directory `/mnt/`. In this example the PC NFS server is at IP address 129.40.46.206:

```
# mount <129.40.46.206>:/nfs/rhe15 /mnt
# ls /mnt
EULA                README-or.html      RELEASE-NOTES-ja.html
...
```

Now create a local directory of the same name and recursively copy the tree via the `cp -a` command:

```
# mkdir /nfs/rhe15
# cd /mnt
# cp -a * /nfs/rhe15
```

This command will take some time, perhaps 5-10 minutes depending on network speeds.

Now unmount the RHEL 5 install tree and repeat the process to copy the files associated with this book:

```
# cd /
# umount /mnt
# mount <129.40.46.206>:/nfs/virt-cookbook-RH5 /mnt
# mkdir /nfs/virt-cookbook-RH5
# cd /mnt
# cp -a * /nfs/virt-cookbook-RH5
```

Now that the files are copied, you can unmount the `/mnt/` directory. Then view the files that you copied:

```
# cd /nfs/virt-cookbook-RH5
# umount /mnt/
# ls
README.txt  sitar-1.0.7-270.1.noarch.rpm      vm/
rsyncd.conf virtcook-controller-1-RH5.s390x.rpm
```

The RPM `virtcook-controller-1-rhe15.s390x.rpm`, contains files for use on the controller. The controller RPM contains the following:

```
# rpm -qlp virtcook-controller-1-RH5.s390x.rpm
/backup/linux
/backup/vm
/etc/cron.daily/nightly.sh
/sbin/backupLinux.sh
/sbin/backupVM.sh
/sbin/clone.sh
/sbin/getVMinfo.sh
/var/www/cgi-bin/catSitar.sh
/var/www/cgi-bin/dazd.sh
/var/www/cgi-bin/dazl.sh
...
/var/www/html/editLog.js
/var/www/html/index.html
/var/www/html/xhr.js
```


The first two entries are empty directories created for backup purposes. Each of the remaining files will be addressed in the sections that follow. From the controller, install the RPM with the following command:

```
# rpm -Uvh virtcook-controller-1-RH5.s390x.rpm
Preparing... ##### [100%]
1:virtcook-controller ##### [100%]
```

7.7.2 Retire the PC NFS server

You have now copied all files related to this book to the controller and you have set the master image automount configuration file to point to it. You should be in a position to retire your PC NFS server, if you desire.

7.7.3 Configuring swap spaces

Turn on the two swap spaces just as you did in section 7.5.1, “Configuring VDISK swap” on page 106.

7.7.4 Configuring yum

You will again configure **yum** so it can install RPMs from automounted install tree. Note that the configuration is identical to the master image because in both instances the install tree is in the directory `/nfs/rhel5/`. However on the controller this directory is local, while on the master image (and later the clones) the directory is automounted.

Create a file named `rhel5.repo` in the `/etc/yum.repos.d` directory:

```
# cd /etc/yum.repos.d
# vi rhel5.repo
[RHEL5]
name=Red Hat Enterprise Linux 5
baseurl=file:///nfs/rhel5/Server
```

Import the RPM key:

```
# cd /nfs/rhel5
# rpm --import RPM-GPG-KEY
```

Note: For a RHEL 5 beta distribution, use the command `rpm --import RPM-GPG-KEY-redhat-beta`

7.7.5 Adding additional RPMs

It is recommended that you install the same packages as you did on the master image. Refer back to “Configuring automount of install tree” on page 107 and “Adding additional RPMs” on page 108. Since you just copied the install tree from the PC NFS server to the controller, you can point **yum** to the new `/nfs/rhel5/` directory.

Use the `yum -y install` command to install the `openmotif` and `xinetd` packages from the local RPM repository and the `rpm -Uvh` command to install the `sitar` package:

```
# yum -y install openmotif xinetd
...
# cd /nfs/virt-cookbook-RH5
# rpm -Uvh sitar-1.0.7-270.1.noarch.rpm
Preparing... ##### [100%]
1:sitar ##### [100%]
```

Important: if you get an error of the following form:

```
Resolving Dependencies
--> Populating transaction set with selected packages. Please wait.
---> Downloading header for openmotif to pack into transaction set.
media://1169877309.407096%233/openmotif-2.3.0-0.3.el5.s390x.rpm: [Errno 4] IOError:
<urlopen error unknown url type: media>
Trying other mirror.
Error: failed to retrieve openmotif-2.3.0-0.3.el5.s390x.rpm from RHEL5
error was [Errno 4] IOError: <urlopen error unknown url type: media>
```

There is a problem. The repository can be built to workaround this problem. First the createrepo RPM must be installed:

```
# cd /nfs/rhel5/Server/
# rpm -Uvh createrepo-0.4.4-2.fc6.noarch.rpm
warning: createrepo-0.4.4-2.fc6.noarch.rpm: Header V3 DSA signature: NOKEY, key ID
37017186
Preparing...                               ##### [100%]
1:createrepo                               ##### [100%]
```

Now, rename the repodata/ directory and create a new one via the **createrepo** command:

```
# mv repodata/ repodata.orig
# createrepo .
844/2495 -
jakarta-commons-collections-testframework-javadoc-3.1-6jpp.1.s390x.rpm
rsh-server-0.17-37.el5.s390x.rpm
Saving Primary metadata
Saving file lists metadata
Saving other metadata
```

The new repository should work for any **yum** operations, but if you ever want to reinstall with this tree, replace the repodata/ with repodata.orig/.

7.7.6 Turning off unneeded services

As with the master image, follow the steps in “Turning off unneeded services” on page 109. Following is a summary:

```
# chkconfig cups off
# chkconfig iptables off
# chkconfig ip6tables off
# chkconfig auditd off
# chkconfig haldaemon off
# chkconfig atd off
# chkconfig kudzu off
# chkconfig mdmonitor off
# chkconfig rpcgssd off
# chkconfig rpcidmapd off
# chkconfig anacron off
# chkconfig mcstrans off
# chkconfig yum-updatesd off
```

7.7.7 Configuring the VNC server

Follow the same steps as described in 7.5.7, “Configuring the VNC server” on page 110, with a small difference, you don’t have to remove `/root/.vnc/passwd` file at the end.

7.7.8 Turning on the NFS server

The NFS server will be needed to export the RHEL 5 install tree and the files associated with this book to the other virtual servers. Enable NFS as follows:

```
# vi /etc/exports
/nfs/rhel5          *(ro,sync)
/nfs/virt-cookbook-RH5 *(ro,sync)
```

These two lines will cause NFS to export:

- The `/nfs/rhel5/` directory, which contains the Red Hat Enterprise Linux 5 installation.
- The `/nfs/virt-cookbook-RH5/` directory, which has the files associated with this book.

Set the NFS server to start at boot time and for this session.

```
# chkconfig nfs on
# service nfs start
Starting NFS services: [ OK ]
Starting NFS quotas: [ OK ]
Starting NFS daemon: [ OK ]
Starting NFS mountd: [ OK ]
```

You could test mounting the directories locally if you choose to.

7.7.9 Turning on the NTP server

It is desirable to have all the system clocks on your Linux images be the same. This can be accomplished by setting up a time server on the controller, and have the other virtual servers synchronize their times against the controller. The controller’s time can be set accurately by having it synchronize against public time servers on the Internet. If you do want to access an external public time server, then make sure your firewall allows traffic through between the controller and the public time servers on the well-known NTP port, 123.

There are basically two possibilities how to connect to public NTP servers on Internet. Either choosing random servers from public list (your system will be then synchronized against only those servers) or using pool of NTP servers. Using the pool of servers is recommended to avoid the so called *public server abuse*. You can read more on this at:

<http://www.pool.ntp.org/>

Test to see that the pool of servers is indeed accessible by use the `ntpdate` command:

```
# ntpdate pool.ntp.org
22 Dec 10:46:12 ntpdate[32170]: step time server 209.223.236.234 offset -60.787960 sec
```

Start the `ntpd` server on the controller at boot time via the `chkconfig` command and for this session via the `service` command:

```
# chkconfig ntpd on
# service ntpd start
Starting ntpd: [ OK ]
```

If you immediately run `ntptrace`, you might see that your time server is stratum 16 which means that the clock is not set accurately:

```
# ntptrace
```

```
localhost: stratum 16, offset 0.000000, synch distance 0.001170
```

After you start **ntpd**, you will have to wait some time for the clock to be adjusted. Use the **ntpq** command with the **peers** subcommand to show the two NTP servers that were set in the `/etc/ntp.conf` file:

```
# ntpq
ntpq> peers
remote          refid          st t when poll reach  delay  offset jitter
=====
alien.astrosmo. 38.14.160.172    2 u  61  64    3 124.862   2.762   3.920
163.25.109.18   140.112.4.189   2 u  61  64    3 301.322 -51.900   3.696
uicsgtw.cs.ui.a .INIT.          16 u   -  64    0   0.000   0.000 4000.00
ntpq> quit
```

You will see different IP addresses because pool of servers is random. After a few minutes (can take up to half an hour), the **ntptrace** command should show that your system is now a stratum 2 server:

```
# ntptrace
localhost: stratum 2, offset -0.002555, synch distance 0.006114
...
```

7.7.10 Setting system to halt on SIGNAL SHUTDOWN

Again, RHEL5 reboots when a Ctrl-Alt-Del key sequence is trapped. This key sequence is simulated by z/VM when a **SIGNAL SHUTDOWN** command is issued. Rather than rebooting, you want your system to halt (shutdown). Change this setting by changing **shutdown -r** to **shutdown -h** in the `/etc/inittab` file:

```
# cd /etc
# vi inittab    // change shutdown -r to shutdown -h
...
# Trap CTRL-ALT-DELETE
ca::ctrlaltdel:/sbin/shutdown -t3 -h now
...
```

This change will be picked up when the system is rebooted.

7.7.11 Configuring SSH keys

SSH sessions are typically authenticated via passwords typed in from the keyboard. With SSH *key-based authentication* sessions can be authenticated via public and private keys so that no password is needed. To accomplish this, the following must be true:

- ▶ The SSH server must have the client's public key.
- ▶ The SSH client must send its private key.
- ▶ The keys must match.

SSH key-based authentication can be set up from the controller (client) to the virtual servers. If the master image has a copy of controller's public key in the file `/etc/ssh/authorized_keys`, and the controller has a symbolic link to its private key in the file `/root/.ssh/id_dsa`, then key based authentication will work to the cloned virtual servers.

Create a new DSA key in the directory `/etc/ssh/`:

```
# cd /etc/ssh
# ssh-keygen -t dsa -P "" -f id_dsa
Generating public/private dsa key pair.
Your identification has been saved in id_dsa.
```

```

Your public key has been saved in id_dsa.pub.
The key fingerprint is:
c1:98:6e:c1:48:52:80:56:98:be:67:aa:1d:d5:76:95 root@lat127.pbm.ihost.com

```

This creates a key pair where the file with the .pub suffix is the public key and the other file is the private key. Note that the private key is only readable by root:

```

# ls -l id_dsa*
-rw----- 1 root root 668 Dec 22 13:47 id_dsa
-rw-r--r-- 1 root root 615 Dec 22 13:47 id_dsa.pub

```

Create a new directory on the master image where the public key will be copied:

```
# mkdir /rhe15master/root/.ssh
```

Copy the public key with the name authorized_keys:

```
# cp id_dsa.pub /rhe15master/root/.ssh/authorized_keys
```

Make a symbolic link to the private key, id_dsa, in the new directory /root/.ssh/:

```

# mkdir /root/.ssh
# cd /root/.ssh
# ln -s /etc/ssh/id_dsa

```

7.7.12 Inserting the vmcp module

To issue CP commands the vmcp module is needed. By default it is not loaded at boot time. One way to accomplish this is to add the **modprobe vmcp** command, which will insert the module, to the file /etc/rc.d/rc.local which is run at boot time:

```

# cd /etc/rc.d
# vi rc.local // add one line
...
touch /var/lock/subsys/local
modprobe vmcp

```

The **vmcp** command will now be available after the next reboot.

7.7.13 Configuring Apache for DAZL

A working Apache Web server is needed for the Web application named *Data About z/VM and Linux (DAZL)*. For details on this application, see section 13.5, “Monitoring z/VM and Linux via a Web application” on page 211. Because this application exposes sensitive data, the entire Web site should be secured. To accomplish this, a valid user ID/password pair should be required to get to the Web site.

Installing Apache

First, install the Apache Web server RPMs via the **yum -y install** command:

```

# yum -y install httpd httpd-manual
...
Running Transaction
  Installing: apr ##### [1/5]
  Installing: postgresql-libs ##### [2/5]
  Installing: apr-util ##### [3/5]
  Installing: httpd ##### [4/5]
  Installing: httpd-manual ##### [5/5]

```

```
Installed: httpd.s390x 0:2.2.3-6.el5 httpd-manual.s390x 0:2.2.3-6.el5
```

```
Dependency Installed: apr.s390x 0:1.2.7-10 apr-util.s390x 0:1.2.7-3
postgresql-libs.s390x 0:8.1.4-1.1
Complete!
```

Securing the Web site

Now that the Apache RPMs are installed, it is recommended that you secure the Web site because the DAZL application exposes much sensitive data. Create a password file that Apache will use to secure the Web site. The **htpasswd** command is used to create a password file named **.htpasswd** in Apache's default DocumentRoot directory, **/var/www/html/**.

Change to the document root directory where you should see three files that were installed with the controller RPM. These are part of the DAZL application:

```
# cd /var/www/html
# ls
editLog.js index.html xhr.js
```

Create a password file for root via the **htpasswd** command:

```
# htpasswd -c .htpasswd root
New password:
Re-type new password:
Adding password for user root
```

Once the password file is created, the configuration file **/etc/httpd/conf/httpd.conf** is modified so the DocumentRoot Directory statement will require valid credentials in this password file. Make a backup copy of the file then add four lines and optionally one comment:

```
# cd /etc/httpd/conf
# cp httpd.conf httpd.conf.orig
# vi httpd.conf // Add 4 lines and one comment to require correct user ID and password
... // around line 300
<Directory "/var/www/html">
...
# AllowOverride controls what directives may be placed in .htaccess files.
# It can be "All", "None", or any combination of the keywords:
# Options FileInfo AuthConfig Limit
#
    AllowOverride None

# add 4 - make this a restricted Web site
    AuthType Basic
    AuthName "This is a restricted Web site"
    AuthUserFile /var/www/html/.htpasswd
    Require user root

#
# Controls who can get stuff from this server.
#
    Order allow,deny
    Allow from all

</Directory>
...
```

Allowing Apache to run CP and SSH commands

The DAZL application uses CP commands via the **vmcp** command to get z/VM data, and the **ssh** command with key-based authentication to get Linux data. By default the **httpd** service runs as the user **apache** which does not have the permission to run these commands. In order to authorize the Web server to do this, two changes must be made

- The **sudo** command is used to allow access to **vmcp** and **ssh**
- SELinux is set to permissive mode

Attention: It is possible to configure SELinux to allow sudo access while still in enforcing mode, but somewhat complicated. If you want to leave SELinux in enforcing mode, see the following related Web page on how to allow **sudo** commands:

http://kbase.redhat.com/faq/FAQ_49_6086.shtm

Modify the `/etc/sudoers` configuration file to allow this access. This is done via the **visudo** command so the configuration file is locked. The line with the **requiretty** directive (around line 56) must be commented as the Web server cannot run from a TTY. Then two lines must be added at the bottom of the file to allow the apache uid to run **vmcp** and **ssh**:

```
# cd /etc
# cp sudoers sudoers.orig
# visudo // Comment "requiretty" near line 56 and add three lines at the bottom
...
# Defaults    requiretty
...
## Allows members of the users group to shutdown this system
# %users    localhost=/sbin/shutdown -h now

# allow www group to run vmcp and ssh so Apache2 can populate DAZL pages
apache     ALL=NOPASSWD:/sbin/vmcp
apache     ALL=NOPASSWD:/usr/bin/ssh
```

Make a backup copy of the file `/etc/selinux/config` and change the SELINUX variable from enforcing to permissive:

```
# cd /etc/selinux
# cp config config.orig
# vi config
# This file controls the state of SELinux on the system.
# SELINUX= can take one of these three values:
#     enforcing - SELinux security policy is enforced.
#     permissive - SELinux prints warnings instead of enforcing.
#     disabled - SELinux is fully disabled.
SELINUX=permissive
# SELINUXTYPE= type of policy in use. Possible values are:
#     targeted - Only targeted network daemons are protected.
#     strict - Full SELinux protection.
SELINUXTYPE=targeted
```

Now Apache should be able to run **vmcp** and **ssh** commands via **sudo**.

Setting ownership of Linux backup directories

In order for DAZL to be able to update the description/log files of each virtual server, the Apache Web server will need permission to write to those files. Apache runs as the group named **apache** so one way to allow this is via the group write and setuid bits. Use the following **chgrp** and **chmod** commands to accomplish this:

```
# cd /backup
# chgrp apache linux
# chmod g+ws linux
```

The **chgrp** command sets the group owner of the directory `/backup/linux/` to **apache**. Setting the group write (g) bit gives that group write permissions and setting the group setuid (s) bit pushes that permission down to newly created directories.

Starting Apache

First stop the firewall if it is running

```
# service iptables stop
```

Start Apache for this session with the **httpd** service script. Also, use the **chkconfig** command so that the Apache Web server starts when the system is booted:

```
# service httpd start
Starting httpd: [ OK ]
# chkconfig httpd on
```

Now the Apache Web server will start and will require the specified user ID/password pair for anyone to get access. Point a browser to the IP address of the controller. You should be prompted for credentials. The following figure shows the prompt window from a FireFox browser:




Figure 7-15 Browser prompting for credentials

When you supply the correct credentials, you should see the DAZL home page as shown in Figure 7-16:




Figure 7-16 DAZL home page

You should now have Apache configured for DAZL. Before you create any clones, there is not a lot that this application will do for you. You can utilize this application later in the book in section 13.5, “Monitoring z/VM and Linux via a Web application” on page 211.

7.7.14 Rebooting the system

You should now reboot the system to test the changes:


```
# reboot
```

After your system comes back in a couple of minutes, start a new SSH session to the controller.

7.7.15 Verifying the changes

You are now done customizing the controller Linux image. **SSH back into the controller** and check a few settings. Test the **vmcp** command with a CP command such as **QUERY NAMES**:

```
# vmcp q n
FTPSEVE - DSC , DTCVSW2 - DSC , DTCVSW1 - DSC , TCPIP - DSC
OPERSYMP - DSC , DISKACNT - DSC , EREP - DSC , OPERATOR - DSC
RHEL5 - DSC
VSM - TCPIP
```

Confirm that both of your swap spaces are operational:

```
# swapon -s
```

Filename	Type	Size	Used	Priority
/dev/dasdb1	partition	259956	0	-1
/dev/dasdc1	partition	519924	0	-2

Verify the NFS server is running:

```
# service nfs status
rpc.mountd (pid 6776) is running...
nfsd (pid 6770 6769 6768 6767 6766 6765 6764 6763) is running...
rpc.rquotad (pid 6748) is running...
```

Congratulations! You have installed and configured Linux twice onto the RHEL5 user ID. You are now ready to clone the master image to a new virtual server.

Configuring RHEL 5 for cloning

It has become appallingly obvious that our technology has exceeded our humanity.

--Albert Einstein

The RHEL5 user ID is now customized with both a master image and a controller. The controller should now be running. In this chapter, you will perform the following steps:

- ▶ “Defining a new user ID for a virtual server” on page 133
- ▶ “Cloning a virtual server manually” on page 136
- ▶ “Cloning a virtual server automatically” on page 140
- ▶ “Cloning five more virtual servers” on page 142

8.1 Defining a new user ID for a virtual server

In this section you will define a new user ID, LINUX01, in z/VM and clone the master image to it.

1. Logon to MAINT and edit the USER DIRECT file to add more Linux ID's.

```
==> x user direct c
```

2. Go to the bottom of the file and add the following 5 lines. In this example the user ID will be LINUX01 with a password of LNX4VM. It will default to have 256MB of memory but can be set up to 1GB. It will have only G permission (General user) It will have a 3338 cylinder (about 2.2 GB) minidisk for the root file system. In this example it is at device address A740 which was formatted and given a label of MMA740 earlier:

```
USER LINUX01 LNX4VM 256M 1G G
INCLUDE LNXDFLT
OPTION APPLMON
MDISK 100 3390 0001 3338 <MMA740> MR LNX4VM LNX4VM LNX4VM
```

3. Add the new volume to the \$ALLOC\$ user ID so cylinder 0 won't show up in the disk map as a gap. Save your changes with the **FILE** subcommand:

```
====> top
====> /alloc
USER $ALLOC$ NOLOG
MDISK A01 3390 000 001 MVA700 R
```

```
...
MDISK A0B 3390 000 001 <MMA740> R
====> file
```

4. Again check for gaps and overlaps. You can use the **ALL** subcommand with the logical OR operator "|" to check for both strings. You should see only one 501 cylinder gap.

```
==> diskmap user
==> x user diskmap
====> all /gap/|/overlap/
----- 4 line(s) not displayed -----
                                0          500          501      GAP
----- 368 line(s) not displayed -----
====> quit
```

5. Bring the changes online with the **DIRECTXA** command:

```
==> directxa user
z/VM USER DIRECTORY CREATION PROGRAM - VERSION 5 RELEASE 2.0
EOJ DIRECTORY UPDATED AND ON LINE
```

The new Linux user ID has now been defined.

8.1.1 Adding LINUX01 to AUTOLOG1's PROFILE EXEC

The new Linux ID you defined needs access to the VSWITCH. A **SET VSWITCH** command with the **GRANT** parameter can be added to AUTOLOG1's **PROFILE EXEC** to do this. Also, an **XAUTOLOG** statement can be added if the user ID is automatically logged on at z/VM IPL time:

Link and access the AUTOLOG1 191 disk read/write and edit the file **PROFILE EXEC**. Add LINUX01 to the sections that grant access to the VSWITCH and that **XAUTOLOG** the Linux user IDs:

```
==> link autolog1 191 1191 mr
==> acc 1191 f
==> x profile exec f // add two lines
/*****/
/* Autolog1 Profile Exec */
/*****/
'cp xautolog tcpip' /* start up TCPIP */
'CP XAUTOLOG DTCVSW1' /* start VSWITCH controller 1 */
'CP XAUTOLOG DTCVSW2' /* start VSWITCH controller 2 */
'cp set pf12 ret' /* set the retrieve key */
'cp set mdc stor 0m 128m' /* Limit minidisk cache in CSTORE */
'cp set mdc xstore 0m 0m' /* Disable minidisk cache in XSTORE */
'cp set srm storbuf 300% 250% 200%' /* Overcommit memory */
'cp set signal shutdown 180' /* Allow guests 3 min to shut down */

/* Grant access to VSWITCH for each Linux user */
'cp set vswitch vsw1 grant rhel5'
'cp set vswitch vsw1 grant linux01'

/* XAUTOLOG each Linux user that should be started */
'cp xautolog rhel5'
'cp xautolog linux01'

'cp logoff' /* logoff when done */
====> file
```

These changes will not take effect until the next IPL, so you must grant this user ID access to the VSWITCH for this z/VM session. This is done as follows:

```
==> set vswitch vsw1 grant LINUX01
Command complete
```

8.1.2 Creating a parameter file for the new LINUX ID

For each Linux guest you want to clone, you need to create a parameter file. This file specifies many of the installation parameters. It will be used both when cloning to this user ID and when installing RHEL 5 manually.

1. Logon to LNXMAINT.
2. Copy an existing configuration file and edit the new file to apply to the new Linux. If the new Linux is going to be on the same network as the controller you will likely only have to change the HOSTNAME and IPADDR variables:

```
==> copy rhel5 conf-rh5 d linux01 = =
==> x linux01 conf-rh5 d
DASD=100-106
HOSTNAME=lat121.pbm.ihost.com
NETTYPE=qeth
IPADDR=129.40.178.121
SUBCHANNELS=0.0.0600,0.0.0601,0.0.0602
NETWORK=129.40.178.0
NETMASK=255.255.255.0
SEARCHDNS=pbm.ihost.com
BROADCAST=129.40.178.255
GATEWAY=129.40.178.254
DNS=129.40.106.1
MTU=1500
PORTNAME=DONTCARE
```

3. Copy an existing parameter file and edit the new file to apply to the new Linux. Modify the file name of the configuration file.

```
==> copy rhel5 parm-rh5 d linux01 = =
==> x linux01 parm-rh5 d
ramdisk_size=40000 root=/dev/ram0 ro ip=off
CMSDASD=191 CMSCONFFILE=LINUX01.CONF-RH5
vnc vncpassword=lnx4vm
```

4. Logoff of LNXMAINT.
5. Logon to LINUX01.
6. Answer **N** to the question “Do you want to IPL Linux from DASD 100”. Verify that the new Linux user ID has a NIC at addresses 600-602:

```
LOGON LINUX01
00: NIC 0600 is created; devices 0600-0602 defined
00: z/VM Version 5 Release 2.0, Service Level 0601 (64-bit),
00: built on IBM Virtualization Technology
...
```

7. Verify that the minidisk at addresses 100 and the VDISKS at address 101 and 102 are read/write:

```
==> q da
00: DASD 0100 3390 MMA740 R/W      3338 CYL ON DASD  A740 SUBCHANNEL = 0000
00: DASD 0101 9336 (VDSK) R/W     524288 BLK ON DASD  VDSK SUBCHANNEL = 000D
00: DASD 0102 9336 (VDSK) R/W    1048576 BLK ON DASD  VDSK SUBCHANNEL = 000E
00: DASD 0190 3390 MVA700 R/O      107 CYL ON DASD  A700 SUBCHANNEL = 0008
00: DASD 0191 3390 MMA70C R/O      300 CYL ON DASD  A70C SUBCHANNEL = 000B
...
```

8. Logoff LINUX01.

You should now be ready to clone to this new user ID.

8.2 Cloning a virtual server manually

Before using the shell script `clone.sh` to clone a server, it is recommended that you clone a server manually to better understand the process.

There are many ways to clone Linux under z/VM. The steps in this section are just one way to do it. The following assumptions are made based on what you have done so far:

- ▶ The source Linux image has a single root file system on minidisk 100.
- ▶ The target user ID, LINUX01 in this example, has identically sized mindisk 100.
- ▶ The `vmcp` command is available to issue z/VM CP commands
- ▶ The z/VM `FLASHCOPY` command can be used but if you don't have that support, the Linux `dd` command will work.

Given these assumptions, one set of steps that can be used to clone a system is as follows:

1. Link the target disk read/write.
2. Copy the source to the target disk via `FLASHCOPY` or the Linux `dd` command.
3. Mount the newly copied root file system.
4. Modify the networking information on the target system.
5. Detach the target disk.
6. IPL the target system.
7. Modify the SSH keys on the target system.

Link the target disk read/write

Start an SSH session to the controller as root.

The target root file system, LINUX01 100, is linked multi-read (read/write if no other user ID has write access) as virtual device 1100 via the CP `LINK` command:

```
# vmcp link linux01 100 1100 mr
```

Copy the source to the target disk via FLASHCOPY

The two disks are copied via the CP `FLASHCOPY` command:

```
# vmcp flashcopy 100 0 end to 1100 0 end
Command complete: FLASHCOPY 100 0 END TO 1100 0 END
```

Attention: If you do not have **FLASHCOPY** support, you can use the Linux **dasdfmt** and **dd** commands. You must first enable the 1100 disk via the **chccwdev -e 1100** command, then determine the newly created device node via the **lsdasd** command:

```
# chccwdev -e 1100
Setting device 0.0.1100 online
Done
# lsdasd
0.0.0100(ECKD) at (94:0) is dasda : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0101(FBA ) at (94: 4) is dasdb : active at blocksize 512, 524288 blocks, 256 MB
0.0.0102(FBA ) at (94: 8) is dasdc : active at blocksize 512, 1048576 blocks, 512 MB
...
0.0.1100(ECKD) at (94:36) is dasdj : active at blocksize 4096, 600840 blocks, 2347 MB
```

In this example the source minidisk (100) is named **/dev/dasda**, while the target minidisk (1100) is named **/dev/dasdj**. Format the device via the **dasdfmt** command using a 4096 byte (4KB) block size:

```
# dasdfmt -b 4096 -y -f /dev/dasdj
Finished formatting the device.
Rereading the partition table... ok
```

Now that the device has been formatted, you can copy the contents of the master image via the **dd** command, again using a block size of 4K (4096) bytes:

```
# dd if=/dev/dasda of=/dev/dasdj bs=4096
600840+0 records in
600840+0 records out
2461040640 bytes (2.5 GB) copied, 81.2098 seconds, 30.3 MB/s
```

Then bring the device offline so the new file system will be recognized when it is brought back online:

```
# chccwdev -d 1100
Setting device 0.0.1100 offline
Done
```

Mount the newly copied root file system

Enable the new minidisk at virtual device address 1100:

```
# chccwdev -e 1100
Setting device 0.0.1100 online
Done
```

Determine which device node is used.

```
# lsdasd
0.0.0100(ECKD) at (94:0) is dasda : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0101(FBA ) at (94: 4) is dasdb : active at blocksize 512, 524288 blocks, 256 MB
0.0.0102(FBA ) at (94: 8) is dasdc : active at blocksize 512, 1048576 blocks, 512 MB
0.0.0200(ECKD) at (94:12) is dasdd : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0203(ECKD) at (94:16) is dasde : active at blocksize 4096, 543240 blocks, 2122 MB
0.0.0204(ECKD) at (94:20) is dasdf : active at blocksize 4096, 840060 blocks, 3281 MB
0.0.0205(ECKD) at (94:24) is dasdg : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0206(ECKD) at (94:28) is dasdh : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0191(ECKD) at (94:32) is dasdi : active at blocksize 4096, 54000 blocks, 210 MB
0.0.1100(ECKD) at (94:36) is dasdj : active at blocksize 4096, 600840 blocks, 2347 MB
```

In this case, the device node is `/dev/dasdj`. Because there is only one partition in the root file system, it will be `/dev/dasdj1`. Mount it over a newly created mount point `/mnt/linux01`

```
# mkdir /mnt/linux01
# mount /dev/dasdj1 /mnt/linux01
```

Observe that this appears to be a root file system:

```
# ls /mnt/linux01/
bin  dev  home  lib64      media  opt   root  selinux  sys  usr
boot etc  lib   lost+found mnt     proc  sbin  srv      tmp  var
```

Modify networking information on the target system

In this example, the only two pieces of networking information that are modified are the IP address (from 129.40.178.128 to 129.40.178.121) and the host name (from `lat128` to `lat121`).

The host name and IP address are changed in the file `/etc/hosts`:

```
# cd /mnt/linux01/etc
# vi hosts
# Do not remove the following line, or various programs
# that require network functionality will fail.
127.0.0.1          localhost.localdomain localhost
::1               localhost6.localdomain6 localhost6
129.40.178.121     lat121.pbm.ihost.com lat121
```

The host name is changed in the file `/etc/sysconfig/network`:

```
# cd sysconfig
# vi network
NETWORKING=yes
NETWORKING_IPV6=yes
HOSTNAME=lat121.pbm.ihost.com
GATEWAY=129.40.178.254
```

The IP address is changed in the file `/etc/sysconfig/network-scripts/ifcfg-eth0`:

```
# cd network-scripts
# vi ifcfg-eth0
# IBM QETH
DEVICE=eth0
BOOTPROTO=static
IPADDR=129.40.178.121
MTU=1500
NETMASK=255.255.255.0
NETTYPE=qeth
ONBOOT=yes
PORTNAME=DONTCARE
SUBCHANNELS=0.0.0600,0.0.0601,0.0.0602
MTU=1500
ARP=no
```

Detach the target disk

Change to the default directory, use the `sync` command to flush the disks and the `umount` command to unmount the modified root file system:

```
# cd
# sync
# umount /mnt/linux01
```


Set the LINUX01 100 disk offline with the **chccwdev** command and detach it via the CP **DETACH** command:

```
# chccwdev -d 1100
Setting device 0.0.1100 offline
Done
# vmcp det 1100
DASD 1100 DETACHED
```

You should now be ready to IPL the manually cloned system.

IPL the target system

Logon to a 3270 session as LINUX01. CMS will IPL and the **PROFILE EXEC** will ask you if you want to IPL from minidisk 100. Type **y** for yes then you can enter the command **#cp vi vmmsg 0** to select the default Linux image from the boot menu:

```
LOGON LINUX01
ENTER PASSWORD (IT WILL NOT APPEAR WHEN TYPED):

00: NIC 0600 is created; devices 0600-0602 defined
00: z/VM Version 5 Release 2.0, Service Level 0601 (64-bit),
00: built on IBM Virtualization Technology
00: There is no logmsg data
00: FILES: 0003 RDR, NO PRT, NO PUN
00: LOGON AT 16:03:14 EST TUESDAY 12/12/06
z/VM V5.2.0 2006-07-18 08:48

DMSACP723I A (191) R/O
DMSACP723I C (592) R/O
DIAG swap disk defined at virtual address 101 (64989 4K pages of swap space)
DIAG swap disk defined at virtual address 102 (129981 4K pages of swap space)
Do you want to IPL Linux from DASD 100? y/n
y
00: zIPL v1.5.3 interactive boot menu
00:
00: 0. default (linux)
00:
00: 1. linux
00:
00: Note: VM users please use '#cp vi vmmsg <input>'
00:
00: Please choose (default will boot in 15 seconds):
00:
00: CP VI VMMSG 0
00: Booting default (linux)...
Linux version 2.6.18-1.2839.el5 (brewbuilder@devel8.z900.redhat.com) (gcc versio
n 4.1.1 20061130 (Red Hat 4.1.1-43)) #1 SMP Tue Dec 5 22:58:42 EST 2006
We are running under VM (64 bit mode)
Detected 2 CPU's
Boot cpu address 0
...
Red Hat Enterprise Linux Server release 4.92 (Tikanga)
Kernel 2.6.18-1.2839.el5 on an s390x

lat121 login:
```

Your new system should come up cleanly using the modified IP address and host name.

Modify the SSH keys on the target system

Start an SSH session to the new clone as root.

The SSH keys that were copied are identical to those of the master image. Manually create three new ones with the **ssh-keygen** command:

```
# cd /etc/ssh
# ssh-keygen -t rsa -N "" -q -f ssh_host_rsa_key
ssh_host_rsa_key already exists.
Overwrite (y/n)? y
# ssh-keygen -t dsa -N "" -q -f ssh_host_dsa_key
ssh_host_dsa_key already exists.
Overwrite (y/n)? y
# ssh-keygen -t rsa1 -N "" -q -f ssh_host_key
ssh_host_key already exists.
Overwrite (y/n)? y
```

Congratulations! You have now cloned a Linux system manually. You can look around the new system. It should be identical to the master image except for the IP address and host name.

Next you will learn how to do it automatically. You will use the LINUX01 user ID again. To clone, the target user ID must be logged off. You could shut the new system down cleanly, but because you will be cloning again, it does not matter. Go to the 3270 session and log off the LINUX01 user ID:

```
==> #cp log
```

8.3 Cloning a virtual server automatically

Now that you have cloned a server manually and better understand the steps, you can use the **clone.sh** script to clone automatically.

Go back to your an SSH session to the controller. The **clone.sh** script should be in your PATH in the directory `/usr/local/sbin/`. You can verify this with the **which** command:

```
# which clone.sh
/sbin/clone.sh
```

The script takes one parameter which is the Linux user ID that the master image will be cloned to. That user ID must be logged off. It reads the parameter file on the LNXMAINT 192 disk (the controller's 191 disk) to obtain information necessary to give the new Linux virtual server an identity. It calls CP **FLASHCOPY** via the **vmcp** module/command to try to copy the 100 (master image) disks. If **FLASHCOPY** fails, the script falls back to copying the disk via the Linux **dasdfmt** and **dd** commands. The script then boots the new Linux via the **XAUTOLOG** command. It also creates an empty backup directory under `/backup/linux/` and adds the server's public key is added to the controller's `known_hosts` file.

It should take less than a minute to clone with **FLASHCOPY** support and 3-20 minutes without it. Following is an example of cloning to the LINUX01 user ID with **FLASHCOPY** support. The output is divided into sections.

```
# clone.sh linux01
Invoking CP command: QUERY LINUX01
HCPCQU045E LINUX01 not logged on
Error: non-zero CP response for command 'QUERY LINUX01': #45
Setting device 0.0.0191 offline
Done
Setting device 0.0.0191 online
Done
LINUX01 CONF-RH5 D1 F          80          13          1 12/12/2006 13:54:35
```

```

WARNING!!: this will copy disk 100 to LINUX01 100
New host name will be: lat121.pbm.ihost.com
New TCP/IP address will be: 129.40.178.121
Other network data is retrieved from LINUX01 CONF-RH5 on 191 disk
Are you sure you want to overwrite these disks (y/n):

```

In the section of output above, the script makes sure the user ID to be cloned to exists and is logged off. It then searches for the correct PARMFILE and obtains the necessary networking information. It then asks if you are sure you want to overwrite the disks on the target user ID.

```

Please enter a brief description of this server
This is a Web Server running RHEL 5

```

You are then prompted to enter a one line description of the server. This will be saved on the controller in the file /backup/linux/<userid>-on-<tcp.ip.addr>. This file is used by the DAZL Web application:

```

Copying 0100 root file system to LINUX01 ...
Invoking CP command: QUERY VIRTUAL 1100
HCPQVD040E Device 1100 does not exist
Error: non-zero CP response for command 'QUERY VIRTUAL 1100': #40
Invoking CP command: LINK LINUX01 0100 1100 MR

Invoking CP command: FLASHCOPY 0100 0 END 1100 0 END
Command complete: FLASHCOPY 0100 0 END TO 1100 0 END
Invoking CP command: DETACH 1100
DASD 1100 DETACHED
Copying disk via FLASHCOPY succeeded ...
Mounting newly cloned image over /mnt/rhel5cloned ...
Invoking CP command: LINK LINUX01 100 1100 MR

```

In the section above the master image root file system is copied to the LINUX01 100 minidisk via the z/VM **FLASHCOPY** command. Should this fail (for example if you don't have **FLASHCOPY** support), the code will fall back to the **dasdfmt** and **dd** commands to perform the copies, which will take a number of minutes.

```

Setting device 0.0.1100 online
Done
Mounting /dev/dasdm1 over /mnt/rhel5cloned ...
Modifying cloned image under /mnt/rhel5cloned ...
Regenerating SSH keys in /mnt/rhel5cloned/etc/ssh/ ...
Adding 129.40.178.121 to known_hosts file
Setting device 0.0.1100 offline
Done
Invoking CP command: DETACH 1100
DASD 1100 DETACHED

```

In the section above, the newly cloned file system (LINUX01 100) is linked, activated and mounted over a temporary directory /mnt/rhel5cloned/. Then networking information is modified in the files /etc/sysconfig/network, /etc/sysconfig/network-scripts/ifcfg-eth0 and /etc/hosts. Then the SSH keys are regenerated so they are unique for the new virtual server. Then the server's public key is added to the controller's /root/.ssh/known_hosts file. Finally the new disk is set offline and detached.

```

Invoking CP command: XAUTOLOG LINUX01
Command accepted
Successfully cloned /rhel5master to LINUX01
You should be able to ping 129.40.178.121 within one minute

```

In the final section, the target user ID is logged on via **XAUTOLOG**. Because the PROFILE EXEC detects that the ID is logged on in a disconnected mode, Linux is IPLed from minidisk 100. A

directory with the user ID and IP address in the name is created under `/backup/linux/`. The new clone should be on the network in less than a minute.

Note: If the `clone.sh` script fails you can also add the `-v` flag for some more diagnostics. Also, check that:

- ▶ The target user ID has been granted access to the VSWITCH
- ▶ The parameter and configuration files are copied and set correctly on LNXMAINT 192

Following is a block diagram of this process both for the manual clone and using the `clone.sh` script:




Figure 8-1 Cloning block diagram

The left side of the figure shows the controller which is on the RHEL5 200 disk. It has the master image mounted over the directory `/rhel5master/`, which is the RHEL5 100 disk. The VDISK swap spaces, RHEL5 101 and 102, are created in memory, so they do not need to be copied.

The script `/sbin/clone.sh` is invoked and it uses either **CP FLASHCOPY** or the Linux `dd` command to copy the 100 minidisk to the target z/VM user ID. The script then mounts the newly copied 100 disk and modifies the networking information to use those values found in the parameter file on the LNXMAINT 192 disk. The script then invokes the **CP XAUTOLOG** command to log that user ID on. Because the user ID is logged on disconnected, the common **PROFILE EXEC** from the LNXMAINT 192 disk IPLs from virtual device address 100 and the newly cloned Linux system is brought to life.

8.4 Cloning five more virtual servers

So far you have installed Linux manually twice on RHEL5 to create a master image and a controller. You have created a new user ID LINUX01 and cloned it. Now it is time to clone five more times. This will give you six virtual servers described in this book. The seventh virtual server will be created via kickstart in Chapter 9, “Installing Linux with kickstart” on page 149. You will, however, prepare six new user IDs so kickstart will have a user ID to install into.

The following steps are involved:

- ▶ “Formatting and label six new DASD” on page 143
- ▶ “Defining six more user IDs” on page 144

- ▶ “Testing logging on to a new user ID” on page 147
- ▶ “Creating six new parameter files” on page 145
- ▶ “Granting user IDs access to VSWITCH” on page 146

8.4.1 Formatting and label six new DASD

Decide which DASD will be used for the six new user IDs by referring to 2.7.2, “z/VM DASD worksheet” on page 18.

Logon to MAINT. Query the devices that you want to assign as PERM space. In this example the devices are A741-A746:

```
==> q <a741-a746>
DASD A741 ZA712 , DASD A742 ZA742 , DASD A743 ZA743 , DASD A744 ZA744
DASD A745 ZA745 , DASD A746 ZA746
```

Attach the DASD devices to MAINT. When attaching volumes to your own user ID, the * parameter can be used (so in the following example * is expanded to MAINT):

```
==> att <a741-a746> *
A741-A746 ATTACHED TO MAINT
```

Note: if the DASD are already attached to SYSTEM, you have to first detach them. For example **det a741-a746 system**

Now format the DASD for PERM or minidisk space with the **CPFORMAT** command that is associated with this book.

```
==> cpformat <a741-a746> as perm
```

Label the following DASD:

TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A741	MAINT	A741	3390	ZA741	A741	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A742	MAINT	A742	3390	ZAA742	A742	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A743	MAINT	A743	3390	ZAA743	A743	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A744	MAINT	A744	3390	ZAA744	A744	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A745	MAINT	A745	3390	ZAA745	A745	0	3339
TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A746	MAINT	A746	3390	ZAA746	A746	0	3339

ARE YOU SURE you want to format the DASD as PERM space (y/n)?

y

...

A741-A746 DETACHED

A741-A746 ATTACHED TO MAINT

DASD status after:

TargetID	Tdev	OwnerID	Odev	Dtype	Vol-ID	Rdev	StartLoc	Size
MAINT	A741	MAINT	A741	3390	MMA741	A741	0	3339
MAINT	A742	MAINT	A742	3390	MMA742	A742	0	3339
MAINT	A743	MAINT	A743	3390	MMA743	A743	0	3339
MAINT	A744	MAINT	A744	3390	MMA744	A744	0	3339
MAINT	A745	MAINT	A745	3390	MMA745	A745	0	3339
MAINT	A746	MAINT	A746	3390	MMA746	A746	0	3339

You could now shutdown and re-IPL for these new DASD to be attached to the system via the `User_Volume_Include MM*` statement in the `SYSTEM CONFIG` file. However, there is an easier way. Simply **DETACH** the DASD from `MAINT` and **ATTACH** them to `SYSTEM`:

```
==> det <a741-a746>
A741-A746 DETACHED BY MAINT
==> att <a741-a746> system
DASD A741 ATTACHED TO SYSTEM MMA741
DASD A742 ATTACHED TO SYSTEM MMA742
DASD A743 ATTACHED TO SYSTEM MMA743
DASD A744 ATTACHED TO SYSTEM MMA744
DASD A745 ATTACHED TO SYSTEM MMA745
DASD A746 ATTACHED TO SYSTEM MMA746
```

The six DASD volumes will now be available to be used for minidisks in the `USER DIRECT` file. They will also be available after the next IPL because their new labels match the pattern `User_Volume_Include MM*` in the `SYSTEM CONFIG` file.

8.4.2 Defining six more user IDs

Define six more user IDs for Linux virtual servers in the `USER DIRECT` file named `LINUX02` - `LINUX07`. You will need to use the DASD volumes you just formatted: one for each virtual server. You can repeat the definition of `LINUX01` six times with the block copy `""6` prefix command. For example:

```
==> x user direct
====> /user linux01
...
""6 *
01846 USER LINUX01 LNX4VM 256M 1G G
01847 INCLUDE LNXDFLT
01848 OPTION APPLMON
""6 MDISK 100 3390 0001 3338 MMA740 MR LNX4VM LNX4VM LNX4VM
```

This will create six more copies of the `LINUX01`. Modify them to have a user ID of `LINUX02` - `LINUX07`, and give each new ID the proper 3390-3 identified by label (`MMA712`-`MMA746` in this example):

```
USER LINUX02 LNX4VM 256M 1G G
INCLUDE LNXDFLT
OPTION APPLMON
MDISK 100 3390 0001 3338 MMA741 MR LNX4VM LNX4VM LNX4VM
*
USER LINUX03 LNX4VM 256M 1G G
INCLUDE LNXDFLT
OPTION APPLMON
MDISK 100 3390 0001 3338 MMA742 MR LNX4VM LNX4VM LNX4VM
*
...
USER LINUX07 LNX4VM 256M 1G G
INCLUDE LNXDFLT
OPTION APPLMON
MDISK 100 3390 0001 3338 MMA746 MR LNX4VM LNX4VM LNX4VM
```

Go to the top of the file and find the definition for the user `$ALLOC$`. Add dummy definitions for cylinder 0 of each of the new volumes and save the changes:

```
====> top
====> /alloc
USER $ALLOC$ NOLOG
MDISK A01 3390 000 001 520RES R
```

```

...
MDISK A0B 3390 000 001 MMA740 R
MDISK A0C 3390 000 001 MMA741 R
MDISK A0D 3390 000 001 MMA742 R
MDISK A0E 3390 000 001 MMA743 R
MDISK A0F 3390 000 001 MMA744 R
MDISK A10 3390 000 001 MMA745 R
MDISK A11 3390 000 001 MMA746 R
...
====> file

```

Check for overlaps and the single gap. **Quit** out of the USER DISKMAP file:

```

==> diskmap user
==> x user diskmap
====> all /gap/|/overlap/
----- 4 line(s) not displayed -----
                                0      500      501      GAP
----- 368 line(s) not displayed -----
====> quit

```

Bring the changes online with the **DIRECTXA USER** command:

```

==> directxa user
z/VM USER DIRECTORY CREATION PROGRAM - VERSION 5 RELEASE 1.0
EOJ DIRECTORY UPDATED AND ON LINE

```

You have now created six new user IDs that can be cloned to.

8.4.3 Creating six new parameter files

New parameter and configuration files must be created for each of the user IDs with the proper networking information. Link and access the LNXMAINT 192 disk read/write and create six new parameter files for LINUX02 through LINUX06 (LINUX07 will be configured in Chapter 9, “Installing Linux with kickstart” on page 149)

```

==> link lnxmaint 192 1192 mr
==> acc 1192 f
==> copy linux01 parm-rh5 f linux02 = =
==> copy linux01 parm-rh5 f linux03 = =
==> copy linux01 parm-rh5 f linux04 = =
==> copy linux01 parm-rh5 f linux05 = =
==> copy linux01 parm-rh5 f linux06 = =

```

Now create six new configuration files for LINUX02 through LINUX07

```

==> copy linux01 conf-rh5 f linux02 = =
==> copy linux01 conf-rh5 f linux03 = =
==> copy linux01 conf-rh5 f linux04 = =
==> copy linux01 conf-rh5 f linux05 = =
==> copy linux01 conf-rh5 f linux06 = =

```

Edit each of the six parameter files so they point to the appropriate configuration file

```

==> x linux02 parm-rh5 f
ramdisk_size=40000 root=/dev/ram0 ro ip=off
CMSDASD=191 CMSCONFFILE=LINUX02.CONF-RH5
vnc vncpassword=lnx4vm
==> x linux03 parm-rh5 f
...

```

Edit each of the six configuration files, replacing the appropriate network values. It is likely that only the TCP/IP address and host name will need to be modified:

```
==> x linux02 conf-rh5 f
DASD=100-102
HOSTNAME=lat122.pbm.ihost.com
NETTYPE=qeth
IPADDR=129.40.178.122
SUBCHANNELS=0.0.0600,0.0.0601,0.0.0602
NETWORK=129.40.178.0
NETMASK=255.255.255.0
SEARCHDNS=pbm.ihost.com
BROADCAST=129.40.178.255
GATEWAY=129.40.178.254
DNS=129.40.106.1
MTU=1500
PORTNAME=DONTCARE
==> x linux03 conf-rh5 f
...
```

When you are finished, release and detach the LNXMAINT 192 disk.

```
==> rel f (det
DASD 1192 DETACHED
```

8.4.4 Granting user IDs access to VSWITCH

Modify the PROFILE EXEC on AUTOLOG1 191 to grant access to the VSWITCH for the six new user IDs and add **XAUTOLOG** commands so they will be booted when the z/VM system IPLs.

Link and access the AUTOLOG1 191 disk so the file can be modified from MAINT:

```
==> link autolog1 191 1191 mr
==> acc 1191 f
```

Edit the PROFILE EXEC:

```
==> x profile exec f
...
/* Grant access to VSWITCH for each Linux user */
'CP SET VSWITCH VSW1 GRANT RHEL5'
'CP SET VSWITCH VSW1 GRANT LINUX01'
'CP SET VSWITCH VSW1 GRANT LINUX02'
'CP SET VSWITCH VSW1 GRANT LINUX03'
'CP SET VSWITCH VSW1 GRANT LINUX04'
'CP SET VSWITCH VSW1 GRANT LINUX05'
'CP SET VSWITCH VSW1 GRANT LINUX06'
'CP SET VSWITCH VSW1 GRANT LINUX07'

/* XAUTOLOG each Linux user that should be started */
'CP XAUTOLOG RHEL5'
'CP XAUTOLOG LINUX01'
'CP XAUTOLOG LINUX02'
'CP XAUTOLOG LINUX03'
'CP XAUTOLOG LINUX04'
'CP XAUTOLOG LINUX05'
'CP XAUTOLOG LINUX06'
'CP XAUTOLOG LINUX07'
====> file
```


It is easiest to grant access to the new user IDs for the current z/VM session with the **SET VSWITCH** command:

```
==> set vswitch vsw1 grant linux02
Command complete
==> set vswitch vsw1 grant linux03
Command complete
==> set vswitch vsw1 grant linux04
Command complete
==> set vswitch vsw1 grant linux05
Command complete
==> set vswitch vsw1 grant linux06
Command complete
==> set vswitch vsw1 grant linux07
Command complete
```

Verify that the user IDs have access with the **QUERY VSWITCH ACCESSLIST** command:

```
==> query vswitch vsw1 acc
VSWITCH SYSTEM VSW1      Type: VSWITCH Connected: 4 Maxconn: INFINITE
PERSISTENT RESTRICTED   NONROUTER                      Accounting: OFF
VLAN Unaware
State: Ready
IPTimeout: 5             QueueStorage: 8
Portname: UNASSIGNED RDEV: 3004 Controller: DTCVSW1 VDEV: 3004
Portname: UNASSIGNED RDEV: 3008 Controller: DTCVSW2 VDEV: 3008 BACKUP
Authorized userids:
    RHEL5   LINUX01   LINUX02   LINUX03   LINUX04   LINUX05
    LINUX06 LINUX07
    SYSTEM
```

8.4.5 Testing logging on to a new user ID

You should now be able to logon to a new user ID and verify the integrity of the definitions. **Logon to LINUX02** and you should first notice that a NIC is created as well as two VDISKS:

```
LOGON LINUX02
00: NIC 0600 is created; devices 0600-0602 defined
00: z/VM Version 5 Release 2.0, Service Level 0601 (64-bit),
00: built on IBM Virtualization Technology
00: There is no logmsg data
00: FILES: NO RDR, NO PRT, NO PUN
00: LOGON AT 10:17:55 EST WEDNESDAY 12/13/06
z/VM V5.2.0 2006-07-18 08:48

DMSACP723I A (191) R/O
DMSACP723I C (592) R/O
DIAG swap disk defined at virtual address 101 (64989 4K pages of swap space)
DIAG swap disk defined at virtual address 102 (129981 4K pages of swap space)
Do you want to IPL Linux from DASD 100? y/n
n
```

If you forgot to grant access to the VSWITCH you will see an error message. Verify that you have OSA devices at addresses 600-602, :

```
==> q osa
00: OSA 0600 ON NIC 0600 UNIT 000 SUBCHANNEL = 0002
00: 0600 QDIO-ELIGIBLE QIOASSIST-ELIGIBLE
...
```

Verify that you have three read/write devices at addresses 100-102 via the **QUERY DASD** command:

```
==> q da
00: DASD 0100 3390 MMA741 R/W      3038 CYL ON DASD  A719 SUBCHANNEL = 0000
00: DASD 0101 9336 (VDSK) R/W     524288 BLK ON DASD  VDSK SUBCHANNEL = 000E
00: DASD 0102 9336 (VDSK) R/W    1048576 BLK ON DASD  VDSK SUBCHANNEL = 0001
00: DASD 0190 3390 MVA700 R/O      107 CYL ON DASD   A700 SUBCHANNEL = 0009
...
```

Logoff of LINUX02.

Congratulations, you have cloned one Linux virtual server and defined six more user IDs that should now be ready for cloning or kickstarting to. You will clone to these user IDs in the chapters that follow.

8.5 Reviewing system status

You can step back now and view your system from a DASD point of view as shown in Figure 8-2. If you have followed all sections in this book you should have used 24 3390-3 volumes: 10 for your z/VM system, 7 for the Linux controller and master image and one for each of the seven virtual servers.

You can also view the system from an administrator's and end user point of view as shown by the horizontal lines and the italicized text on the right side of the figure. The z/VM and Linux system administration roles may be performed by the same person, but these roles can also be done by different administrators. The Linux end users may not care that their servers are virtual machines and may be oblivious to the fact that they might have been cloned in a matter of minutes.




Figure 8-2 Linux virtual server system - DASD view and role view

Installing Linux with kickstart

Kickstart is an automated way of installing RHEL 5. Using kickstart, you can create a single file that answers all of the questions usually asked during an interactive installation.

In the last chapter, you cloned six new virtual servers, and in this chapter you will kickstart a seventh. In comparison, cloning a server is faster, assuming the FLASHCOPY command is available. However, kickstarting a server is more flexible, as it allows for different package configurations as well as pre-install and post-install scripting.

The controller is now configured as an installation server, with the installation tree shared via NFS. You will now configure it as a kickstart server to perform automated installations over the network. You will then install the final Linux server with kickstart.

The following steps are involved in installing Linux with kickstart:

- ▶ Configure the controller for kickstart
- ▶ Configure the LINUX07 user for kickstart
- ▶ Kickstart the LINUX07 user

9.1 Configure the controller for kickstart

In this section, you configure the controller to host the kickstart file, which you use to perform the automated installation of the Linux virtual server called LINUX07. This section assumes you have already set up the RHEL 5 install tree as described in 7.7, “Configuring the controller” on page 121.

The installer generates a kickstart file at the end of every installation. It is based on the answers provided during the interactive install. This kickstart file is named `anaconda-ks.cfg` and is located in the `/root/` directory. You use this kickstart file from RHEL5 as a template for LINUX07. Perform the following steps:

1. From an Secure Shell (SSH) session to the controller, create a directory to hold the kickstart file. Then, copy the default kickstart file to this directory, rename it, and modify the permissions so others may read it:

```
# mkdir /nfs/ks
# cp /root/anaconda-ks.cfg /nfs/ks/linux07-ks.cfg
# chmod +r /nfs/ks/linux07-ks.cfg
```

- Next, use **vi** to edit the kickstart configuration file. Remove the lines with the ~~strike-through~~, and edit the lines in bold in to customize this kickstart for LINUX01:

```
# vi /nfs/ks/linux07-ks.cfg
install
nfs --server=129.40.178.128 --dir=/nfs/rhel5 1
lang en_US.UTF-8
network --device eth0 --mtu=1500 --bootproto static --ip 129.40.178.127 2
--netmask 255.255.255.0 --gateway 129.40.178.254 --nameserver 129.40.106.1
--hostname linux07.pbm.ihost.com 3
rootpw --iscrypted $1$d6Mi5lj9$jjzwhlKOUK37qXQzTLVRSm.
firewall --disabled 4
authconfig --enableshadow --enablemd5
selinux --enforcing
timezone America/New_York
bootloader --location=mbr driveorder=dasda,dasdd,dasdg,dasdh,dasdi,dasdj,dasdk 5
reboot 6
key --skip 7
# The following is the partition information you requested
# Note that any partitions you deleted are not expressed
# here so unless you clear all partitions first, this is
# not guaranteed to work
zerombr yes 8
clearpart --all --initlabel 9
part / --fstype ext3 --size=1 --grow --ondisk=dasda 10
#part pv.6 noformat onpart dasdgl 11
#part pv.5 noformat onpart dasdfl
#part pv.3 noformat onpart dasddl
#part pv.4 noformat onpart dasdel
#volgroup VolGroup00 psize=32768 pv.3 pv.4 pv.5 pv.6
#logvol /nfs fstype ext3 name=LogVol00 vgname=VolGroup00 size=8992

%packages 12
@base
@base-x
@core
comps-extras
cracklib-dicts
gnome-mime-data
kernel-headers
nash
rmt
tzdata

%post 13
echo ARP=no >> /etc/sysconfig/network-scripts/ifcfg-eth0 14
echo /dev/dasdb1 swap swap defaults 0 0 >> /etc/fstab 15
echo /dev/dasdc1 swap swap defaults 0 0 >> /etc/fstab
```

Note the following points, which explain the command lines that are numbered above:

- IP address of installation server and path to install tree.
- IP address of new linux server
- Host name of new linux server
- Disable firewall. Only advisable if server is not on an external network.

- 5 Remove references to additional drives only available to the controller.
- 6 Add this line, so that the server automatically shuts down after kickstart
- 7 Skip entering an installation number. If you have one, enter it here instead of using `--skip`. For more information, see “Stage 2 of the RHEL 5 installation” on page 99.
- 8 Add this line to perform a non-interactive direct access storage device (DASD) format.
- 9 Removes all existing partitions. Uncomment this line and add `--initlabel`
- 10 Defines the root partition. The `--size 1` and `--grow` options specify all of the 100 disk.
- 11 Previously defined Logical Volume Manager (LVM) used for install tree. Delete these lines.
- 12 Specifies packages to install. The `@core` entry is required for a minimal install.
- 13 Add section for post-install script.
- 14 This step is performed after installation. `ARP=no` is required for interfaces on a layer 3 z/VM Virtual Switch (VSWITCH).
- 15 Add entries for virtual disk (VDISK) swap spaces in `/etc/fstab`.

Note: The `zerombr` and `clearpart` options mentioned here are chosen because the DASD are not yet formatted for Linux use. For future kickstarts to the same DASD volumes, they will already be formatted. Thus, you can save a substantial amount of time by only recreating the file systems and not reformatting the DASD. In this case you would use the following kickstart options:

```
zerombr no
clearpart --all
```

3. Finally, add the path to the kickstart folder to `/etc/exports`

```
# vi /etc/exports
/nfs/rhel5/          *(ro,sync)
/nfs/virt-cookbook-RH5 *(ro,sync)
/nfs/ks              *(ro,sync)
```

4. Restart the NFS service on the controller. The `showmount -e` command should show the exported file systems:

```
# service nfs restart
Shutting down NFS mountd: [ OK ]
Shutting down NFS daemon: [ OK ]
Shutting down NFS quotas: [ OK ]
Shutting down NFS services: [ OK ]
Starting NFS services: [ OK ]
Starting NFS quotas: [ OK ]
Starting NFS daemon: [ OK ]
Starting NFS mountd: [ OK ]
# showmount -e
Export list for lat128.pbm.ihost.com:
/nfs/ks          *
/nfs/rhel5       *
/nfs/virt-cookbook-RH5 *
```

9.2 Configure the LINUX07 user for kickstart

Earlier you should have created the user ID LINUX07, it is time to configure it for kickstart. LINUX07 must have its own parameter and configuration files, which are again based on the RHEL5 user ID.

LOGOFF of MAINT and logon to LNXMAINT. Copy the parameter and configuration files from RHEL5 to LINUX07 as follows:

```
==> copy rhel5 parm-rh5 d linux07 = =
==> copy rhel5 conf-rh5 d linux07 = =
```

Edit the LINUX07 PARM-RH5 file. Because this is a non-interactive installation, the vnc options are no longer required. The **ks=** line directs the installer to get the kickstart file from the installation server. **RUNKS=1** is required for kickstarts, and the **cmdline** option prevents the installer's text-based user interface from opening on the 3270 console:

```
==> x linux07 parm-rh5 d
ramdisk_size=40000 root=/dev/ram0 ro ip=off
CMSDASD=191 CMSCONFFILE=linux07.conf-rh5
ks=nfs:129.40.178.128:/nfs/ks/linux07-ks.cfg
RUNKS=1 cmdline
====> file
```

Next, edit the LINUX07 CONF file, and change the DASD range and networking information:

```
==> x linux07 conf-rh5 d
DASD=100-102
HOSTNAME=linux07.pbm.ihost.com
NETTYPE=qeth
IPADDR=128.40.178.127
...
====> file
```

9.3 Kickstart the LINUX07 user

Perform the following steps to kickstart the LINUX07 user:

1. Logoff of LNXMAINT and logon to LINUX07. When asked to IPL from disk 100, answer **n**:

```
LOGON LINUX07
...
DIAG swap disk defined at virtual address 101 (64989 4K pages of swap space)
Do you want to IPL Linux from DASD 100? y/n
n
00: 0602 QDIO-ELIGIBLE QIOASSIST-ELIGIBLE
```

2. As in "Installing the master image" on page 95, we will need to temporarily add more memory for the install process. Temporarily modify the storage up to 512MB with the **DEFINE STORAGE** command. Then **IPL CMS** and again answer **n** to the question of IPLing Linux:

```
==> def stor 512m
00: STORAGE = 512M
00: Storage cleared - system reset.
==> ipl cms
...
Do you want to IPL Linux from DASD 200? y/n
n
```

Verify that you have a 512MB virtual machine:

```
==> q v stor
00: STORAGE = 512M
```

This change is for the duration of the user ID session. When you logoff and log back on this user ID, the storage will go back to 256MB.

3. Run **rhel15 exec** to initiate the kickstart. You see some initial kernel messages, followed by the file system format and Red Hat Package Manager (RPM) package installation.

Note: Towards the end of the kickstart, it is normal to see some unrecognized characters on the screen. This is because the 3270 console cannot display the progress meter during the post installation phase. To automatically clear the 3270 console and avoid multiple screens of unreadable messages, issue the **#cp term more 0 0** command before running **RHEL5 EXEC**.

```
==> rhel15
...
Kernel command line: ramdisk_size=40000 root=/dev/ram0 ro ip=off
                      CMSDASD=191 CMSCONFIGFILE= LINUX07.conf
                      ks=nfs:129.40.178.128:/nfs/ks/linux07-ks.cfg
                      RUNKS=1 cmdline
...
```

4. The first time kickstart is run, the installer must format the DASD for Linux use. It is normal to see error messages of the following format if the DASD you are using has never been formatted. In subsequent kickstart installs, you should not see these errors:

```
end_request: I/O error, dev dasda, sector 0
Buffer I/O error on device dasda, logical block 0
Please wait while formatting drive dasda...
```

Note: The VDISK swap device is configured in the %post section of the kickstart file.

5. At the end of the kickstart, IPL the 100 disk to make any changes to your RHEL 5 master image:

```
/mnt/sysimage/dev done
/mnt/sysimage done
you may safely reboot your system
==> #cp ip1 100
00: zIPL v1.5.3 interactive boot menu
00: 0. default (linux)
00: 1. linux
...
```

Congratulations! You have now installed Linux onto the virtual server using kickstart. This process can be repeated in the future for other Linux guests. For the purpose of this book, we present a minimal installation with kickstart. However, you can completely customize the kickstart file to install different packages based on your requirements. For more information regarding kickstart options, see the documentation located at:

<http://www.redhat.com/docs/manuals/enterprise/RHEL-5-manual/>

Servicing Linux with Red Hat Network

This chapter describes Red Hat Network (RHN) and its ability to manage the virtual servers. Using **yum**, the virtual servers can be updated when Red Hat errata are released. You can also use **yum** to install new packages with automatic dependency resolution. RHN is accessed by the following link:

<http://rhn.redhat.com/>

The following sections describe how to configure a Linux guest for **yum**, and manage the guest through RHN:

- ▶ “Registering your system with RHN” on page 155.
- ▶ “Installing and updating packages using yum” on page 156.
- ▶ “Managing your Linux guest through RHN” on page 157.
- ▶ “Updating a system without Internet access” on page 158.

10.1 Registering your system with RHN

This section assumes you have already obtained a valid entitlement for RHEL 5 on System z, or have completed the steps to obtain an evaluation copy. To receive a free 90-day evaluation, visit:

<http://www.redhat.com/rhel/details/eval>

Select the link named **Red Hat Enterprise Linux AS for IBM eServer zSeries and IBM S/390** and create an account. Before using **yum** for the first time, you must import the Red Hat GPG key and register your Linux guest with RHN. Use the commands below, substituting your RHN user name, password, and host name of the Linux guest.

```
# rpm --import /usr/share/rhn/RPM-GPG-KEY
# rhnreg_ks --username=myuser --password=myspw --profilename=linux01.pbm.ihost.com
```

10.2 Installing and updating packages using yum

Now that your system is registered with RHN, you can use **yum** to keep the system updated. You can download and install the latest version of a package by running **yum** with the RPM package name. You can also specify multiple packages on the command line separated by spaces. The **yum install** command installs the package if it is not present, and the **yum upgrade** command updates to the latest version if it is already installed. If a package has any dependencies, **yum** automatically downloads and installs them for you.

Update the **cpp** package to get the latest security fixes:

```
# rpm -q cpp
cpp-4.1.1-30
# yum upgrade cpp
Loading "rhnpplugin" plugin
Loading "installonlyn" plugin
Setting up Upgrade Process
Setting up repositories
rhel-s390x-server-5-beta 100% |=====| 950 B 00:00
...
=====
Package Arch Version Repository Size
=====
Updating:
cpp s390x 4.1.1-43.el5 RHEL5 2.6 M

Transaction Summary
=====
Install 0 Package(s)
Update 1 Package(s)
Remove 0 Package(s)

Total download size: 2.6 M
Is this ok [y/N]: y
Downloading Packages:
Running Transaction Test
Finished Transaction Test
Transaction Test Succeeded
Running Transaction
  Updating : cpp ##### [1/2]
  Cleanup : cpp ##### [2/2]

Updated: cpp.s390x 0:4.1.1-43.el5
Complete!
```

Now query the **cpp** package and you should see that it has been updated.

```
# rpm -q cpp
cpp-4.1.1-43.el5
```

To update every installed package on the system, run:

```
# yum upgrade
```

For more information about the **yum** command see the **yum(8)** man page.

10.3 Managing your Linux guest through RHN

You can also manage the packages on this Linux guest through the Web interface at:

<http://rhn.redhat.com/>

When you first log in to RHN, you see the system you registered under the **Systems** tab. If there is a red exclamation point next to your system, there are errata waiting to be applied. The number of relevant errata and the corresponding number of packages are visible to the left of the system name. Click the number beneath Errata or Packages to get a detailed list. If there is a blue check-mark, then the system is fully updated.




Figure 10-1 RHN system overview

Next, click the link that is the system name. This brings you to a detailed overview, where you can see the system properties as Figure 10-2 shows. Click the Packages tab to view all packages installed on this system. From this tab, you can also update, remove, or install new packages onto the system.




Figure 10-2 RHN system details

For more information about managing your systems through RHN, including usage guides and frequently asked questions, see:

<http://rhn.redhat.com/help>

10.4 Updating a system without Internet access

The **yum** command communicates with RHN using secure Web traffic. If your Linux guest is not connected to the Internet, or is behind a firewall that prevents access to RHN, you can still use all of the **yum** functionality.

10.4.1 Configuring the server

This process uses the controller configured Chapter 7., “Installing and configuring RHEL 5” as a **yum** repository. The controller exports the RHEL 5 install tree over NFS. Your Linux guest uses the automounter to access this install tree, which **yum** uses instead of RHN.

For more information on exporting the install tree over NFS, refer back to 7.7.8, “Turning on the NFS server” on page 125. The following sections assume the install tree is exported over NFS as `/nfs/rhel5/`.

10.4.2 Configuring the client

On the Linux guest, you will first configure the automounter to mount the installation tree from the controller on demand. The automounter will automatically mount a remote directory when it is accessed, and automatically unmount it after a period of inactivity. Edit the file `/etc/auto.master` and add the following line at the bottom:

```
# vi /etc/auto.master
...
/nfs    /etc/auto.controller
```

Next, create the file `/etc/auto.controller`, and add the following line, substituting the IP address of your controller:

```
# vi /etc/auto.controller
rhel5          -ro,hard,intr    <129.40.178.128>:/nfs/rhel5
```

Now, create the `/nfs` directory. Restart the **autofs** service to pick up the configuration changes, then list the contents of the automounted directory:

```
# mkdir /nfs
# service autofs restart
Stopping automount: [ OK ]
Starting automount: [ OK ]
# ls /nfs/rhel5
EULA          README-or.html    RELEASE-NOTES-ja.html
eula.en_US    README-pa.html    RELEASE-NOTES-ko.html
...
```

Now that the installation tree is accessible, you will configure **yum** to use it. Create a file named `rhel5.repo` in the `/etc/yum.repos.d/` directory:

```
# vi /etc/yum.repos.d/rhel5.repo
[RHEL5]
name=Red Hat Enterprise Linux 5
baseurl=file:///nfs/rhel5/Server
```

Finally, you need to import the RPM GPG key so that **yum** knows you are installing official Red Hat packages. The Red Hat GPG key is located in the install tree. Import the key with:

```
# rpm --import /nfs/rhel5/RPM-GPG-KEY
```

Note: Red Hat signs each RPM with a private GPG key, which is compared to your public key each time a package is installed. This method ensures that the RPM is a genuine, unaltered package. When installing an RPM, if you ever see a message similar to:

```
Header V3 DSA signature: NOKEY, key ID 897da07a
```

Either the correct GPG key has not been imported, or the package itself has been altered by a third party.

You are now ready to use **yum** to install or upgrade an RPM package. Refer back to “Installing and updating packages using yum” on page 156 for **yum** syntax.

10.4.3 Updating packages on the server

The RPMs are located in the `/Server` subdirectory of the install tree. Beneath this directory, there is a subdirectory named `/repodata` which contains repository files used by **yum**. Whenever a new set of RPMs is added to the `/Server` directory, you must rebuild the repository data with the **createrepo** command.

On the controller, first install the **createrepo** RPM with:

```
# yum install createrepo
...
Running Transaction
  Installing: createrepo                      ##### [1/1]

Installed: createrepo.noarch 0:0.4.4-2.fc6
Complete!
```

Next, backup the current repository and create a new one with the **createrepo** command:

```
# cd /nfs/rhel5/Server
# mv repodata repodata.orig
# createrepo /nfs/rhel5/Server
96/2480 - system-config-network-1.3.97-1.el5.noarch.rpm
...
```

It should take about five minutes to build the new repository data, depending on the number of RPMs.

You now have a new repository based on the RPMs in `/nfs/rhel5/Server`. You should repeat this procedure any time an RPM (or set of RPMs) change. You can also use this to create multiple RPM repositories, based on anything you like. For example, you can have a repository named “test” containing the latest packages from RHN, as well as a “production” repository based on an official RHEL update. You can then create a `.repo` file on the client pointing to either repository, based on the role of that client.

For example, on the server:

```
# cd /nfs/rhel5
# cp -a Server Server.production
# cp -a Server Server.test
```

Now, any time you update an RPM in `/nfs/rhel5/Server.test/`, run **createrepo** on that directory. On the client, in the `/etc/yum.repos.d/` directory you can have either:

```
/etc/yum.repos.d/rhel5.production.repo:
[RHEL5]
name=RHEL 5 production
baseurl=file:///nfs/rhel5/Server.production/
```

or

```
/etc/yum.repos.d/rhel5.test.repo:
[RHEL5]
name=RHEL 5 test
baseurl=file:///nfs/rhel5/Server.test/
```

Note that this method requires maintaining separate copies of each directory of RPMs, which can fill the `/nfs` directory on the controller rather quickly. Red Hat provides a separate product named Satellite which maintains a single tree, while managing the RPM version differences. The Satellite provides other features similar to RHN as well. For more information, see:

<https://www.redhat.com/rhn/rhndetails/architecture/>

Cloning open source virtual servers

The secret to creativity is knowing how to hide your sources.

--Albert Einstein

This chapter describes how to clone and customize the following Linux virtual servers:

- ▶ “Creating a virtual Web server” on page 161
- ▶ “Creating a virtual LDAP server” on page 165
- ▶ “Creating a virtual file and print server” on page 173
- ▶ “Creating a virtual application development server” on page 177

The sections that follow don’t go into the theory nor detail on the four types of servers. Rather, they are just a reference to get the servers quickly installed and configured. There are many other resources that go into depth on these types of servers.

11.1 Creating a virtual Web server

The example in this section uses the LINUX01 user ID to create a virtual Web server. You should have a vanilla virtual server cloned to the user ID LINUX01 as described in Chapter 8, “Configuring RHEL 5 for cloning” on page 133.

11.1.1 Installing Apache RPMs

SSH into the IP address of the new LINUX01 server. Install the following Apache RPMs via the `yum -y install` command. The `-y` flag prevents the “Is this OK” question:

```
# yum -y install httpd httpd-manual
...
=====
Package                Arch      Version      Repository      Size
=====
Installing:
httpd                   s390x     2.2.3-6.el5   RHEL5           1.1 M
httpd-manual            s390x     2.2.3-6.el5   RHEL5           831 k
Installing for dependencies:
apr                     s390x     1.2.7-10     RHEL5           122 k
```

apr-util	s390x	1.2.7-3	RHEL5	78 k
postgresql-libs	s390x	8.1.4-1.1	RHEL5	197 k

Transaction Summary

```
=====
Install      5 Package(s)
Update       0 Package(s)
Remove       0 Package(s)
```

Total download size: 2.3 M

Downloading Packages:

Running Transaction Test

warning: httpd-manual-2.2.3-6.el5: Header V3 DSA signature: NOKEY, key ID 897da07a

Finished Transaction Test

Transaction Test Succeeded

Running Transaction

Installing: apr	##### [1/5]
Installing: postgresql-libs	##### [2/5]
Installing: apr-util	##### [3/5]
Installing: httpd	##### [4/5]
Installing: httpd-manual	##### [5/5]

Installed: httpd.s390x 0:2.2.3-6.el5 httpd-manual.s390x 0:2.2.3-6.el5

Dependency Installed: apr.s390x 0:1.2.7-10 apr-util.s390x 0:1.2.7-3

postgresql-libs.s390x 0:8.1.4-1.1

Complete!

Verify that the RPMs were installed

```
# rpm -qa | grep httpd
httpd-2.2.3-6.el5
httpd-manual-2.2.3-6.el5
```

Before starting the Apache Web server, use the **chkconfig** command to set the service to start at boot time:

```
# chkconfig --list httpd
httpd          0:off  1:off  2:off  3:off  4:off  5:off  6:off
# chkconfig httpd on
# chkconfig --list httpd
httpd          0:off  1:off  2:on   3:on   4:on   5:on   6:off
```

11.1.2 Testing Apache

Start the Apache Web server to verify it is installed successfully.

```
# service httpd start
Starting httpd: [ OK ]
```

To verify that Apache is installed correctly, after it's been started, **bring up a Web browser** and point it to the server. For example, the virtual server running on LINUX01 can be reached with the following URL:

http://<129.40.178.121>/

You should see the following test page to verify the Web server is working:




Figure 11-1 Apache test page

If you get an error in starting Apache, look in the log file `/var/log/httpd/error-log` for clues. If Apache started successfully but you can't reach the test page from a browser, try accessing it using the IP address rather than the DNS name.

11.1.3 Turning on a firewall

RHEL 5 comes with an IP tables firewall which is disabled after a default installation. Your enterprise may have firewalls in front of Web servers, but you may also want a firewall running on this virtual server. This section describes how to quickly enable an IP tables firewall and configure it to allow Web traffic through.

Verify that the firewall is off via the `chkconfig --list` command. The service name is **iptables**:

```
# chkconfig --list iptables
iptables          0:off  1:off  2:off  3:off  4:off  5:off  6:off
```

Turn on the firewall at boot time with the `chkconfig` command, and for this session with the `service` command:

```
# chkconfig iptables on
# service iptables start
Applying iptables firewall rules: [ OK ]
Loading additional iptables modules: ip_conntrack_netbios_ns [ OK ]
```

Go back to your browser and **click refresh**. You should get an error that the server is not responding. This is because packets for ports for http: and https: (80 and 443) are dropped by default. To allow Web traffic through, you can modify the file `/etc/sysconfig/iptables`. First make a backup copy, then add two rules (emboldened) to allow these ports then save your changes:

```
# cd /etc/sysconfig
# cp iptables iptables.orig
# vi iptables
*filter
:INPUT ACCEPT [0:0]
:FORWARD ACCEPT [0:0]
:OUTPUT ACCEPT [0:0]
:RH-Firewall-1-INPUT - [0:0]
-A INPUT -j RH-Firewall-1-INPUT
-A FORWARD -j RH-Firewall-1-INPUT
-A RH-Firewall-1-INPUT -i lo -j ACCEPT
-A RH-Firewall-1-INPUT -p icmp --icmp-type any -j ACCEPT
-A RH-Firewall-1-INPUT -p 50 -j ACCEPT
-A RH-Firewall-1-INPUT -p 51 -j ACCEPT
-A RH-Firewall-1-INPUT -p udp --dport 5353 -d 224.0.0.251 -j ACCEPT
-A RH-Firewall-1-INPUT -p udp -m udp --dport 631 -j ACCEPT
-A RH-Firewall-1-INPUT -p tcp -m tcp --dport 631 -j ACCEPT
-A RH-Firewall-1-INPUT -p tcp -m tcp --dport 80 -j ACCEPT
-A RH-Firewall-1-INPUT -p tcp -m tcp --dport 443 -j ACCEPT
-A RH-Firewall-1-INPUT -m state --state ESTABLISHED,RELATED -j ACCEPT
-A RH-Firewall-1-INPUT -m state --state NEW -m tcp -p tcp --dport 22 -j ACCEPT
-A RH-Firewall-1-INPUT -j REJECT --reject-with icmp-host-prohibited
COMMIT
```

Restart the firewall to pick up the new rules:

```
# service iptables restart
Flushing firewall rules: [ OK ]
Setting chains to policy ACCEPT: filter [ OK ]
Unloading iptables modules: [ OK ]
Applying iptables firewall rules: [ OK ]
Loading additional iptables modules: ip_conntrack_netbios_ns [ OK ]
```

Go back to your browser and **click refresh** again. You should not get an error this time. You should now have a firewall that allows Web traffic.

11.1.4 Configuring SSL for Apache

Use the Secure Sockets Layer (SSL) to encrypt data between the client (browser) and the server. This is done by specifying an **https** prefix in the URL which uses port 443 rather than using the conventional **http** prefix which uses port 80.

To use SSL, the `mod_ssl` package is required. You can show that SSL communications do not work by changing `http` to **https** in your browser:

```
https://<129.40.178.121>/
```

Click reload in your browser and you should get a communications error.

Installing the SSL Apache module

RHEL 5 makes it very easy to install and enable SSL support for Apache. Install the `mod_ssl` RPM via the `yum -y install` command:

```
# yum -y install mod_ssl
...
Install      2 Package(s)
Update       0 Package(s)
Remove       0 Package(s)

Total download size: 212 k
```

```

Is this ok [y/N]: y
Downloading Packages:
Running Transaction Test
Finished Transaction Test
Transaction Test Succeeded
Running Transaction
  Installing: distcache ##### [1/2]
  Installing: mod_ssl ##### [2/2]

Installed: mod_ssl.s390x 1:2.2.3-6.el5
Dependency Installed: distcache.s390x 0:1.4.5-14.1
Complete!

```

Verify that the RPM was added:

```

# rpm -qa | grep ssl
openssl-0.9.8b-8.3.el5
openssl-0.9.8b-8.3.el5
mod_ssl-2.2.3-6.el5

```

Restart the Web server:

```

# service httpd restart
Stopping httpd: [ OK ]
Starting httpd: [ OK ]

```

Go back to your browser and click restart again. This time you should get a warning about a self-signed certificate. This is acceptable - for a production Web site you will want a certificate signed by a certificate authority.

11.1.5 Populating your Web site

You can begin to put your Web pages in the directory `/var/www/html/` which is the default Web root.

11.1.6 Apache resources

The following Web sites contain additional information on Apache:

```

http://www.sampublishing.com/articles/article.asp?p=30115&seqNum=4
http://www.sitepoint.com/article/securing-apache-2-server-ssl
http://www.securityfocus.com/infocus/1786

```

11.2 Creating a virtual LDAP server

The Lightweight Directory Access Protocol (LDAP) is commonly implemented via the OpenLDAP package which comes standard with most Linux distributions. Among other directory functions, OpenLDAP allows for centralized login authentication and user and group ID resolution.

In this section you will install Linux manually and set up login authentication to a new virtual LDAP server. Then you will go back to the virtual Web server you just created and point it to the new LDAP server.

The steps in this section are as follow:

- ▶ “Cloning a Linux virtual server” on page 166
- ▶ “Installing the openldap server” on page 166

- ▶ “Configuring the OpenLDAP server” on page 167
- ▶ “Migrating existing users to LDAP” on page 168
- ▶ “Configuring an LDAP client” on page 171
- ▶ “Adding new user accounts” on page 172

11.2.1 Cloning a Linux virtual server

Start an SSH session as root to the controller and clone the master image to the LINUX02 user ID:

```
# clone.sh linux02
Invoking CP command: QUERY LINUX02
HCPCQU045E LINUX02 not logged on
Error: non-zero CP response for command 'QUERY LINUX02': #45
Setting device 0.0.0191 offline
Done
Setting device 0.0.0191 online
Done
LINUX02  CONF-RH5 D1 F          80          13          1 12/22/2006 13:19:54

WARNING!!: this will copy disk 100 to LINUX02 100
New host name will be: lat182.pbm.ihost.com
New TCP/IP address will be: 129.40.178.182
Other network data is retrieved from LINUX02 CONF-RH5 on 191 disk
Are you sure you want to overwrite these disks (y/n): y
Please enter a brief description of this server
This is an LDAP server running RHEL5
...
Successfully cloned /rhel5master to LINUX02
You should be able to ping 129.40.178.122 within one minute
```

You should now have a vanilla RHEL5 system running on LINUX02.

11.2.2 Installing the openldap server

Start an SSH session to the IP address of the new virtual server running on LINUX02. Use the **yum** command to install the OpenLDAP client and server RPMs:

```
# yum -y install openldap-clients openldap-servers
...
=====
Package                Arch      Version      Repository      Size
=====
Installing:
openldap-clients        s390x     2.3.27-4     RHEL5           189 k
openldap-servers        s390x     2.3.27-4     RHEL5           2.3 M
Installing for dependencies:
libtool-ltdl            s390x     1.5.22-6.1   RHEL5           37 k

Transaction Summary
=====
Install      3 Package(s)
Update      0 Package(s)
Remove      0 Package(s)

Total download size: 2.5 M
Downloading Packages:
Running Transaction Test
warning: openldap-clients-2.3.27-4: Header V3 DSA signature: NOKEY, key ID 897da07a
Finished Transaction Test
```

```

Transaction Test Succeeded
Running Transaction
  Installing: libtool-ltdl ##### [1/3]
  Installing: openldap-clients ##### [2/3]
  Installing: openldap-servers ##### [3/3]

Installed: openldap-clients.s390x 0:2.3.27-4 openldap-servers.s390x 0:2.3.27-4
Dependency Installed: libtool-ltdl.s390x 0:1.5.22-6.1
Complete!

```

11.2.3 Configuring the OpenLDAP server

Any detailed description of LDAP is outside the scope of this book. Rather, short configuration recommendations are given in this section.

There are two important configuration values that must be chosen.

- ▶ The suffix or base distinguished name of the LDAP Domain Information Tree (DIT) - the most common suffix is to use your company's DNS name.
- ▶ The LDAP administrator or root name and password.

Choose an administrative password and run the **slappasswd** command which displays an encrypted version of it. The output of this command will be used shortly in a configuration file so you may want to make a copy of it.

```

# slappasswd
New password: <1nx4vm>
Re-enter new password: <1nx4vm>
{SSHA}4FiGwLm+cy+I96TyiWMn4evNXSxa5aJ2

```

The OpenLDAP server configuration file is `/etc/openldap/slapd.conf` file. Move down about a page to the lines beginning with **suffix** and **rootdn** and set them appropriately. In this example the following values are used:

```

LDAP suffix      dc=pbm,dc=ihost,dc=com
Root user (rootdn)  cn=ldaproot,dc=pbm,dc=ihost,dc=com
Root password      lnx4vm (encrypted output from slappasswd)

```

Make a backup copy of the main OpenLDAP configuration file, `/etc/openldap/slapd.conf`, and modify the original. First set the suffix and root user distinguished name:

```

# cd /etc/openldap
# cp slapd.conf slapd.conf.orig
# vi slapd.conf
...
database      bdb
# suffix      "dc=my-domain,dc=com"
# rootdn      "cn=Manager,dc=my-domain,dc=com"
suffix "dc=pbm,dc=ihost,dc=com"
rootdn  "cn=ldaproot,dc=pbm,dc=ihost,dc=com"
...

```

Set the **rootpw** line to a value of the encrypted password that was the output of the **slappasswd** command:

```

...
# rootpw      secret
# rootpw      {crypt}ijFYncSNctBYg
rootpw {SSHA}4FiGwLm+cy+I96TyiWMn4evNXSxa5aJ2
...

```

Save the `slapd.conf` file. Your LDAP server should now be minimally configured.

Start the LDAP service

Start LDAP at boot time via the `chkconfig` command and for this session via the `service` command:

```
# chkconfig ldap on
# service ldap start
Checking configuration files for slapd: config file testing succeeded      [ OK ]
Starting slapd: [ OK ]
```

Query the LDAP database via the `ldapsearch` command. The `-x` flag specifies that simple authentication is used:

```
# ldapsearch -x
# extended LDIF
#
# LDAPv3
# base <> with scope subtree
# filter: (objectclass=*)
# requesting: ALL
#
# search result
search: 2
result: 32 No such object
```

The result shows that the LDAP directory can be searched, but that it is empty. This is expected as no data has been added to it.

11.2.4 Migrating existing users to LDAP

A common method of populating the LDAP database is via LDAP Directory Interchange Format (LDIF) files. Red Hat includes a set of migration scripts with the OpenLDAP server RPM, written by PADL Software Pty Ltd (<http://padl.com>). These scripts allow you to convert users and groups from the `/etc/` directory to LDIF format. The scripts are in the `/usr/share/openldap/migration/` directory. Before converting the `/etc/group` and `/etc/passwd` files, add a user that will be used to test LDAP authentication. In this example, **ldapuser1** is added via the `useradd` command and the password is set via the `passwd` command:

```
# useradd ldapuser1
# passwd ldapuser1
Changing password for user ldapuser1.
New UNIX password: <1nx4vm>
Retype new UNIX password: <1nx4vm>
passwd: all authentication tokens updated successfully.
```

The PADL tools have a shared configuration file named `migrate_common.ph`. Make a backup copy of it and modify it. There are two lines to be changed which set the domain name and suffix (or root) of LDAP tree. In this example the suffix is **pbm.ihost.com**:

```
# cd /usr/share/openldap/migration
# cp migrate_common.ph migrate_common.ph.orig
# vi migrate_common.ph
...
# Default DNS domain
$DEFAULT_MAIL_DOMAIN = "<pbm.ihost.com>";

# Default base
```

```
$DEFAULT_BASE = "<dc=pbm,dc=ihost,dc=com>";  
...
```

The first tool conversion Perl script is **migrate_base.pl**. Redirect the output to a file named **accounts.ldif**. This will be the file that you use to populate the LDAP server. After you run it, take a look at the first 9 lines of the LDIF file via the **head** command to give you an idea of the format:

```
# ./migrate_base.pl > accounts.ldif  
# head -9 accounts.ldif  
dn: dc=ihost,dc=com  
dc: ihost  
objectClass: top  
objectClass: domain  
  
dn: dc=pbm,dc=ihost,dc=com  
dc: pbm  
objectClass: top  
objectClass: domain
```

Important: There appears to be a bug in **migrate_base.pl** when the suffix has more than two components. This will later result in an error while trying to import the LDIF file:

```
slapadd: line 5: database (dc=pbm,dc=ihost,dc=com) not configured to hold  
"dc=ihost,dc=com"
```

If your suffix (Base DN) has more than two components, you can work around the bug by deleting the entry or entries in the LDIF file with fewer components than your suffix. In this example, **pbm.ihost.com** has three components, so the first entry (first four lines and one blank line) in the LDIF file must be deleted. Then the **slapadd** command succeeded.

The next two scripts migrate the **/etc/passwd** and **/etc/group** files. Append the output of both of these to the **accounts.ldif** file via the **>>** redirection operator:

```
# ./migrate_passwd.pl /etc/passwd >> accounts.ldif  
# ./migrate_group.pl /etc/group >> accounts.ldif
```

Search for the string **ldapuser1** in the **accounts.ldif** file:

```
# grep ldapuser1 accounts.ldif  
dn: uid=ldapuser1,ou=People,dc=pbm,dc=ihost,dc=com  
uid: ldapuser1  
cn: ldapuser1  
homeDirectory: /home/ldapuser1  
dn: cn=ldapuser1,ou=Group,dc=pbm,dc=ihost,dc=com  
cn: ldapuser1
```

The output shows that the user was migrated to the LDIF file.

Now it is time to populate the LDAP server. This can be done while the server is not running via the **slapadd -l** command. First stop the LDAP service then add the data in the LDIF file:

```
# service ldap stop  
Stopping slapd: [ OK ]  
# slapadd -l accounts.ldif  
bdb_db_open: Warning - No DB_CONFIG file found in directory /var/lib/ldap: (2)  
Expect poor performance for suffix dc=pbm,dc=ihost,dc=com.
```

The database is stored in the directory `/var/lib/ldap/`. For the OpenLDAP server to start, all files in this directory must be owned by the `ldap` user and group. This can be accomplished via the **chown** command:

```
# chown ldap:ldap /var/lib/ldap/*
```

Set the LDAP server:

```
# service ldap start
Checking configuration files for slapd: bdb_db_open: Warning - No DB_CONFIG file found
in directory /var/lib/ldap: (2)
config file testing succeeded
[ OK ]
Starting slapd: [ OK ]
```

Note: Resolving the warning “**Expect poor performance for suffix dc=pbm,dc=ihost,dc=com.**” is left as an exercise for the reader :))

Test that you can query the LDAP directory for `ldapuser1` via the **ldapsearch** command. The **-b** flag sets the base of the search (it is necessary because the default suffix of `dc=pbm,dc=ihost,dc=com` has not been configured into the LDAP client; later it will not be needed):

```
# ldapsearch -x -b dc=pbm,dc=ihost,dc=com uid=ldapuser1
# extended LDIF
#
# LDAPv3
# base <dc=pbm,dc=ihost,dc=com> with scope subtree
# filter: uid=ldapuser1
# requesting: ALL
#
# ldapuser1, People, pbm.ihost.com
dn: uid=ldapuser1,ou=People,dc=pbm,dc=ihost,dc=com
uid: ldapuser1
...
# numEntries: 1
```

You should now have an OpenLDAP server installed, configured and populated with users and groups.

Deleting duplicate users

You now have a duplicate set of users and groups in both the `/etc/` file system and in LDAP. There are different ways that you can manage this duplicity. For this section, the following changes are recommended:

Delete **ldapuser1** from file system This user was designed to be the first LDAP uid so it should not also be in the file system

Delete **root** from LDAP Having uid of 0 (root) in LDAP is may not be a good security design.

Delete the `ldapuser1` from the file system with the **userdel** command, and delete `root` from LDAP via the **ldapdelete** command:

```
# userdel ldapuser1
# ldapdelete -x -D cn=ldaproot,dc=pbm,dc=ihost,dc=com -W \
uid=root,ou=People,dc=pbm,dc=ihost,dc=com
Enter LDAP Password: <1nx4vm>
```


Now `ldapuser1`'s credentials are only in LDAP and the root password is only in the local file system.

11.2.5 Configuring an LDAP client

You are now ready to configure a system to authenticate users using the new LDAP server. You will first go to a different virtual server, running on the `LINUX01` user ID, and configure it to point to this LDAP server.

Start an SSH session to the Web server running on `LINUX01`.

Invoke the command `authconfig-tui`. Use the **Tab** key to move between fields, the **space bar** to change selections and the **Enter** key to select:

```
# authconfig-tui
```

```
+-----+ Authentication Configuration +-----+
|
|  User Information      Authentication
|  [*] Cache Information  [*] Use MD5 Passwords
|  [ ] Use Hesiod        [*] Use Shadow Passwords
|  [*] Use LDAP          [*] Use LDAP Authentication
|  [ ] Use NIS           [ ] Use Kerberos
|  [ ] Use Winbind       [ ] Use SMB Authentication
|                        [ ] Use Winbind Authentication
|                        [*] Local authorization is sufficient
|
|                        +-----+
|                        | Cancel |
|                        +-----+
|
|                        +-----+
|                        | Next  |
|                        +-----+
|
+-----+
```

Under *User Information*, select **Cache Information** and **Use LDAP**. Under *Authentication*, select **Use LDAP Authentication** and **Local authorization is sufficient**. Press **Enter** when you have tabbed to the **Next** “button”.

```
+-----+ LDAP Settings +-----+
|
|  [ ] Use TLS
|  Server: ldap://<129.40.178.122>/
|  Base DN: <dc=pbm,dc=ihost,dc=com>
|
|  +-----+
|  | Back  |
|  +-----+
|
|  +-----+
|  | Ok   |
|  +-----+
|
+-----+
```

On the next screen, set the *Server* value to point to the LDAP server. In this example, it is `ldap://129.40.178.122/`. Set the *Base DN* to your suffix value. In this example it is `dc=pbm,dc=ihost,dc=com`. “Press” **OK**.

Your LDAP client should now be pointing to the LDAP server. Test it via the `id ldapuser1` command:

```
# id ldapuser1
```

```
uid=500(ldapuser1) gid=500(ldapuser1) groups=500(ldapuser1)
context=root:system_r:unconfined_t:s0-s0:c0.c1023
```

Authentication should also allow LDAP. Test this by **starting another SSH session** to the LDAP server and logging in as ldapuser1:

```
login as: ldapuser1
ldapuser1@129.40.178.123's password:
```

When you get an SSH session as ldapuser1 this shows that authentication is working.

11.2.6 Adding new user accounts

There are different front-ends to LDAP administration, however, there is no industry standard. Details on front-end tools are beyond the scope of this section, however, it is useful to be able to add users via line commands. This section describes how to create a new LDIF file and add a new user.

Go back to the directory `/usr/share/openldap/` and view the LDIF file you created earlier, `accounts.ldif` via the `less` command. Search for the user `ldapuser1` via the `/` subcommand:

```
# cd /usr/share/openldap/migration
# less accounts.ldif
/ldapuser1
```

Before:

```
dn: uid=ldapuser1,ou=People,dc=pbm,dc=ihost,dc=com
uid: ldapuser1
cn: ldapuser1
objectClass: account
objectClass: posixAccount
objectClass: top
objectClass: shadowAccount
shadowLastChange: 13515
shadowMax: 99999
shadowWarning: 7
loginShell: /bin/bash
uidNumber: 500
gidNumber: 500
homeDirectory: /home/ldapuser1
```

Copy and paste the lines for that user to a new file `ldapuser.ldif`. Change the name `ldapuser1` to the desired new name (`ldapuser2` in this example). Also increment the `uidNumber` field (to 501 in this example)

```
# vi ldapuser.ldif
```

After:

```
dn: uid=ldapuser2,ou=People,dc=pbm,dc=ihost,dc=com
uid: ldapuser2
cn: ldapuser2
objectClass: account
objectClass: posixAccount
objectClass: top
objectClass: shadowAccount
shadowLastChange: 13515
shadowMax: 99999
shadowWarning: 7
loginShell: /bin/bash
uidNumber: 501
```

```
gidNumber: 500
homeDirectory: /home/ldapuser2
```

You now have created a new LDIF file containing the entries for a new LDAP user with a unique UID. Now you can add the user to the LDAP database via the following **ldapadd** command:

```
# ldapadd -x -D cn=ldaproot,dc=pbm,dc=ihost,dc=com -W -f ldapuser.ldif
Enter LDAP Password:

adding new entry "cn=ldapuser2,ou=Group,dc=pbm,dc=ihost,dc=com"
```

Set a password

You can set the new user's password via the following **ldappasswd** command:

```
# ldappasswd -x -D cn=ldaproot,dc=pbm,dc=ihost,dc=com -W -s lnx4vm \
uid=ldapuser2,ou=People,dc=pbm,dc=ihost,dc=com
Enter LDAP Password: <lnx4vm>

Result: Success (0)
```

You can test logging into a virtual server with the new user's credentials. If you successfully configured the virtual server running on LINUX01 to point to the LDAP server, try a new SSH session with the new user. You should be able to successfully login:

```
login as: ldapuser2
ldapuser2@129.40.178.182's password:
Could not chdir to home directory /home/ldapuser2: No such file or directory
```

The issue of not having a home directory will be addressed in section 12.3, "Centralizing home directories for LDAP users" on page 189.

11.3 Creating a virtual file and print server

Samba allows Windows clients to map Linux file systems as shared drives. Samba can also act as a middle-man between Windows clients and a Linux print server. The recommended Linux print server is CUPS - the Common UNIX Printing System. This section does not describe the configuration of CUPS but it does describe how the necessary RPMs are installed.

The steps in this section are as follow:

- ▶ "Cloning a Linux virtual server" on page 173
- ▶ "Installing necessary RPMs" on page 174
- ▶ "Configuring Samba configuration file" on page 175
- ▶ "Adding a Samba user" on page 175
- ▶ "Starting Samba at boot time" on page 176
- ▶ "Testing your changes" on page 176

11.3.1 Cloning a Linux virtual server

From the controller, clone a basic virtual server. In this example the user ID `LINUX03` is used.

```
# clone.sh linux03
Invoking CP command: QUERY LINUX03
HCPCQU045E LINUX03 not logged on
Error: non-zero CP response for command 'QUERY LINUX03': #45
```

```

Setting device 0.0.0191 offline
Done
Setting device 0.0.0191 online
Done
LINUX03  CONF-RH5 D1 F          80          13          1 12/22/2006 13:20:03

WARNING!!: this will copy disk 100 to LINUX03 100
New host name will be: lat183.pbm.ihost.com
New TCP/IP address will be: 129.40.178.123
Other network data is retrieved from LINUX03 CONF-RH5 on 191 disk
Are you sure you want to overwrite these disks (y/n): y
Please enter a brief description of this server
This is a Samba server running RHEL5
...
Successfully cloned /rhel5master to LINUX03
You should be able to ping 129.40.178.283 within one minute

```

Start an SSH session to the new virtual server.

11.3.2 Installing necessary RPMs

Add the following RPMs via the **yum -y** command:

```

# yum -y install samba-common samba samba-client
...
=====
Package                Arch      Version      Repository      Size
=====
Installing:
samba                  s390x     3.0.23c-2    RHEL5           16 M
samba-client           s390x     3.0.23c-2    RHEL5           4.6 M
samba-common           s390      3.0.23c-2    RHEL5           9.2 M
samba-common           s390x     3.0.23c-2    RHEL5           9.1 M
Installing for dependencies:
popt                   s390      1.10.2-36.el5 RHEL5           69 k

Transaction Summary
=====
Install      5 Package(s)
Update       0 Package(s)
Remove       0 Package(s)

Total download size: 39 M
Downloading Packages:
Running Transaction Test
warning: samba-client-3.0.23c-2: Header V3 DSA signature: NOKEY, key ID 897da07a
Finished Transaction Test
Transaction Test Succeeded
Running Transaction
  Installing: samba-common ##### [1/5]
  Installing: popt ##### [2/5]
  Installing: samba-client ##### [3/5]
  Installing: samba ##### [4/5]
  Installing: samba-common ##### [5/5]

Installed: samba.s390x 0:3.0.23c-2 samba-client.s390x 0:3.0.23c-2 samba-common.s390
0:3.0.23c-2 samba-common.s390x 0:3.0.23c-2
Dependency Installed: popt.s390 0:1.10.2-36.el5
Complete!

```

Confirm that the RPMs were added:

```
# rpm -qa | grep samba
samba-common-3.0.23c-2
samba-common-3.0.23c-2
samba-3.0.23c-2
samba-client-3.0.23c-2
```

11.3.3 Configuring Samba configuration file

The one configuration file for Samba is `/etc/samba/smb.conf`. It is easy to add an SMB share that will be made available by the Samba server. A good test directory is `/usr/share/doc/` as it has much good Linux documentation. The following example will create a file *share* named `sharedoc`:

```
# cd /etc/samba
# cp smb.conf smb.conf.orig
# vi smb.conf    // add three lines at the bottom of the file:
...
[sharedoc]
    comment = RHEL 5 on System z documentation
    path = /usr/share/doc/
```

You can verify the syntax of your changes with the `testparm` command:

```
# testparm smb.conf
Load smb config files from smb.conf
Processing section "[homes]"
Processing section "[printers]"
Processing section "[sharedoc]"
Loaded services file OK.
Server role: ROLE_STANDALONE
Press enter to see a dump of your service definitions
...
```

This change will create an SMB share named **sharedoc** consisting of the contents of the directory `/usr/share/doc` and below.

11.3.4 Adding a Samba user

The default method that Samba uses to determine users' credentials is to look in the `/etc/samba/smbpasswd` file. That user must first exist in the Linux file system (`/etc/passwd`, `/etc/shadow`, etc). To create a new Samba user, the **smbpasswd -a** command is used. First use the **useradd** and **passwd** commands to add a user locally. In this example, the user `sambauser1` is used:

```
# id sambauser1
id: sambauser1: No such user
# useradd sambauser1
# passwd sambauser1
Changing password for sambauser1.
New password: <1nx4vm>
Re-enter new password: <1nx4vm>
Password changed
```

Add the user `sambauser1` to the `smbpasswd` file via the **smbpasswd -a** command:

```
# smbpasswd -a sambauser1
New SMB password: <1nx4vm>
Retype new SMB password: <1nx4vm>
```

```
startsmbfilepwent_internal: file /etc/samba/smbpasswd did not exist. File successfully
created.
account_policy_get: tdb_fetch_uint32 failed for field 1 (min passwd length), returning 0
...
Added user sambauser1.
```

You can see that the last **smbpasswd** command added sambauser1 to the file smbpasswd:

```
# cat smbpasswd
sambauser1:502:2E6F0C45D305054CAAD3B435B51404EE:74154D10CC18CFC98F1ED128DB8764DA:[U
]:LCT-45A3AAB2:
```

This method of maintaining Samba users, groups and passwords is good for a small number of users. For a larger number of users, merging Samba and LDAP is recommended. It is not as simple as pointing the virtual file and print server at the virtual LDAP server as described in “Creating a virtual LDAP server” on page 165 because the Samba schema must first be added to LDAP. Details are outside the scope of this book.

11.3.5 Starting Samba at boot time

Samba can be started for the current session via the **service** command and at boot time via the **chkconfig** command:

```
# service smb start
Starting SMB services: [ OK ]
Starting NMB services: [ OK ]
# chkconfig smb on
```

Samba should now be running and configured to start at boot time.

11.3.6 Testing your changes

You can verify that Samba is running via the following **service** command:

```
# service smb status
smbd (pid 6987 6982) is running...
nmbd (pid 6985) is running...
```

You can verify the shares that are available via the following **smbclient** command:

```
# smbclient -U sambauser1 -L localhost
Password:

Domain=[LAT123] OS=[Unix] Server=[Samba 3.0.23c-2]

      Sharename      Type      Comment
      -----
      sharedoc        Disk      RHEL 5 on System z documentation
      IPC$            IPC       IPC Service (Samba Server)
      sambauser1      Disk      Home Directories
Domain=[LAT123] OS=[Unix] Server=[Samba 3.0.23c-2]
...
```

You can test getting a Samba share from a Windows desktop. Go to any Windows Explorer window (such as *My Computer*) and select **Tools -> Map Network Drive**. Use the Universal Naming Convention (UNC) to specify the Samba server and share name as shown in the upper left corner of Figure 11-2 on page 177. In this example the UNC is **\\129.40.178.123\sharedoc**. Then click **Finish**. If all the steps were correct, you should see the files in a new Explorer window as shown in the bottom right corner of the figure.




Figure 11-2 Mapping a network drive to the Samba server

You should now have Samba configured and running with one new share available.

If you prefer a DOS command line, you can also link to the share via the following **net use** command:

```
c:\>net use y: \\129.40.178.123\sharedoc
The password is invalid for \\129.40.178.123\sharedoc.

Enter the user name for '129.40.178.123': sambauser1
Enter the password for 129.40.178.123:
The command completed successfully.
```

You can detach the share via the following **net use** command:

```
c:\>net use y: /delete
y: was deleted successfully.
```

11.3.7 Configuring printing

Configuring printing is more complex and is beyond the scope of this section. For details see the Redpaper *Printing with Linux on zSeries Using CUPS and Samba*, REDP-3864, on the Web at:

<http://www.redbooks.ibm.com/abstracts/redp3864.html>

11.4 Creating a virtual application development server

Most Linux distributions come with a basic set of application development tools, making Linux one of the most versatile development systems. These basic tools are ideal for projects of any size.

The development languages used in implementation range from scripting languages such as Python or Tcl, to compiled languages such as C/C++ and Java. There are software available on Linux to help form a development system for developers to create integrated applications. MySQL and Apache are among them. A popular open source Web platform is LAMP, which stands for the open source software and programming languages used to make up the platform: Linux, Apache, MySQL, Python or PHP.

From the controller clone a virtual server to the user ID LINUX04.

```
# clone.sh linux04
...
```

Note that before installing the development tools, the root file system is about half full:

```
# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/dasda1     2.3G  1.1G  1.1G  49% /
tmpfs           124M    0  124M   0% /dev/shm
```

SSH in to the new virtual server. You can use the `yum -y groupinstall` command to install the groups named **development-tools** and **development-libs**. This will add about 181 packages which requires a number of minutes to complete:

```
# yum -y groupinstall development-tools development-libs
...
Transaction Summary
=====
Install      181 Package(s)
Update        0 Package(s)
Remove        0 Package(s)
...
Complete!
```

Your application development server is now ready to use. You may choose to add or remove different packages. Use `df -h` command to show that your system should still have about 30% free space:

```
# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/dasda1     2.3G  1.5G  635M  71% /
tmpfs           124M    0  124M   0% /dev/shm
```

11.4.1 Additional resources

The following Web sites are resources for additional information on application development topics:

Scripting languages

<http://www.perl.com/>
<http://www.python.org/>
<http://www.freeos.com/guides/lsst/>

C/C++

<http://gcc.gnu.org/onlinedocs/gcc/>
http://en.wikipedia.org/wiki/GNU_Compiler_Collection#External_links
http://vertigo.hsrl.rutgers.edu/ug/make_help.html
http://www.gnu.org/software/make/manual/html_chapter/make_toc.html

Java

<http://www-130.ibm.com/developerworks/java/>

<http://java.sun.com/>
<http://csdl.ics.hawaii.edu/~johnson/613f99/modules/04/jar-files.html>
<http://java.sun.com/j2se/1.3/docs/tooldocs/solaris/jdb.html>

Linux kernel development

<http://www.kernel.org/pub/linux/docs/lkm1/#blkd>

Web development

<http://www.onlamp.com/>
<http://cgi.resourceindex.com/>
<http://www.perl.com/>

Miscellaneous Recipes

Two things are infinite: the universe and human stupidity; and I'm not sure about the universe.

--Albert Einstein

This chapter has the following sections of miscellaneous tasks that you might want to perform:

- ▶ “Adding a logical volume” on page 181
- ▶ “Extending an existing logical volume” on page 187
- ▶ “Centralizing home directories for LDAP users” on page 189
- ▶ “Rescuing a Linux system” on page 192

12.1 Adding a logical volume

There are times when you require more disk space than a single direct access storage device (DASD) volume provides. For example, if you want to have a shared /home/ directory you will want it to be of sufficient size. When this is the case, you can use the Logical Volume Manager (LVM) to combine multiple DASD volumes into one logical volume.

The following process describes how to create a logical volume, or extend an existing logical volume with additional DASD on a Linux guest. The overall steps in creating a logical volume are as follows:

- ▶ Add minidisks to the z/VM directory entry and IPL Linux
- ▶ Bring the new DASD online
- ▶ Format and partition the DASD
- ▶ Create the logical volume and file system
- ▶ Update the file system table
- ▶ Make the change persistent

12.1.1 Adding minidisks to the z/VM directory entry

The overall steps are the following. Specific details of these steps on z/VM are not given.

- ▶ Determine the labels of the volumes that will be added.

- ▶ Add minidisk statements to define minidisks (at virtual addresses 103 and 104 of size 6678 cylinders in this example) to the appropriate Linux user ID definition in the USER DIRECT file.
- ▶ Create the USER DISKMAP file to verify the disk layout
- ▶ Bring the changes online with the **DIRECTXA** command
- ▶ Modify the Linux system to recognize the new minidisks
- ▶ Shutdown the system and logoff the z/VM user ID. **The LINUX02 user ID is used** in the following example (this puts the logical volume on the LDAP server)
- ▶ Logon to the user ID and verify the new minidisks are available.

12.1.2 Making the new minidisks available

Before you shut down, make a backup copy then modify the `/etc/modprobe.conf` file to include the new minidisks at virtual addresses 103 and 104:

```
# cd /etc
# cp modprobe.conf modprobe.conf.orig
# vi modprobe.conf
alias eth0 qeth
options dasd_mod dasd=100-104
```

Save the file. To effect the change, you must build a new initial RAMdisk with the following **mkinitrd** command, then run **zipl** to write the changes to the boot record:

```
# mkinitrd -v -f /boot/initrd-$(uname -r).img $(uname -r)
Creating initramfs
...
Adding module jbd
Adding module ext3
Adding module dasd_mod with options dasd=100-104
Adding module dasd_eckd_mod
Adding module dasd_fba_mod
# zipl
Using config file '/etc/zipl.conf'
Building bootmap in '/boot/'
Building menu 'rh-automatic-menu'
Adding #1: IPL section 'linux' (default)
Preparing boot device: dasda (0100).
Done.
# shutdown -h now
...
```

When your system comes back up, **start an SSH session** to it. Use the **lsdasd** command to verify that the new minidisks have been recognized

```
# lsdasd
0.0.0100(ECKD) at ( 94: 0) is dasda : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0101(FBA ) at ( 94: 4) is dasdb : active at blocksize 512, 524288 blocks, 256 MB
0.0.0102(FBA ) at ( 94: 8) is dasdc : active at blocksize 512, 1048576 blocks, 512 MB
0.0.0103(ECKD) at ( 94:12) is dasdd : active at blocksize 4096, 1202040 blocks, 4695 MB
0.0.0104(ECKD) at ( 94:16) is dasde : active at blocksize 4096, 1202040 blocks, 4695 MB
```

12.1.3 Formatting and partitioning the minidisks

You could format the minidisks sequentially, but you can also use the following bash **for** loop to put two **dasdfmt** jobs in the background so as to format both in parallel:

```
# for i in d e
```

```
> do
> dasdfmt -b 4096 -y -f /dev/dasd$i &
> done
[1] 2713
[2] 2714
```

When the jobs are finished use the **fdasd** command with the **-a** flag to create a single partition from each minidisk:

```
# fdasd -a /dev/dasdd
auto-creating one partition for the whole disk...
writing volume label...
writing VTOC...
rereading partition table...
# fdasd -a /dev/dasde
auto-creating one partition for the whole disk...
writing volume label...
writing VTOC...
rereading partition table...
```

The minidisks are now ready for you to use in the logical volume. If you are creating a new logical volume, see 12.1.4, “Create the logical volume and file system” on page 184. If you are extending an existing logical volume, skip ahead to 12.2, “Extending an existing logical volume” on page 187.

12.1.4 Create the logical volume and file system

The overall steps involved in creating a logical volume are:

- ▶ Create physical volumes from the two DASD
- ▶ Create a single volume group
- ▶ Create a single logical volume
- ▶ Make a file system from the logical volume




Figure 12-1 LVM block diagram

Figure 12-1 shows a block diagram of the logical volume manager reflecting this example.

Creating physical volumes from the two DASD

The **pvccreate** command initializes DASD for use by LVM. Initialize the two new DASD partitions. Verify with the **pvdplay** command:

```
# pvccreate /dev/dasdd1 /dev/dasde1
Physical volume "/dev/dasdd1" successfully created
Physical volume "/dev/dasde1" successfully created

# pvdplay
--- NEW Physical volume ---
PV Name           /dev/dasdd1
VG Name
PV Size           4.59 GB
Allocatable       NO
PE Size (KByte)   0
Total PE          0
Free PE           0
Allocated PE      0
PV UUID           eksaUw-HvSX-S9m8-a5u0-RB0n-fMH7-y6fkRb

--- NEW Physical volume ---
```

```

PV Name          /dev/dasde1
VG Name
PV Size          4.59 GB
Allocatable      NO
PE Size (KByte)  0
Total PE         0
Free PE          0
Allocated PE     0
PV UUID          y61Mf2-PkCk-w46g-1Sk1-3M9d-7vUZ-rtvaJX

```

Creating a single volume group

The **vgcreate** command can be used to create a volume group named **homevg** from the two DASD. Use the **vgdisplay** command to verify:

```

# vgcreate homevg /dev/dasdd1 /dev/dasde1

# vgdisplay
--- Volume group ---
VG Name          homevg
System ID
Format           lvm2
Metadata Areas   2
Metadata Sequence No 1
VG Access        read/write
VG Status        resizable
MAX LV           0
Cur LV          0
Open LV          0
Max PV           0
Cur PV          2
Act PV           2
VG Size          9.16 GB
PE Size          4.00 MB
Total PE         2346
Alloc PE / Size  0 / 0
Free PE / Size   2346 / 9.16 GB
VG UUID          IHAq2g-ME3w-b6LY-E3hA-raNk-bFOG-Poprma

```

In this example, there are 2346 free physical extents.

Creating a single logical volume

The **lvcreate** command is used to create a logical volume. The **-l 2346** flag specifies to use all free extents, in this example. The **-n home1v** specifies the name of the new logical volume. The last argument **homevg** specifies the name of the volume group from which the logical volume will be created. Use the **lvdisplay** command to verify:

```

# lvcreate -l 2346 -n home1v homevg
Logical volume "home1v" created
# lvdisplay
--- Logical volume ---
LV Name          /dev/homevg/home1v
VG Name          homevg
LV UUID          roBwTM-sxkF-AdLn-sePN-KnzT-n36r-71kIxk
LV Write Access  read/write
LV Status        available
# open           0
LV Size          9.16 GB
Current LE       2346
Segments         2
Allocation       inherit

```

```
Read ahead sectors    0
Block device          253:0
```

Making a file system from the logical volume

Now you have a logical volume. Use the **mke2fs** command to create a file system out of it. The **-j** flag adds a journal so it will be of type ext3:

```
# mke2fs -j /dev/homevg/home1v
mke2fs 1.36 (05-Feb-2005)
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
402400 inodes, 803840 blocks
40192 blocks (5.00%) reserved for the super user
...
```

The file system created from the logical volume is now ready to be mounted.

12.1.5 Updating the file system table

You could now mount the file system manually. However if you add the mount to the file system table file, `/etc/fstab`, you can effectively test the change by using the **mount** command with only one argument. Add one line to the file:

```
# cd /etc
# vi fstab
LABEL=/                /                ext3    defaults    1 1
/dev/dasdb1            swap             swap    defaults    0 0
/dev/dasdc1            swap             swap    defaults    0 0
/dev/homevg/home1v     /home            ext3    defaults    0 0
...
```

Mount the `/home/` file system with one argument. Use the **ls** command to verify that there is no data in the logical volume except the `lost+found/` directory. Use the **df -h** command to verify that it is mounted.

```
# mount /home
# ls /home
lost+found/
# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/dasda1     2.3G  1.2G  1016M  53% /
tmpfs           124M    0   124M   0% /dev/shm
/dev/mapper/homevg-home1v
                9.1G  149M   8.5G   2% /home
```

Moving data from existing file system

You may have noticed that there may be some data in the directory which will serve as the mount point. To complete the addition of the logical volume, it is recommended that you move any data from the existing directory to the new logical volume. First unmount the logical volume and view the contents of the `/home/` directory:

```
# umount /home
# ls -F /home
ldapuser1/
```

In this example, there is only one subdirectory. You can move the contents from the root file system to the new logical volume a number of different ways. Following is one method:


```
# cd /home
# mkdir /tmp/home
# mv * /tmp/home
# cd ..
# mount /home
# cd /home
# mv /tmp/home/* .
# ls -F
ldapuser1/  lost+found/
```

Even though you tested mounting the file system via reading the `/etc/fstab` file, you may want to test a reboot to verify the logical volume is successfully mounted.

12.2 Extending an existing logical volume

This section describes the process of adding a new minidisk to an existing LVM. This is useful when your logical volume has run out of space. In this example, the `vgdisplay` command shows that the existing volume group is full.

```
# vgdisplay
--- Volume group ---
VG Name                homevg
...
Total PE                2346
Alloc PE / Size         2346 / 9.16 GB
Free PE / Size          0 / 0
VG UUID                 IHAq2g-ME3w-b6LY-E3hA-raNk-bFOG-Poprma
```

First, repeat the steps at the beginning of this section to add a new minidisk. In this example, a minidisk at virtual address 105 is added of size 3338 cylinders.

Create a new RAMdisk to enable the new minidisk

Edit the `/etc/modprobe.conf` file and add the new minidisk at address 105 to the existing range:

```
# vi /etc/modprobe.conf
alias eth0 qeth
options dasd_mod dasd=100-105
```

Use the `mkinitrd` command to rebuild the initial RAMdisk, then the `zipl` command to rewrite the boot sector on the root partition.

```
# mkinitrd -v -f /boot/initrd-$(uname -r).img $(uname -r)
...
# zipl
...
```

Reboot the system to test the changes.

```
# reboot
...
```

When your system comes back, verify that the new minidisk is available via the `lsdasd` command:

```
# lsdasd
...
0.0.0100(ECKD) at ( 94: 0) is dasda : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0101(FBA ) at ( 94: 4) is dasdb : active at blocksize 512, 524288 blocks, 256 MB
0.0.0102(FBA ) at ( 94: 8) is dasdc : active at blocksize 512, 1048576 blocks, 512 MB
```

```
0.0.0103(ECKD) at ( 94:12) is dasdd : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0104(ECKD) at ( 94:16) is dasde : active at blocksize 4096, 600840 blocks, 2347 MB
0.0.0105(ECKD) at ( 94:20) is dasdf : n/f
```

Format the minidisk via the **dasdfmt** command and make a single partition via the **fdasd -a** command as you did before:

```
# dasdfmt -b 4096 -y -f /dev/dasdf
Finished formatting the device.
Rereading the partition table... ok
# fdasd -a /dev/dasdf
auto-creating one partition for the whole disk...
writing volume label...
writing VTOC...
rereading partition table...
```

Creating a physical volume

Use the **pvccreate** command to create a physical volume from the minidisk:

```
# pvccreate /dev/dasdf1
Physical volume "/dev/dasdf1" successfully created
```

Extending the volume group

Use the **vgextend** command to extend the volume group into the new physical volume. Then, use **vgdisplay** to verify that the volume group has free space.

```
# vgextend homevg /dev/dasdf1
Volume group "homevg" successfully extended
# vgdisplay
--- Volume group ---
VG Name                homevg
...
Total PE                2932
Alloc PE / Size         2346 / 9.16 GB
Free PE / Size          586 / 2.29 GB
VG UUID                 IHAq2g-ME3w-b6LY-E3hA-raNk-bF0G-Poprma
```

Note there are 586 new free physical extents (PEs) in this example.

Extend the logical volume and the file system

Now that you have free space in the volume group, you can increase the size of the existing logical volume with the **lvextend** command. The **-l** option specifies the number extents to add. Finally, use the **resize2fs** command, which increases the size of the file system while it is mounted. You can use the **df** command to show the file system size before and after you extend it as the following example shows:

```
# df -h | grep home
/dev/mapper/homevg-homelv          9.1G  149M   8.5G   2% /home
# lvextend -l +586 /dev/homevg/homelv
Extending logical volume homelv to 11.45 GB
Logical volume homelv successfully resized
# resize2fs -p /dev/homevg/homelv
resize2fs 1.39 (29-May-2006)
Filesystem at /dev/homevg/homelv is mounted on /home; on-line resizing required
Performing an on-line resize of /dev/homevg/homelv to 3002368 (4k) blocks.
The filesystem on /dev/homevg/homelv is now 3002368 blocks long.

# df -h | grep home
/dev/mapper/homevg-homelv        12G  152M   11G   2% /home
```

You have now added the new minidisk as free space to the existing logical volume. Test your changes by rebooting your system:

```
# reboot
...
```

12.3 Centralizing home directories for LDAP users

If you have completed “Creating a virtual LDAP server” on page 165, you have a working LDAP authentication server that provides centralized login authentication. If you have completed section 12.1, “Adding a logical volume” on page 181, you have a larger file system mounted over `/home/` for storing user data. Now you can bring these together with the automount service to have a centralized `/home` file system. In this fashion, users can login to all virtual servers using the same credentials and being able to access the same data. Further, you can modify the golden image so that all newly cloned virtual servers will inherit this setup. Following is a block diagram




Figure 12-2 Block diagram of centralized LDAP authentication and automounted `/home` file system

12.3.1 Configuring the NFS server

Configure `LINUX02` to export `/home` over NFS. This is similar to the configuration of the controller in “Turning on the NFS server” on page 125.

Start an SSH session to the virtual server running on `LINUX02`. Add one line to the `/etc/exports` file:

```
# vi /etc/exports
/home                *(rw,sync)
```

Set the NFS service to start at boot time via the `chkconfig` command and for this session via the `service` command:

```
# chkconfig nfs on
# service nfs start
Starting NFS services: [ OK ]
Starting NFS quotas: [ OK ]
Starting NFS daemon: [ OK ]
Starting NFS mountd: [ OK ]
```

Test mounting the newly exported file system locally:

```
# mount localhost:/home /mnt
# ls /mnt
ldapuser1 lost+found
```

You now have /home/ available for NFS mounting.

12.3.2 Configuring the master image for LDAP and automount

In this section you will shut down the controller and boot the master image. You will then configure it for LDAP authentication and automount of /home/ to the virtual server running on LINUX02.

Start a 3270 connect to the controller, shut it down, and IPL the master image:

```
Red Hat Enterprise Linux Server release 4.92 (Tikanga)
Kernel 2.6.18-1.2839.el5 on an s390x
```

```
lat128 login: root
Password:
```

```
Last login: Fri Dec 15 09:49:10 from 9.56.60.150
```

```
#shutdown -h now
```

```
...
```

```
==> ip1 100
```

```
...
```

```
==> #cp disc
```

Configuring LDAP

You can modify the authentication settings via the command **authconfig-tui** (you can also use **authconfig** from a graphical environment such as VNC).

Use the **Tab** key to move between fields, the **space bar** to change selections and the **Enter** key to select:

```
# authconfig-tui
```

```
+-----+ Authentication Configuration +-----+
|
|  User Information      Authentication
|  [*] Cache Information  [*] Use MD5 Passwords
|  [ ] Use Hesiod        [*] Use Shadow Passwords
|  [*] Use LDAP          [*] Use LDAP Authentication
|  [ ] Use NIS           [ ] Use Kerberos
|  [ ] Use Winbind       [ ] Use SMB Authentication
|                        [ ] Use Winbind Authentication
|                        [*] Local authorization is sufficient
|
|               +-----+               +-----+
|               | Cancel |               | Next |
|               +-----+               +-----+
|
+-----+
```

Under *User Information*, select **Cache Information** and **Use LDAP**. Under *Authentication*, select **Use LDAP Authentication** and **Local authorization is sufficient**. Press **Enter** when you have tabbed to the **Next** “button”.

```

+-----+ LDAP Settings +-----+
|
|      [ ] Use TLS
|  Server: ldap://<129.40.178.122>/
|  Base DN: <dc=pbm,dc=ihost,dc=com>
|
|      +-----+           +-----+
|      | Back |           | Ok  |
|      +-----+           +-----+
|
+-----+

```

Set the *Server* value to point to the LDAP server. In this example, it is `ldap://129.40.178.122/`. Set the *Base DN* to your suffix value. In this example it is `dc=pbm,dc=ihost,dc=com`. “Press” **OK**.

Your LDAP client should now be pointing to the LDAP server. Test it via the `id ldapuser1` command:

```

# id ldapuser1
uid=500(ldapuser1) gid=500(ldapuser1) groups=500(ldapuser1)
context=root:system_r:unconfined_t:s0-s0:c0.c1023

```

Authentication should also allow LDAP. Test this by **starting another SSH session** to the LDAP server and logging in as `ldapuser1`:

```

login as: ldapuser1
ldapuser1@129.40.178.122's password:

```

When you get an SSH session as `ldapuser1` this shows that authentication is working.

Configuring automount

Now SSH to the master image to configure the automounter. Add an entry to the bottom of `/etc/auto.master` for `/home`.

```

# vi /etc/auto.master
/nfs    /etc/auto.controller
/home   /etc/auto.home

```

Create the file `/etc/auto.home` and add one line to it:

```

# vi /etc/auto.home
*       <129.40.178.122>:/home/&

```

The asterisk (*) is used as a wildcard character to represent the local subdirectory. The ampersand (&) is used as the remote system name or the remote subdirectory. Whatever is in the local directory name field replaces the ampersand character.

Finally, restart **autofs** and test logging in as `ldapuser1` with **su**. You will see that `/home/ldapuser1` is now mounted from the LDAP server:

```

# service autofs restart
Stopping automount: [ OK ]
Starting automount: [ OK ]
# su - ldapuser1
$ pwd
/home/ldapuser1
$ mount | grep ldapuser1
129.40.178.122:/home/ldapuser1 on /home/ldapuser1 type nfs (rw,addr=129.40.178.122)

```

You have now configured the automounter to mount a remote LDAP user's home directory at login.

You can now shut down the master image, and IPL the controller (200). Clone a new virtual server via the **c1one.sh** script. Start an SSH session to the new virtual server and LDAP authentication and the automounting of /home/ via NFS should work.

12.4 Rescuing a Linux system

This section describes how to boot your Linux server into different modes for troubleshooting purposes. It covers booting Linux into single user mode, and also entering a rescue environment when you require more advanced troubleshooting.

12.4.1 Entering single user mode

Single user mode is helpful when you need to recover the root password, or if you are having problems while booting Linux into the default runlevel. To enter single user mode, first IPL your Linux server from the 3270 console. You will see a message similar to:

```
zIPL v1.3.2 interactive boot menu
0. default (linux)
1. linux
Note: VM users please use '#cp vi vmsg <input>'
Please choose (default will boot in 15 seconds):
```

Use the **#cp vi vmsg** command to boot the desired menu option (zero in this example), followed by the number one for single user mode:

```
==> #cp vi vmsg 0 1
```

After some initial kernel boot messages, you should see:

```
INIT: Entering runlevel: 1
Entering non-interactive startup
Telling INIT to go to single user mode.
INIT: Going single user
INIT: Sending processes the TERM signal
INIT: Sending processes the KILL signal
sh-3.00#
```

In single user mode, you are logged in as the root user. You can use the **passwd** command to set the root password. All of the file systems in `/etc/fstab` are mounted, but networking has not been started. To exit single user mode, you can type **reboot**, or enter **init 3** to continue booting normally.

12.4.2 Entering a rescue environment

If you encounter errors mounting the root file system, or have other problems that prevent you from entering single user mode, you can enter a rescue environment. This environment loads a Linux image in memory, and does not attempt to mount the root file system.

To enter a rescue environment, initiate an interactive Linux installation. For more detailed information about interactive installation, see Chapter 7., “Installing and configuring RHEL 5” on page 89. Perform the following steps:

1. Logon to LNXMAINT. Copy the RHEL5 EXEC file to a new file named RESCUE EXEC, and copy the user's PARM-RH5 file to a new file (LINUX07 RESCUE in this example):

```
==> copy rhel5 exec d rescue = =
==> copy linux07 parm-rh5 d = rescue =
```

2. Next, edit RESCUE EXEC to point to the new LINUX07 RESCUE file:

```
==> xedit RESCUE EXEC
...
00005 'PUN RHEL5          KERNEL * (NOH'
00006 'PUN' userid() '  RESCUE * (NOH'
00007 'PUN RHEL5          INITRD * (NOH'
...
==> file
```

3. Edit the LINUX07 RESCUE file, replacing any kickstart or VNC lines with the **rescue** command line option:

```
==> xedit LINUX07 RESCUE
ramdisk_size=40000 root=/dev/ram0 ro ip=off
CMSDASD=191 CMSCONFFILE= LINUX07.CONF-RH5
rescue
```

4. Now **logoff** of LNXMAINT and **login** to LINUX07. Answer **no** to IPL from DASD question, and run RESCUE EXEC.

```
==> RESCUE
Linux version 2.6.18-1.2839.el5 (brewbuilder@devel8.z900.redhat.com) (gcc versio
n 4.1.1 20061130 (Red Hat 4.1.1-43)) #1 SMP Tue Dec 5 22:58:42 EST 2006
We are running under VM (64 bit mode)
Detected 2 CPU's
Boot cpu address 0
Built 1 zonelists. Total pages: 65536
Kernel command line: ramdisk_size=40000 root=/dev/ram0 ro ip=off
                      CMSDASD=191 CMSCONFFILE= LINUX07.CONF-RH5
                      rescue
...
The install process directs you to telnet or SSH to the IP address of your Linux server to
begin the first stage of the installation.
```

5. Use SSH to connect to the IP address and log in as root. After choosing the language, the rescue environment will prompt you for the location of the rescue image, which is located in the install tree on the controller.
6. Press **F2** to allow for additional devices. Choose **NFS image**, then enter the IP address of the controller and the path `/nfs/rhel5`.
7. The rescue image will search for your Linux installation and will prompt you to mount the partitions it finds. After this, you will be presented with a shell prompt. If you chose to mount your root partition, it will be mounted to the `/mnt/sysimage` directory.

Note: if the rescue image cannot find your partition, you can try to mount it yourself via the **mount** command. For example:

```
# mount /dev/dasda1 /mnt/runtime/
# ls /mnt/runtime/
bin      home      media     root      sys
boot     lib       mnt       sbin      tmp
dev      lib64     opt       selinux   usr
etc      lost+found  proc      srv       var
```

8. Type **exit** to leave the shell and exit rescue mode.

Part 3

Common tasks

This part of the book discusses tasks common to z/VM, SLES 10 and RHEL 5.

Monitoring z/VM and Linux

Not everything that can be counted counts, and not everything that counts can be counted.

--Albert Einstein

This chapter briefly describes how to monitor z/VM and Linux. For a more thorough chapter on z/VM performance and monitoring, see Chapter 11, *Monitoring performance and capacity*, in the Manual *Getting Started With Linux*, SC24-6096 on the Web at:

http://publibz.boulder.ibm.com/cgi-bin/bookmgr_OS390/Shelves/hcsh2a70

There are a number of z/VM monitoring tools such as Computer Associates' VM:Monitor, IBM's z/VM Performance Toolkit and Velocity Software's ESALPS. The IBM z/VM Performance Toolkit is briefly described in this section.

For more information on Computer Associates' VM:Monitor, see:

<http://www.ca.com/>

For more information on Velocity's ESALPS, see:

<http://www.velocitysoftware.com/>

This chapter describes the following topics:

- ▶ "Using INDICATE and other commands" on page 197
- ▶ "The z/VM Performance Toolkit" on page 201
- ▶ "Monitoring Linux" on page 208
- ▶ "Registering Linux images with the Performance Toolkit" on page 210

13.1 Using INDICATE and other commands

z/VM has many commands to monitor the state of the system. **CP INDICATE** is the most commonly used, and there are other commands that are addressed.

13.1.1 Using the INDICATE command

z/VM has some basic commands such as **INDICATE**. There are many parameters that can be included. Use the command **HELP INDICATE** for a basic understanding and then press **F11** for help on each parameter.

INDICATE LOAD

If no parameter is specified **INDICATE LOAD** is the default option. There are two flavors of this, a class G and a class E. Class G users can use **INDICATE** to display recent contention for system resources, display environment characteristics and measurements of resources used by their virtual machine.

The output from user ID with class E privilege (e.g. MAINT, OPERATOR) is shown here. The lines are number for clarity of the description that follows:

```
==> ind load
1  AVGPROC-038% 03
2  XSTORE-000021/SEC MIGRATE-0001/SEC
3  MDC READS-000068/SEC WRITES-000001/SEC HIT RATIO-099%
4  PAGING-0031/SEC STEAL-000%
5  Q0-00006(00000)                                DORMANT-00357
6  Q1-00001(00000)                                E1-00000(00000)
7  Q2-00001(00000) EXPAN-002 E2-00000(00000)
8  Q3-00034(00000) EXPAN-002 E3-00000(00000)
9
10 PROC 0000-038%                                PROC 0001-038%
11 PROC 0002-038%
12
13 LIMITED-00000
```

The **INDICATE LOAD** command gives a snapshot of current system performance. Except for the counts of virtual machines in various queues and the limited list, the values you see here are a smoothed average over the past 4 minutes. Areas where z/VM performance analysts tend to focus are the following:

- ▶ AVGPROC on line **1** gives the overall processor utilization, 38% in this example. The number following it is the number of on-line processors, 3 in this example. The individual processor utilization is shown on lines **10** and **11**. Take a glance at these to see if they are somewhat balanced. There are cases where an imbalance is okay. This would include very low utilization scenarios or cases where there are not enough ready to run virtual processors to keep the physical processors busy. Line **2** describes paging to expanded storage. Most z/VM systems on z900 class machines can sustain 1000s of paging operations a second without any problems. The MIGRATE rate is the number of pages per second being moved from expanded storage out to paging space on DASD. A healthy system will have a MIGRATE rate significantly lower than the XSTORE rate. However, there are times the MIGRATE value will spike for brief periods of time.
- ▶ Minidisk cache (MDC) statistics are given on the third line. The effectiveness of MDC can be judged by the combination of the READS rate and the HIT RATIO. If both are high, then a large number of physical I/Os are avoided due to the MDC feature. However, a high HIT RATIO with a low value for the READS rate is not good (it doesn't matter much if you have a 100% hit ratio, but are doing only 1 I/O per second).
- ▶ Line **4** describes more storage (memory) management. The PAGING rate is important. Higher values will often impact performance. The STEAL percentage is often misleading. This is basically the percentage of pages taken from guests that z/VM believes are non-dormant. Since some guests have periodic timers going off, they appear to be active to z/VM even when relatively idle. Pages taken from these guests are considered stolen. So there are scenarios where a system only has active guests, in which case all pages

taken would be considered stolen. Bearing this in mind, if a high STEAL value is observed, the paging rate needs to be checked. If the paging rate is low, then the STEAL value is not important.

- On lines 5 through 8 you also see a series of counters that represent the users in various queues. The z/VM scheduler classifies work into 3 different classes (1 through 3) and a special class of zero. So the Column of Q_x values and E_x represent the virtual machines in the dispatch list and the eligible list. The most important value here to validate is that there are no virtual machines in the Eligible list: E1, E2, E3; this implies z/VM has stopped dispatching some virtual machines to avoid over committing resources. Do not worry about the values in parenthesis.

INDICATE QUEUES EXP

Another useful command to understand the state of the system is the **INDICATE QUEUES EXP**. Following is an example:

```
==> ind q exp
DATAMGT1      Q3 AP 00000537/00000537 .... -2.025 A02
BITNER        Q1 R00 00000785/00000796 .I.. -1.782 A00
EDLLNX4       Q3 PS 00007635/00007635 .... -1.121 A00
TCP/IP        Q0 R01 00004016/00003336 .I.. -.9324 A01
APCTEST1      Q2 IO 00003556/00003512 .I.. -.7847 A01
EDLWRK20      Q3 AP 00001495/00001462 .... -.6996 A01
EDL           Q3 IO 00000918/00000902 .... -.2409 A01
EDLWRK11      Q3 AP 00002323/00002299 .... -.0183 A00
EDLWRK18      Q3 IO 00001052/00000388 .... -.0047 A00
EDLWRK4       Q3 AP 00004792/00002295 .... .0055 A01
EDLWRK8       Q3 AP 00004804/00004797 .... .0089 A02
EDLWRK16      Q3 AP 00002378/00002378 .... .0170 A02
EDLWRK2       Q3 AP 00005544/00002956 .... .0360 A00
EDLWRK12      Q3 AP 00004963/00002348 .... .0677 A01
EDLWRK6       Q3 IO 00000750/00000302 .... .0969 A02
EDLWRK3       Q3 AP 00005098/00005096 .... .0999 A02
EDLWRK17      Q3 AP 00004786/00004766 .... .1061 A01
EDLWRK9       Q3 AP 00002372/00002334 .... .1107 A02
EDLWRK5       Q3 IO 00002376/00002376 .... .1205 A01
EDLWRK14      Q3 AP 00002426/00002323 .... .1238 A02
EDLLIB19      Q3 IO 00001226/00001100 .... .1309 A02
EDLWRK19      Q3 AP 00002322/00002298 .... .1705 A00
EDLWRK15      Q3 AP 00002839/00002781 .... .2205 A02
EDLWRK1       Q3 AP 00002969/00002935 .... .2491 A02
```

This is another class E command and displays the virtual processors (a single virtual machine may have multiple virtual processors) what queue (dispatch list, eligible, limit list) they are in and what state they are. This is a snapshot in time. Again you want to make sure there are not any virtual machines in the eligible list. Normal virtual processors in the dispatch list will be Q_x ($x=1,2,3$). Eligible list would be marked as E_x . The third column in the example also gives state of virtual processor. This can be helpful to get a feel for how the virtual processors might be constrained. Virtual processors that are actually running at the snapshot are marked with and RNN where NN is the processor number they are on. An R without a number means the virtual processor is ready to run but there is not an available processor. (**Note:** the virtual machine that issues the **INDICATE** command will always be one of the running machines). Other states are documented in the help for **IND Q EXP**. One doesn't have to be concerned about the other columns unless detailed analysis is required or if IBM support requests it. Also, always remember that is just a snapshot in time so often repeating this command over time can give a more accurate picture of your z/VM system.

13.1.2 Using other basic commands

Some other useful basic commands are briefly mentioned. All examples are shown from the MAINT user ID. The results will be different for users with fewer privileges.

Getting help

To get help on the system use the **HELP** command. Sometimes it's hard to find help for exactly the command you're looking for. Some useful help commands are as follow

```
==> help           // for basic help
==> help cp menu    // for a menu of all CP commands
==> help cpquery    // for a menu of all CP QUERY command
==> help cpset      // for a menu of all CP SET commands
```

Determining who is logged on

To see who is logged on to the system use the **QUERY NAMES** command. For example

```
==> q n
LINUX06 - DSC , LINUX04 - DSC , LINUX03 - DSC , LINUX07 - DSC
LINUX01 - DSC , SLES9   - DSC , FTPSERVE - DSC , DTCVSW2 - DSC
DTCVSW1 - DSC , TCPIP   - DSC , OPERSYMP - DSC , DISKACNT - DSC
EREP     - DSC , OPERATOR - DSC , MAINT   -L0005
VSM      - TCPIP
```

Determining storage or memory

To see how much central and expanded storage (memory) use the **QUERY STORAGE** and **QUERY XSTOR** commands. For example:

```
==> q stor
STORAGE = 3G
==> q xstor
XSTORE= 1024M online= 1024M
XSTORE= 1024M userid= SYSTEM usage= 97% retained= 0M pending= 0M
XSTORE MDC min=0M, max=1024M, usage=96%
XSTORE= 1024M userid= (none) max. attach= 1024M
```

Determining processors or CPUs

To see how many processors (CPs, IFLs, CPUs) you have, use the **QUERY PROCESSORS** command. For example:

```
==> q proc
PROCESSOR 00 MASTER
PROCESSOR 01 ALTERNATE
PROCESSOR 02 ALTERNATE
PROCESSOR 03 ALTERNATE
```

Determining software level

To determine what level of CP your system is at, use the **QUERY CPLEVEL** command. For example:

```
==> q cplevel
z/VM Version 5 Release 1.0, service level 0401 (64-bit)
Generated at 08/31/04 17:33:32 EST
IPL at 03/10/05 14:42:02 EST
```

Determining system cylinder allocation

The **QUERY ALLOC MAP** command shows you the system's allocate of spool, paging and directory space. For example:

```
==> q alloc map
```

VALID	RDEV	EXTENT	EXTENT	TOTAL	IN USE	% ALLOCATION		
		START	END			HIGH	USED	TYPE
520RES	A700	1	20	20	1	1	5%	DRCT ACTIVE
520SPL	A703	0	3338	601020	40950	63360	6%	SPOOL
520PAG	A704	0	3338	601020	8167	9872	1%	PAGE
MPA706	A706	0	3338	601020	7840	12448	1%	PAGE
...								

Determining DASD, OSA and virtual resources

The **QUERY DASD** and **QUERY DASD FREE** commands will show you what DASD is assigned to the system and what DASD is free to be assigned. Similarly the **QUERY OSA** and **QUERY OSA FREE** commands will report on the OSA resources. Finally, the **QUERY VIRTUAL ALL** command can be useful. Following is the short form of these commands without any output shown:

```
==> q da
==> q da free
==> q osa
==> q osa free
==> q v all
```

13.2 The z/VM Performance Toolkit

To use the z/VM Performance Toolkit, the product must be ordered. You should only configure the product if you have ordered it.

Much more detail can be found in the following books:

- ▶ *z/VM Performance Toolkit*, SC24-6136, on the Web starting at the z/VM 5.2 bookshelf:
<http://www-03.ibm.com/servers/eserver/zseries/zos/bkserv/zvmpdf/zvm52.html>
 Search for **Toolkit** on that page.
- ▶ *The Program Directory for Performance Toolkit for VM*, GI11-2854-00, on the Web at
<http://www.vm.ibm.com/progdir/5vmptk20.pdf>
- ▶ The IBM Redbook *Linux on IBM zSeries and S/390: Performance Toolkit for VM*, SG24-6059, on the Web at:
<http://www.redbooks.ibm.com/abstracts/sg246059.html>

The section that follow describe how to set up and use the IBM Performance Toolkit *very briefly*:

- ▶ “Configuring the z/VM Performance Toolkit” on page 201
- ▶ “Using the z/VM Performance Toolkit” on page 205

13.2.1 Configuring the z/VM Performance Toolkit

The Performance Toolkit is installed with z/VM. Configuration is described in the Program Directory. Following is a summary of how to turn it on. Again, you should configure the product only if you have ordered it. You can query which priced products are enabled via the **QUERY PRODUCT** command:

```
==> q product
DMSVML2060I LNXMAINT 192 linked as 0120 file mode Z
Ready; T=0.01/0.01 11:35:43
Product State Description
5VMDIR10 Disabled 00/00/00.00:00:00.$BASEDDR DIRECTORY MAINTENANCE FL 510
```

```

5VMPTK20 Disabled 00/00/00.00:00:00.$BASEDDR PERFORMANCE TOOLKIT FOR VM
5684096K Disabled 00/00/00.00:00:00.$BASEDDR RSCS Networking Version 3 Release 2
Modification 0
5767002P Disabled 00/00/00.00:00:00.$BASEDDR RACF for VM/ESA V2

```

To enable it, **logon to MAINT** and enter the following command:

```

==> service perftk enable
VMFSRV2760I SERVICE processing started
...
VMFSUT2760I VMFSUFTB processing started
VMFSUT2760I VMFSUFTB processing completed successfully
VMFSRV2760I SERVICE processing completed successfully

```

You should see a few screens of messages scroll by and finally the success messages shown above. This will enable the Performance Toolkit for the current z/VM session. To enable it across IPLs, modify the SYSTEM CONFIG file and uncomment the two lines changing DISABLED to **ENABLED** and reIPL your system:

```

==> cprel a
CPRELEASE request for disk A scheduled.
HCPZAC6730I CPRELEASE request for disk A completed.
==> link * cfl cfl mr
==> acc cfl f
==> x system config f
====> /5vmptk10
PRODUCT PRODID 5VMPTK10 STATE ENABLED DESCRIPTION '00/00/00.00:00:00.$BASEDDR P
ERFORMANCE TOOLKIT FOR VM'
...

```

Check your changes for syntax errors and put the CP disk back online

```

==> acc 193 g
==> cpsyntax system config f
CONFIGURATION FILE PROCESSING COMPLETE -- NO ERRORS ENCOUNTERED.
==> rel f (det
DASD OCF1 DETACHED
==> cpacc * cfl a
CPACCESS request for mode A scheduled.
HCPZAC6732I CPACCESS request for MAINT's OCF1 in mode A completed.

```

13.2.2 Configuring Web Browser support

Once the product is enabled, the TCPIP profile must be modified to add browser capabilities for the Performance Toolkit.

1. Logon to TCPMAINT. Edit the <systemID> TCPIP D file and search for the string reserve ports. This is where z/VM TCP/IP ports are reserved

```

==> x <systemID> tcpip d
====> /port

```

2. Add the following line under the PORT entries:

```

...
PORT
 20  TCP FTPSERVE  NOAUTOLOG ; FTP Server
 21  TCP FTPSERVE           ; FTP Server
 23  TCP INTCLIEN           ; TELNET Server
; 25  TCP SMTP           ; SMTP Server
; 53  TCP NAMESRV          ; Domain Name Server
; 53  UDP NAMESRV          ; Domain Name Server
; 67  UDP BOOTPD           ; BootP Server

```



```

; 67  UDP DHCPD           ; DHCP Server
; 69  UDP TFTPd           ; TFTPd (Trivial FTP) Server
; 81  TCP PERFSVM         ; Performance Toolkit
; 111 TCP PORTMAP         ; Portmap Server
...

```

3. Save your changes. The TCPIP user ID needs to be recycled in order for our changes to take effect. You can **FORCE** and **XAUTOLOG TCPIP** from a console. Alternatively, **if you are in position** to relPL the system, you can issue the command **shutdown reipl iplparms cons=sysc**.

When the system comes back, logon to TCPMAINT and check if everything was successful by issuing the **NETSTAT CLIENTS** command. You want to see that the service PERFSVM is a client (listening). This should be shown after a few screens of output:

```

==> netstat clients
...
Client: PERFSVM           Authorization: {none}
Notes Handled: none
Last Touched:  0:00:25
Vmcf error count: 0

```

The output of the command is lengthy, you want to make sure you have an entry for PERFSVM.

13.2.3 Configuring PERFSVM

The PERFSVM user ID is the Performance Toolkit service machine.

1. **Logon to PERFSVM.** If you successfully enabled the product, you should be put in a Performance Toolkit session and see the following text at the top of the screen:

```

FCX001           Performance Toolkit for VM
FCXBAS500I Performance Toolkit for VM FL510 BASE
Monitor event started -- recording is activated
Monitor sample started -- recording is activated

```

2. Press **PF12 twice** to get to a CMS prompt.
3. Copy the PROFILE XEDIT from the MAINT 191 disk so XEDIT sessions will have a common interface among user IDs.
 - a. Use the **VMLINK** command to both link the disk read-only and access it as the highest available file mode. The default read password is **read**, however, if you changed your passwords as described in section 4.9.1, "Changing passwords in USER DIRECT" on page 60, then it will be 1nx4vm.

```

==> vmlink maint 191
ENTER READ PASSWORD:
1nx4vm
DMSVML2060I MAINT 191 linked as 0120 file mode Z

```

- b. Copy the PROFILE XEDIT to the A disk:

```

==> copy profile xedit z = a

```
4. Copy the default configuration files, which are on PERFSVM's D disk, to your A disk:

```

==> copy * * d = a

```
 5. The main configuration file is FCONX \$PROFILE. Edit that file and search for the string VMCF. This should take you to line 173 where the next 4 lines are comments starting with an *. Perform the following changes:

- Uncomment the second and fourth line by changing *C to FC
- Change IDTEST PASSFILE to IDTEST CP on the fourth line

- Add the text **FC MONCOLL LINUXUSR ON** after the fourth line

The modified lines should be as follows:

```
==> x fconx $profile a
====> /vmcf
* Following command activates VMCF data retrieval interface
FC MONCOLL VMCF ON
* Following command activates Internet interface
FC MONCOLL WEBSERV ON TCPIP TCPIP 81 IDTEST CP
FC MONCOLL LINUXUSR ON
* Following command activates Internet interface with SSL
*C MONCOLL WEBSERV ON SSL TCPIP TCPIP 81 IDTEST RACF
...
```

6. Save your changes. The line you added tells the Performance Toolkit to collect Linux performance data.
7. Create a remote data retrieval authorization file – replace <systemID> with your system name:

```
==> x fconrmt authoriz
====> a 2
<systemID> PERFSVM S&FSERV
<systemID> MAINT DATA CMD EXCPMSG
```

8. Create a system identification file – replace <systemID> with your z/VM system name:

```
==> x fconrmt systems
====> a
<systemID> PERFSVM ESA N FCXRES00
```

9. Create a Linux system definition file. Add the TCP/IP addresses of your Linux system(s). The following example shows adding seven Linux virtual servers:

Use port 8803 for Linux performance data:

```
==> x fconx linuxusr
LINUX01 129.40.178.121:8803
LINUX02 129.40.178.122:8803
LINUX03 129.40.178.123:8803
LINUX04 129.40.178.124:8803
LINUX05 129.40.178.125:8803
LINUX06 129.40.178.126:8803
LINUX07 129.40.178.127:8803
```

10. Edit the PROFILE EXEC file and uncomment the five MONITOR SAMPLE and the two MONITOR EVENT statements:

Before:

```
...
/*** Once you have PERFKIT enabled and running uncomment the ***/
/*** following comments ***/
/* 'CP MONITOR SAMPLE ENABLE PROCESSOR' */
/* 'CP MONITOR SAMPLE ENABLE STORAGE' */
/* 'CP MONITOR SAMPLE ENABLE USER ALL' */
/* 'CP MONITOR SAMPLE ENABLE I/O ALL' */
/* 'CP MONITOR SAMPLE ENABLE APPLDATA ALL' */
/* 'CP MONITOR EVENT ENABLE STORAGE' */
/* 'CP MONITOR EVENT ENABLE I/O ALL' */
```

```
'PERFKIT' /* Invoke the PERFKIT module @FC012BD*/
```

Exit

After:

```

...
/**** Once you have PERFKIT enabled and running uncomment the      ***/
/**** following comments                                           ***/
'CP MONITOR SAMPLE ENABLE PROCESSOR'
'CP MONITOR SAMPLE ENABLE STORAGE'
'CP MONITOR SAMPLE ENABLE USER ALL'
'CP MONITOR SAMPLE ENABLE I/O ALL'
'CP MONITOR SAMPLE ENABLE APPLDATA ALL'
'CP MONITOR EVENT  ENABLE STORAGE'
'CP MONITOR EVENT  ENABLE I/O ALL'

'PERFKIT'                      /* Invoke the PERFKIT module   @FC012BD*/

Exit

```

11. Save your changes with the **FILE** subcommand.

You should now be ready to run the Performance Toolkit.

13.2.4 Starting the z/VM Performance Toolkit

To start the Performance Toolkit enter the following command:

```

====> perfkit
FCX001                      Performance Toolkit for VM              Autoscroll 12
FCXBAS500I Performance Toolkit for VM FL520 BASE
FCXAPP530I Connected to *IDENT for resource FCXRES00
FCXAPF530I Connected to *IDENT for resource FCXSYSTEM
FCXTCP571I Connected to TCP/IP server TCPIP on path 0003
FCXTCR571I Connected to TCP/IP server TCPIP on path 0004
FCXAPP527I User PERFSVM connected on path 0007
FCXAPC535I Connected to resource FCXRES00 on path 0006, for S&F-Coll
FCXTCP575I WebServer host IP address is 129.40.178.120:00081
FCXTCR575I TCPRequest host IP address is 129.40.178.120:41780
FCXTCR590I TCPRequest interface activated
HCPMOF6229E Monitor event collection is already active.
HCPMOG6229E Monitor sample collection is already active.
FCXTCP590I WebServer interface activated

```

Disconnect from PERFSVM now.

```
Command ====> disc
```

The Performance Toolkit should now be configured and running.


13.2.5 Using the z/VM Performance Toolkit

The Performance Toolkit can be used via a Web browser or 3270 interface.

Using a Web browser interface

To use the Web-enabled Performance Toolkit, perform the following steps:

1. Point a browser to your z/VM system at port 81. For example:
<http://129.40.178.120:81>
2. You should see your system on the *Web Session Setup* screen. Click it and you will be presented with the Web Server Logon screen.



Remote Performance Monitoring Session Setup

Web Server Logon

You are connected to the data retrieval interface of the Performance Toolkit for VM on system **LNXVM52**. Data retrieval authorization is based on your VM user identification on that system. Please enter your userid and password (CP)

VM UserID: Password :

Figure 13-1 Performance Toolkit logon screen

3. Enter any valid user ID and password. MAINT can be used.
4. You should see the *Central Monitoring System Load Overview* with your system name on the left side.
5. Click your system name and you should see the *Initial Performance Data Selection Menu* screen as shown in Figure 13-2 on page 206.




Figure 13-2 Browser interface to the Performance Toolkit

Using a 3270 interface

Logon to PERFSVM. Run the **PROFILE EXEC** and you should be put into the Performance Toolkit for z/VM environment. The subcommand **monitor** should present the panel shown below.

```
==> profile
FCXBAS500I Performance Toolkit for VM FL510 BASE
Monitor event started -- recording is activated
Monitor sample started -- recording is activated
...
FCX001 Performance Toolkit for VM
FCXBAS500I Performance Toolkit for VM FL510 BASE
HCPMOF6229E Monitor event collection is already active.
HCPMOG6229E Monitor sample collection is already active.
```

Command ==> **monitor**

```
FCX124 Performance Screen Selection (FL510 BASE ) Perf. Monitor

General System Data      I/O Data      History Data (by Time)
1. CPU load and trans.   11. Channel load  31. Graphics selection
2. Storage utilization   12. Control units 32. History data files*
3. Storage subpools      13. I/O device load* 33. Benchmark displays*
4. Priv. operations      14. CP owned disks* 34. Correlation coeff.
5. System counters       15. Cache extend. func.* 35. System summary*
6. CP IUCV services      16. DASD I/O assist 36. Auxiliary storage
7. SP00L file display*   17. DASD seek distance* 37. CP communications*
8. LPAR data             18. I/O prior. queueing* 38. DASD load
9. Shared segments       19. I/O configuration 39. Minidisk cache*
A. Shared data spaces    1A. I/O config. changes 3A. Paging activity
B. Virt. disks in stor.  21. User resource usage* 3B. Proc. load & config*
C. Transact. statistics  22. User paging load* 3C. Logical part. load
D. Monitor data          23. User wait states* 3D. Response time (all)*
E. Monitor settings      24. User response time* 3E. RSK data menu*
F. System settings       25. Resources/transact.* 3F. Scheduler queues
G. System configuration   26. User communication* 3G. Scheduler data
H. VM Resource Manager    27. Multitasking users* 3H. SFS/BFS logs menu*
I. Exceptions             28. User configuration* 3I. System log
K. User defined data*     29. Linux systems*      3K. TCP/IP data menu*
                          3L. User communication
                          3M. User wait states
```

Drilling down into report screens

You should now be able to use the active report screens. To drill down into these screens, move the cursor to any of the titles that are active (active titles display the number or letter in white, inactive titles are in green). Some of the more useful report screens to drill down into are:

```
21. User resource usage
22. User paging load
23. User wait states
28. User configuration
29. Linux systems
```

13.3 Monitoring Linux

To monitor Linux performance data, a data gatherer process must be running. There are different ways of gathering this data. Data can be gathered in the kernel and as a user application. SuSE SLES9, SLES10 and Red Hat RHEL 4 and RHEL 5 have been enabled for the kernel to gather performance data. There is a package called the *Linux RMF PM Data Gatherer* (also called *rmfpms*) that runs as a user application. Both of these data gatherers work in conjunction with the IBM z/VM Performance Toolkit.

13.3.1 Monitoring Linux with rmfpms

As a user application, the Linux RMF PM Data Gatherer (rmfpms) can be used. Currently it is not part of an IBM product and is intended for evaluation purposes only. A description of rmfpms is as follows:

“rmfpms is a modular data gatherer for Linux®. The gathered data can be analyzed using the RMF PM client application. The performance data is accessible through XML over HTTP so you can easily exploit it in your own applications.”

The following Web site is a starting point:

<http://www-03.ibm.com/servers/eserver/zseries/zos/rmf/rmfhtmls/pmweb/pmlin.html>

To download the data gatherer, scroll down and look for the following text and links:

- * 31 bit data gatherer (kernel24 - 630 KB, kernel26 - 1040 KB).
- * 64 bit data gatherer (kernel24 - 650 KB, kernel26 - 666 KB).

You can download the appropriate gatherer via a browser, or, if you have access to the Internet you can use an FTP client. You will want one of two files depending on whether you have a 31-bit or 64-bit kernel:

```
rmfpms_s390_kernel26.tgz - for 31-bit distributions
rmfpms_s390x_kernel26.tgz - for 64-bit distributions
```

Following is an example of downloading the tar file for 31-bit distributions directly from the Internet. **Get an SSH session on the controller** or any other virtual server. Change to the home directory via the `cd` command with no argument. Download the appropriate tar file with the `wget` command. For a 64-bit SLES 9 and for SLES 10 use:

```
# cd
# wget ftp://ftp.software.ibm.com/eserver/zseries/zos/rmf/rmfpm_s390x_kernel26.tgz
```

For RHEL 4 and RHEL 5 use:

```
# wget ftp://ftp.software.ibm.com/eserver/zseries/zos/rmf/rmfpm_s390x_kernel26_rhel4.tgz
```

Untar the file with the `tar` command and change to the `rmfpms/` directory:

```
# tar xzf rmfpms_s390x_kernel26*.tgz
# cd rmfpms/
# ls -aF
./      .rmfpms_config      README              bin/  enable_autostart*
../     .rmfpms_config_autostart  autostart_rmfpms  doc/
```

You should now be able to start **rmfpms** in the `bin/` directory with the following command:

```
# bin/rmfpms start
Creating /opt/IBM/rmfpms/.rmfpms ...
Starting performance gatherer backends ...
DDSRV: RMF-DDS-Server/Linux-Beta (Aug 9 2004) started.
DDSRV: Functionality Level=2.008
```

```
DDSRV: Reading exceptions from gpmexsys.ini and gpmexusr.ini.
DDSRV: Server will now run as a daemon process.
done!
```

Once it is running, you can view the performance data from a browser pointing to the Linux image and port 8803 as shown in Figure 13-3.




Figure 13-3 Browser view of rmfpms interface

You can also register Linux images with the Performance Toolkit - see section 13.4, “Registering Linux images with the Performance Toolkit” on page 210.

13.3.2 Monitoring Linux performance data from the kernel

To monitor Linux performance data directly from the kernel, the following must be true:

1. The APPLMON option must be set in the user directory.
2. Applmon data monitoring must be built into the kernel.

The first requirement should be true as the OPTION APPLMON was set for the controller and for Linux user IDs in earlier sections.

For the second requirement, SLES 9, SLES 10 and RHEL 5 now have this function built in. Details of this function are described in Chapter 15, *Linux monitor stream support for z/VM* in the manual *Device Drivers, Features, and Commands* for the October 2005 stream, on the Web at:

http://www-128.ibm.com/developerworks/linux/linux390/october2005_documentation.html

A quick description of how to use this built-in monitoring function follows.

There are three modules that are built into the kernel but are not loaded by default. They are named `appldata_mem`, `appldata_os` and `appldata_net_sum`. You can verify that they are not loaded with the `lsmod` and `grep` commands:

```
# lsmod | grep appldata
```

There is no output so no modules with the string `appldata` are loaded. Load those modules now via the `modprobe` command and verify they have been loaded:

```
# modprobe appldata_mem
# modprobe appldata_os
# modprobe appldata_net_sum
```

Now if you repeat the `lsmod` command, you should see the following:

```
# lsmod | grep appldata
appldata_net_sum      20064  0
appldata_os           21512  0
appldata_mem          20112  0
```

The directory in the virtual `/proc/` file system where the monitoring variables exist is `/proc/sys/appldata/`. In this directory there are five files as follow:

<code>timer</code>	Controls whether any data gathering is in effect.
<code>interval</code>	Sets the interval, in milliseconds, that samples will be taken.
<code>mem</code>	Controls the memory data gathering module
<code>os</code>	Controls the CPU data gathering module
<code>net_sum</code>	Controls the net data gathering module

To turn on the built in kernel monitoring, use the `echo` command to send a non-zero value into four of the five monitoring variables in the `/proc/` virtual file system:

```
# echo 1 > /proc/sys/appldata/timer
# echo 1 > /proc/sys/appldata/mem
# echo 1 > /proc/sys/appldata/os
# echo 1 > /proc/sys/appldata/net_sum
```

Built-in kernel monitoring should now be turned on. You may only want to leave the monitoring on for specific periods of time. As Linux monitoring data is captured, the Performance Toolkit's minidisk space can fill up relatively quickly.

13.4 Registering Linux images with the Performance Toolkit

To register Linux images that have performance data gathering enabled, **logon to PERFSVM** and create a file `FCONX LINUXUSR A` and add Linux user ID/IP address:port pairs. The following example shows adding the SLES9X and LINUX01 user IDs to this file:

```
==> x fconx linuxusr a
====> a 3
*Linux-ID   IP address for DDS Interface:Port
SLES9X      <129.40.178.130>
LINUX01     <129.40.178.121>
```

Restart the performance toolkit via the `profile` command. After the system has had some time to collect data, you should be able to use the Performance Toolkit to monitor Linux systems that have both monitoring data being captured and an entry in the `FCONX LINUXUSR` file. To view that data, drill down into menu 29, Linux systems.

13.5 Monitoring z/VM and Linux via a Web application

A basic Web application is written to demonstrate one way to view data of both z/VM and the Linux virtual servers. The system is named DAZL, an acronym for **D**ata **A**bout **z/VM** and **L**inux (yes, a name shamelessly force fit to come up with a cool acronym :)). To supply the DAZL information, a Web Server is run on the controller that makes available some HTML pages in the DocumentRoot directory and some bash shell scripts in the cgi-bin/ directory. If you have been progressing sequentially through the book, the Web server should be configured by now. If not, see chapter 7, especially the section “Configuring Apache for DAZL” in section 7.7.

A philosophy of DAZL is to keep common information grouped into pages about one screen in size, utilizing HTML tables to maximize the real estate of a browser screen. This application is not a heavily tested, nor is it a professional monitoring system. Rather it is a set of simple Web pages and scripts that can be a start of a home-grown monitoring tool, if you choose to investigate it.

This section shows some screen captures of the Web application, then the application’s relatively simple design is described in some detail in section 13.5.3, “DAZL design” on page 220. All source code is included in the controller RPM described in.

Important: DAZL is not a strategic direction for monitoring z/VM and Linux. A more strategic solution from IBM’s point of view is IBM Director and z/VM Center. See section 1.4, “IBM Director and z/VM Center Extension” on page 5.

13.5.1 Overall design

Following is a block diagram of the overall design of DAZL from an execution point of view:




Figure 13-4 DAZL overall design

13.5.2 DAZL screen captures

The main Web page is shipped with the file name `index.html`. If you followed all the steps in section It allows you to generate basic pages or reports about:

Linux systems	Each Linux virtual server that was cloned
z/VM DASD	Each volume in the USER DISKMAP report on the MAINT 191 disk
z/VM status	Output of simple z/VM query commands

DAZL home page

Following is a screen capture of the DAZL home page:




Figure 13-5 DAZL main page

z/VM status page

If you click the **z/VM status** button on the right, you will get some basic information about your z/VM system from the following commands:

- ▶ IND
- ▶ Q ALLOC MAP
- ▶ Q NAMES
- ▶ Q STOR, Q XSTOR
- ▶ Q CPLEVEL
- ▶ Q VSWITCH

These values are obtained via the Linux **vmcp** interface to z/VM CP commands. Following is a screen capture of the z/VM status page:




Figure 13-6 z/VM status page

From this page, you can drill down to get more detailed information. From the **Indicate Load** table cell, you can drill down to view the output of **INDICATE QUEUES EXP**. From the **QUERY VSWITCH** table cell, you can drill down to view the output of the **QUERY VSWITCH DETAILS** and **QUERY VSWITCH ACCESS** commands.

DASD report

If you click on the **DASD report** button in the center of the main page, you will get a report on the z/VM system volumes that comprise your system. This report is another way of displaying the contents of the USER DISKMAP file. The accuracy of the report generated relies on the USER DISKMAP file being up to date under /backup/vm/USER.DISKMAP on the controller. There is a checkbox that allows update this file on Linux from the MAINT 191 disk. Clicking that checkbox will copy the USER DISKMAP file from z/VM, however, it still relies on the file being up to date. If you have modified the USER DIRECT file and run **DIRECTXA** but not run **DISKMAP**, then there is a good chance the data will be out of date (a good convention to adopt is to always run **DISKMAP** before running **DIRECTXA**).

Following is a screen capture of the DASD report

Volume Label	Device Address	Minidisks (first three)	Status	Cylinders used/total
MMA711	A711	\$ALLOC\$ A04 SLES9X 100 SLES9X 102	CP SYSTEM	3339/3339
MMA712	A712	\$ALLOC\$ A05 SLES9X 200	CP SYSTEM	3339/3339
MMA713	A713	\$ALLOC\$ A06 LNXMAINT 0191 LNXMAINT 0192 More	CP SYSTEM	3339/3339
MMA714	A714	\$ALLOC\$ A07 SLES9X 204	CP SYSTEM	3339/3339
MMA715	A715	\$ALLOC\$ A08 SLES9X 205	CP SYSTEM	3339/3339
MMA716	A716	\$ALLOC\$ A09 SLES9X 206	CP SYSTEM	3339/3339
MMA717	A717	\$ALLOC\$ A0A SLES9X 207	CP SYSTEM	3339/3339
MMA718	A718	\$ALLOC\$ A0B LINUX01 200 LINUX01 202	CP SYSTEM	3339/3339

Figure 13-7 DASD report

For each DASD in the report, you can drill down into the **Volume Label** column to get the text of that volume's report in the USER DISKMAP file, and into the **Device Address** column to get the output of the CP command **QUERY DASD DETAILS <vaddr>** for that volume.

Linux report

If you click on **Linux report** in the left side of the main page, you will get a report on the Linux clones. It is generated starting from data under the `/backup/linux/` directory. When the **clone.sh** script clones a new Linux image, it also creates a directory of the form `<userID>-on-<TCP.IP.address>/` under `/backup/linux/`. For example, if you clone a virtual server to LINUX01 with an IP address of 129.40.178.121, the directory created will be `/backup/linux/LINUX01-on-129.40.178.121/`. A row is created in the report's table for each directory, assuming they are associated with Linux systems. If this directory structure does not reflect the existing Linux images, the report will not be correct.

Important: If you have not used the **clone.sh** script to clone and still want to try out DAZL, this is possible. You will just have to create a directory structure of Linux servers under `/backup/linux/` described above.

For each directory found, the user ID and TCP/IP address are extracted from the name. The existence of these directories drive the main loop of the report generation. Each TCP/IP address that is extracted from the directory structure is **pinged**. If the ping is successful, the table cell entries for that virtual server are displayed in green and made to be drill down links. If the ping is not successful, the table cell entries are displayed as plain red text. The **Sitar Cron** entries are drawn in green if the `sitar.html` file is found in each virtual server's `/etc/` directory and in red if it is not.

Following is a screen capture of the Linux report:

z/VM User ID	Linux Host name	IP address	Sitar data	Description/Log
LINUX01	lat121.pbm.ihost.com	129.40.178.121	Cron New	This is a Web Server
LINUX02	lat122.pbm.ihost.com	129.40.178.122	Cron New	This is an LDAP server
LINUX03	lat123.pbm.ihost.com	129.40.178.123	Cron New	This is a Samba server
LINUX04	lat124.pbm.ihost.com	129.40.178.124	Cron New	This is an application development server
LINUX05	lat125.pbm.ihost.com	129.40.178.125	Cron New	Test server with LDAD, automount /home/
LINUX06	lat126.pbm.ihost.com	129.40.178.126	Cron New	This is a second Web Server

Figure 13-8 Linux report

Linux report drill down pages

From the Linux report page, you can drill down into the following columns:

z/VM User ID	z/VM-related data
Linux host name	Linux non-networking related data
IP address	Linux networking related data
Sitar data	Output of Sitar - either from the nightly cron run, or a new report in real time

In the right-most column, **Description/Log**, you can keep a record of each virtual server. The data is retrieved from and stored in the file `descLog.txt` in each of the virtual server's directories under `/backup/linux/`. These files can be viewed and edited directly from the Web application.

z/VM User ID drill down

Following is a screen capture of the z/VM related data when drilling down under the **z/VM user ID** column:




Figure 13-9 z/VM user ID drill down report

The first table cell in the upper left corner shows the directory entry of the specified user ID extracted from the USER DIRECT file. This file must be up to date on the controller. There is a checkbox, **Refresh /backup/vm**, on the DAZL home page that allows you to update all z/VM configuration files including the USER DIRECT file. The table cell in the upper right shows the output of the **INDICATE USER** command for the specified user ID. The bottom two table cells display the contents of the installation parameter files with file types of PARMFILE for SLES 9 and PARM-S10 for SLES 10, or PARM-RH5 and CONF-RH5 for RHEL5.

Linux host name drill down

Following is a screen capture of the z/VM related data when drilling down under the **Linux host name** column:




Figure 13-10 Linux information drill down report

This report gives the output from the following commonly run commands to query the status of Linux systems.

df -h	Display file system disk usage
mount	Display mounted file systems
runlevel	Display previous and current run levels
w	Show who is logged on
uname	Display system information about this distribution
free -m	Display megabytes of free and used memory
ps tree	Display a tree of processes
lsdasd	List DASD (disks)

IP address drill down

Following is a screen capture of the z/VM related data when drilling down under the **IP address** column:




Figure 13-11 Linux networking drill down report

This report is generated from the output of the following four network-related commands:

ifconfig eth0	Display information about the interface eth0
ip link show	Display IP link information
netstat -tan	Display TCP network information
iptables -L	List IP tables (firewall) rules

Sitar data drill down

You can drill down into the **Cron** link which will use the Sitar output file that should be generated by a cron job each night. Also you can drill down into the **New** link which will generate a Sitar HTML file on demand. Following is a screen capture of the z/VM related data when drilling down under the **Sitar** column:




Figure 13-12 Sitar drill down report

Linux report log file editing

Another useful feature of this Web application is the ability to maintain a flat text file for each of the Linux virtual servers from a browser. The basic premise is that the first line of the file is an overall description of the virtual server and the remainder of the file can be used to log changes. This feature utilizes Asynchronous Java and XML (AJAX) for pushing and pulling changes between the browser and the Web server without having to update the entire page.

The flat text files are maintained on the controller under the directory `/backup/linux/` with one file named `descLog.txt` under the each Linux subdirectory (of the form `<userID>-on-<TCP.IP.address>`). For example, a Linux system running on the user ID `LINUX01` with a TCP/IP address of `129.40.178.121` would have a flat text file named `/backup/linux/LINUX01-on-129.40.178.121/descLog.txt`

You can these files manually via an SSH session on the controller. That is still true, but editing the files via a Web interface is another, perhaps more convenient, way of viewing and editing a set of files. Please note there is no mechanism for locking files. If you are editing a file via the Web interface and in the file system (or from two different browsers), then it is possible to lose changes. Adding a locking mechanism is left as an exercise for the reader :)).

Following is a screen capture of one Linux description/log file being edited:




Figure 13-13 Editing Linux description/log files in place

13.5.3 DAZL design

This section discusses some of the design of DAZL.

The main page, `index.html`, is a static HTML page which invokes one of three Common Gateway Interface (CGI) bash scripts. These scripts are run on the server in real time to generate reports. Those scripts in turn, invoke other CGI scripts where the reports have drill down links. The ability to edit description/log files in place utilizes Java Script and AJAX.

The xhr class and motivation to use AJAX was obtained from the book *Build Your Own AJAX Web Applications*, by Matthew Eernisse, published by SitePoint Ltd in 2006. See the following Web site for details on this book:

<http://www.sitepoint.com/books/ajax1/>

The Java Script file, `xhr.js`, is included, unchanged, with permission. It is a part of the Fleegix.js JavaScript Toolkit, copyrighted and distributed under the Apache License, v2.0. It is available from:

<http://js.fleegix.org/>

The main page is named `index.html` which goes in Apache's DocumentRoot, `/srv/www/htdocs/`, by default in SLES 9 and 10 or `/var/www/html` in RHEL 5. In addition there is the AJAX Java Script file `xhr.js`, obtained from the book above, and the Java Script `editLog.js` written to edit the text files. The CGI scripts reside in Apache's CGI directory, `/srv/www/cgi-bin/`, by default in SLES 9 and 10. They are as follow:

dazd.sh	Create the DASD report from the USER DISKMAP file
dazl.sh	Create the Linux report from the directories under <code>/backup/linux/</code>
dazvm.sh	Create the z/VM status report
getDasdInfo.sh	Create a simple page from z/VM QUERY DASD DETAILS command
getDesc.sh	Return the first line (the description) of the file <code>descLog.txt</code>

getLinuxData.sh	Create a table page from commonly used Linux commands
getLog.sh	Return the entire file descLog.txt
getNetworkData.sh	Create a table page from commonly used Linux network commands
indQ.sh	Create a simple page from z/VM QUERY DASD DETAILS command
qVswitch.sh	Create a simple page from the z/VM QUERY VSWITCH command
getVMdata.sh	Create a page of z/VM data related to one Linux virtual server
runSitar.sh	Create a Sitar HTML file for a Linux virtual server on demand
getVolMap.sh	Create a page with value from USER DISKMAP for a z/VM volume
saveLog.sh	Save in-place changes to descLog.txt file for a Linux virtual server

Following is a block diagram of the DAZL system from a programming point of view:




Figure 13-14 DAZL design block diagram

Backup and restore

I never think of the future. It comes soon enough.

--Albert Einstein

Given the opening quote, Albert Einstein would probably have not have made a good z/VM and Linux system administrator :)).

Backup and restore can be divided into two fundamental categories, each of which must be able to answer a basic question:

Incremental back up How do I quickly get back a file that was deleted or corrupted?

Disaster recovery How do I restore my systems if my entire data center is destroyed?

A key attribute of incremental back up is self-service. Ideally, you as the system administrator should not have to restore individual files that have been deleted or corrupted, rather, you should be easily be able to tell end users how to do it themselves. Or at least you should be able to get access to the files quickly.

A key to disaster recovery is practice. There is no *silver bullet*; disaster recovery takes planning and hard work. One rule of disaster recovery to consider is “For every backup you make, you should do one restore”. This chapter only touches on disaster recovery in the final section.

Getting back to incremental backup and restore, both your z/VM system and your Linux virtual servers must be considered. The following sections address this:

- ▶ “Incremental backup of z/VM” on page 224
- ▶ “Incremental backup of Linux virtual servers” on page 227

14.1 Incremental backup of z/VM

The following configuration files on z/VM are important:

- ▶ SYSTEM CONFIG on the MAINT CF1 minidisk
- ▶ USER DIRECT on the MAINT 2CC minidisk
- ▶ <system_ID> TCPIP and SYSTEM DTCPARMS on the TCPMAINT 198 minidisk
- ▶ TCPIP DATA on the TCPMAINT 592 minidisk
- ▶ PROFILE EXEC on the AUTOLOG1 191 minidisk

In addition, it would be helpful to backup all files on the LNXMAINT 192 minidisk. Two bash scripts are written to back up these files and other z/VM data:

backupVM.sh	Backs up the files listed above. This script should not be your primary backup procedure, but it may help as a secondary method.
getVMinfo.sh	Runs some basic CP commands to capture information that may be helpful.

14.1.1 The getVMinfo.sh script

There are some CP commands which also capture important information about the systems. A small script, **getVMinfo.sh** is supplied to issue the CP commands. This file should have been copied to the directory `/usr/local/sbin/`:

```
# cat /usr/local/sbin/getVMinfo
#!/bin/bash
...
echo "output of CP QUERY PROC:"
echo "-----"
vmcp QUERY PROC
echo ""
echo "output of CP QUERY FILES:"
echo "-----"
vmcp QUERY FILES
echo ""
echo "output of CP QUERY NSS ALL MAP:"
echo "-----"
vmcp QUERY NSS ALL MAP
echo ""
echo "output of CP QUERY CPLEVEL:"
echo "-----"
vmcp QUERY CPLEVEL
```

Running getVMinfo.sh script

Try running the script. You should see output similar to the following:

```
# getVMinfo.sh
output of CP QUERY PROC:
-----
PROCESSOR 00 MASTER
PROCESSOR 01 ALTERNATE
...

output of CP QUERY FILES:
-----
FILES: 0000133 RDR, 0000018 PRT,      NO PUN

output of CP QUERY NSS ALL MAP:
-----
```

```

FILE FILENAME FILETYPE MINSIZE BEGPAG ENDPAG TYPE CL #USERS PARMREGS VMGROUP
0043 CMS      NSS      0000256K 00000 0000D  EW  A  00005  00-15  NO
...
output of CP QUERY CPLEVEL:
-----
z/VM Version 5 Release 2.0, service level 0601 (64-bit)
Generated at 02/13/06 11:45:25 EDT
IPL at 08/14/06 08:51:11 EDT

```

14.1.2 The backupVM.sh script

The **backupVM.sh** script backs up important z/VM files to the `/backup/vm/` directory. The first command that it runs is the above **getVMinfo.sh** script.

Important: Please note two important aspects of this script

1. It copies the USER DIRECT file which contains all of the system's passwords (unless you are also using an external security manager). So security to the controller becomes as important as security to the MAINT user ID.
2. It backs up important z/VM data to a Linux system running under the same z/VM. If your z/VM system cannot be brought back, then this Linux system cannot be started and you cannot get the important z/VM data. Therefore, you may consider copying the output of this script to a different LPAR or different physical server.

Following is the main portion of the **backupVM.sh** script:

```

# cd /usr/local/sbin/
# cat backupVM.sh
...
# main()
cd /backup/vm          # change directory to /backup/vm where data is saved
getVMinfo.sh > zVMinfo.txt # run getVMinfo.sh to save basic VM information

# get USER DISKMAP from MAINT 191
linkAccess MAINT 191 as 1191
getFile USER.DISKMAP from 1191
relDetach 1191

# get USER DIRECT from MAINT 2CC
linkAccess MAINT 2CC as 12cc
getFile USER.DIRECT from 12cc
relDetach 12cc

# get SYSTEM CONFIG from MAINT CF1
linkAccess MAINT CF1 as 1cf1
getFile SYSTEM.CONFIG from 1cf1
relDetach 1cf1

# get TCPIP files from TCPMAINT 198
systemID=`vmcp q userid | awk '{print $3}'`
linkAccess TCPMAINT 198 as 1198
getFile $systemID.TCPIP from 1198
getFile SYSTEM.DTCPARMS from 1198
relDetach 1198

```

```
# get TCPIP DATA from TCPMAINT 592
linkAccess TCPMAINT 592 as 1592
getFile TCPIP.DATA from 1592
relDetach 1592

# get PROFILE EXEC from AUTOLOG1 191 - rename to different FT
linkAccess AUTOLOG1 191 as 2191
CMSdevice=`cat /proc/dasd/devices | grep 2191 | awk '{print $7}'`
cmsfscat -a -d /dev/$CMSdevice PROFILE.EXEC > PROFILE.EXECAUT1
relDetach 2191

getFiles 191          # Get all files from LNXMAINT 192 which is our 191 disk
```

The `linkAccess()` function uses the CP **LINK** command via **vmcp** to link to the specified disk read-only, then the **chccwdev** command to enable the new disk. The `getFile()` function uses the **cmsfslst** command to copy a single file to the `/backup/vm/` directory.

Running backupVM.sh script

Try running it now. You may choose to first remove any existing files. You should see output similar to the following:

```
# cd /backup/vm
# rm *          // be sure you are in the right directory when you issue this!
# backupVM.sh
Backing up USER.DISKMAP seems to have succeeded
Backing up USER.DIRECT seems to have succeeded
Backing up SYSTEM.CONFIG seems to have succeeded
Backing up LNXVM52.TCPIP seems to have succeeded
Backing up SYSTEM.DTCPARMS seems to have succeeded
Backing up TCPIP.DATA seems to have succeeded
Backing up CHPW52.XEDIT seems to have succeeded
...
Backing up SLES-S10.EXEC seems to have succeeded
```

You should see a number of files copied. All text files are converted to ASCII so you should be able to read them from Linux. Your output will differ:

```
# ls -F
CHPW52.XEDIT      LINUX04.PARMPFILE  SLES-S10.EXEC     SYSTEM.CONFIG
CPFORMAT.EXEC    LINUX05.PARMPFILE  SLES10.EXEC       SYSTEM.DTCPARMS
LABEL520.EXEC    LINUX06.PARMPFILE  SLES10.INITRD     TCPIP.DATA
LABEL520.XEDIT   LINUX07.PARMPFILE  SLES10.KERNEL     USER.DIRECT
LINUX01.PARMPFILE LNXVM52.TCPIP     SLES10.PARM-S10   USER.DISKMAP
LINUX02.PARMPFILE PROFILE.EXEC       SLES10.PARMPFILE  zVMinfo.txt
LINUX03.PARMPFILE PROFILE.EXECAUT1   SWAPGEN.EXEC
```

Running backupVM.sh daily via cron

The **backupVM.sh** script is run once a day on the controller via the **cron** daemon from the script `/etc/cron.daily/nightly.sh`:

```
# tail -4 /etc/cron.daily/nightly.sh
# run sitar, backupVM.sh and backupLinux.sh nightly on the controller
sitar --format=html --outfile=/srv/www/htdocs/sitar.html
backupVM.sh          # backup z/VM files to /backup/vm/
backupLinux.sh         # backup Linux files to /backup/linux/
```

If this does successfully run each night, you will always have backed up files that are no older than one day.

14.2 Incremental backup of Linux virtual servers

Your IT shop may have an existing backup/restore solution for Linux. For example:

- ▶ Computer Associates' Brightstor Enterprise Backup
- ▶ Innovation Data Processing's FDR/UPSTREAM
- ▶ IBM's Tivoli Storage Manager (TSM)
- ▶ SecureAgent Software's SecureBackup
- ▶ Veritas' Backup Exec

For details of these and other solutions, see the *Software Developer Products for Linux on IBM System z and S/390* page on the Web at:

<http://www-1.ibm.com/servers/eserver/zseries/solutions/s390da/linuxproduct.html>

Descriptions of these products are outside the scope of this book, and they are a much more complete solution than what is described in the sections that follow.

Some simple **cron** scripts and configuration of **rsync** follow. These will result in the `/etc/` directories and other information of the virtual servers to be backed up to the controller nightly.

14.2.1 Configuring rsync on the controller

Because the master image was set up to allow the controller to copy its `/etc/` directory and for ssh key-based authentication, each of the virtual servers' `/etc/` directories can be copied with a single **rsync** command. For example, the following commands will copy the `/etc/` directory on LINUX01 at IP address 129.40.178.121:

```
# cd /backup/LINUX01-on-129.40.178.121
# rsync -r --timeout=30 129.40.178.121:/etc .
```

To perform this backup on each of the virtual servers, a script named **backupLinux.sh** is provided. It iterates through the directories created by the clone script under `/backup/linux/` of the form `<userID>-on-<IPaddress>`:

```
# cd /usr/local/sbin
# cat backupLinux.sh
#!/bin/bash
...
BACKUP="/backup/linux"
cd $BACKUP
for i in *-on-*          # iterate through dirs with "-on-" in their names
do
    IP_addr=${i#*-on-}    # this chops the head off and grabs the IP address
    cd $BACKUP/$i        # change directory to next virtual server
    rsync -r --timeout=3 $IP_addr:/etc . > /dev/null 2>&1 # use rsync to backup
    rc=$?
    if [ $rc != 0 ]; then # error
        echo "Error: rsync returned $rc while backing up $i"
    else
        echo "Backing up $i seems to have succeeded"
    fi
done
```

This script should backup the `/etc/` directory of each Linux system cloned to the appropriate directory under `/backup/linux/`.

14.2.2 Configuring sitar to run nightly on the virtual servers

SITAR is a tool that creates documentation describing your system. It is an acronym for System InformaTion At Runtime. In addition to backing up the `/etc/` configuration files, a document describing your system might be helpful. If sitar is run once a day and the output is put in a file in `/etc/`, then you will have additional information about your system backed up.

This command can easily be run nightly via **cron**:

```
# cd /etc/cron.daily
# vi run-sitar    // add two lines
#!/bin/bash
sitar --format=html --outfile=/etc/sitar.html
```

14.3 Disaster recovery of z/VM and virtual Linux servers

In addition to incremental backups, you should do regular system backups of your z/VM system. Sections 4.10, “Backing up your z/VM system to tape” on page 61 and 4.12, “Restoring your z/VM system from tape” on page 67 just touched on this.

You may choose to do a full volume backups of all DASD in the LPAR. Then in the event of a disaster, your entire system could be restored. This is the most thorough and best way to perform backups, and is one of the areas where the System z platform excels.

You may also choose to backup a subset of the volumes (or perhaps you may choose to backup all volumes once a quarter, but backup a subset once a month). Two critical user IDs are LNXMAINT and the controller user ID. If you have followed all steps in this book, then each of the virtual servers `/etc/` file system is being backed to `/backup/` file system which is the controller user ID's 203 minidisk in this book. The master image root file system (100 minidisk) and the controller root file system (200 minidisk) are also critical. Given that these minidisks are vital to your system, you may choose to back them up more regularly or in a different fashion. You can look at the `USER DISKMAP` file, created on the **MAINT 191** disk by the **DISKMAP** command, to determine which volumes to back up. You will probably have many more critical volumes than these three, but consider these especially in your hierarchy of backed up data.

References

This book refers to additional material that can be downloaded from the Internet as described below.

A.1 Related books

These publications are also relevant as further information sources:

- ▶ *Linux for zSeries and S/390 Device Drivers, Features, and Commands*, LNUX-1403
- ▶ *SUSE LINUX Enterprise Server: INSTALLATION AND ADMINISTRATION*
- ▶ *SUSE LINUX Enterprise Server: ARCHITECTURE-SPECIFIC INFORMATION*
- ▶ *SUSE LINUX Enterprise Server: START-UP GUIDE*
- ▶ *z/VM Guide for Automated Installation and Service: Version 5 Release 1.0*, GC24-6099
- ▶ *z/VM System Messages and Codes — CP: Version 5 Release 1.0*, GC24-6119
- ▶ *z/VM TCP/IP Messages and Codes: Version 5 Release 1.0*, GC24-6124
- ▶ *The Program Directory for Performance Toolkit for VM*, GI11-4800
- ▶ *z/VM CP Commands and Utilities Reference: Version 5 Release 1.0*, SC24-6081
- ▶ *z/VM CP Planning and Administration: Version 5 Release 1.0*, SC24-6083
- ▶ *z/VM Getting Started with Linux on zSeries: Version 5 Release 1.0*, SC24-6096
- ▶ *z/VM TCP/IP Planning and Customization: Version 5 Release 1.0*, SC24-6125
- ▶ *z/VM Performance Toolkit*, SC24-6136
- ▶ *Communication Controller for Linux on zSeries V1.0 Implementation Guide*, SC31-6872
- ▶ *Linux on IBM eServer zSeries and S/390: Performance Toolkit for VM*, SG24-6059
- ▶ *Linux on IBM eServer zSeries and S/390: Application Development*, SG24-6807
- ▶ *IBM Lotus Domino 6.5 for Linux on zSeries Implementation*, SG24-7021
- ▶ *Printing with Linux on zSeries Using CUPS and Samba*, REDP-3864

A.2 Online resources

These Web sites and URLs are also relevant as further information sources:

- ▶ The Linux for zSeries and S/390 portal:
<http://linuxvm.org/>
- ▶ The linux-390 list server:
<http://www2.marist.edu/htbin/wlvindex?linux-390>
- ▶ Linux on System z and S/390 developerWorks®:
<http://awlinux1.alphaworks.ibm.com/developerworks/linux390/index.shtml>
- ▶ z/VM publications:
<http://www.vm.ibm.com/pubs/>
- ▶ z/VM performance tips:
<http://www.vm.ibm.com/perf/tips/>

A.3 Important z/VM files

z/VM differs from Linux in regard to the location and number of configuration files. In Linux, there are many configuration files and most of them are in or under the `/etc/` directory. On z/VM, there are relatively few configuration files. However, they are on many different minidisks. Table 14-1 provides a summary and the location of important z/VM configuration files.

Table 14-1 Important z/VM configuration files

File	Location	Description
SYSTEM CONFIG	MAINT CF1	This is the operating system's main configuration file. It defines the system name, the CP volumes, User volumes and other settings.
USER DIRECT	MAINT 2CC	This file defines the user directory. All user IDs or virtual machines known to the system are defined here (assuming a directory maintenance product is not being used).
<System_ID> TCPIP	TCPMAINT 198	This file defines the resources for the primary z/VM TCP/IP stack, including TCP/IP address, OSA resources, subnet mask and gateway. It is initially created by the IPWIZARD tool as PROFILE TCPIP.
SYSTEM DTCPARMS	TCPMAINT 198	This file is created to define the TCP/IP stacks on the system. It is initially created by the IPWIZARD tool.
TCPIP DATA	TCPMAINT 592	This file defines the DNS server, the domain name and some other settings. It is initially created by the IPWIZARD tool.
PROFILE EXEC	AUTOLOG1 191	This file is a REXX EXEC that is run when the system starts up. It is analogous to the <code>/etc/inittab</code> file in Linux.

A.4 Cheat sheets

This section contains quick references or “cheat sheets” for the XEDIT and vi editors

A.4.1 XEDIT cheat sheet

XEDIT has line commands which are typed on the command line (===>) and prefix commands which are typed over the line numbers on the left side of the screen.

Line Commands

a	Add a line
a<n>	Add 'n' lines
c/<old>/<new>/ <n> <m>	Search for string 'old' and replace it with 'new' for 'n' lines below the current line and 'm' times on each line. '*' can be used for 'n' and 'm'
/<string>	Search for 'string' from the current line
-/<string>	Search backwards for 'string'
all /<string>/	Show all occurrences of 'string' and hide other lines
bottom	Move to the bottom of the file
top	Move to the top of the file
down <n>	Move down 'n' lines
up <n>	Move up 'n' lines
file	Save the current file and exit XEDIT
ffile	Save the current file and exit but don't warn of overwrite
save	Save the current file but don't exit
quit	Exit XEDIT if no changes have been made
qquit	Exit XEDIT even if changes have not been saved
left <n>	Shift 'n' characters to the left
right <n>	Shift 'n' characters to the right
get <file>	Copy file and insert past the current line
:<n>	Move to line 'n'
?	Display last command
=	Execute last command
x <file>	Edit 'file' and put it into the XEDIT "ring"
x	Move to the next file in the ring

Prefix Commands

a	Add one line
a<n>	Add 'n' lines
c	Copies one line
cc	Copies a block of lines
d	Deletes one line
dd	Deletes a block of lines
f	Line after which a copy (c) or a move (m) is to be inserted
p	Line before which a copy (c) or a move (m) is to be inserted
i	Insert a line
i<n>	Insert 'n' lines
m	Move one line
mm	Move a block of lines
"	Replicate a line
"<n>	Replicate a line 'n' times
""	Replicate a block of lines

A.4.2 vi cheat sheet

Following is a small subset of vi commands, but those most commonly used. The vi editor has three modes:

1. Input mode - the **Insert** key, **i**, **o** (add a line below), **O** (add a line above) and other commands put you in this mode. When you are in this mode you will see the text --INSERT-- in the last line.
2. Command mode - 'Esc' gets you out of input mode and into command mode

```

i      brings you back to input mode
dd     deletes a line and puts it in the buffer
<n>dd  delete <n> lines
x      delete a character
dw     delete a word
p      add the buffer past the current location
P      add the buffer before the current location
o      add a line and go into insert mode
/string - search for string
n      do the last command again (this can be powerful)
jkl;   cursor movement
A      add text at the end of the line
<nn>G  go to line <nn>
G      go to the last line in the file
yy     yank a line (copy into buffer)
<n>yy  yank n lines

```

3. Command line mode - pressing the colon : key brings you to this mode

```

:wq     save (write & quit)
:q!     quit and discard changes
:<nn>    go to line number <nn>
:r <file> read <file> into the current file
:1,$s/old/new/g globally replace <old> with <new>
:help    give help

```

Common source code

This section lists source code for z/VM and Linux that is common regardless of Linux distribution. The common code is in the following categories

- ▶ z/VM REXX EXECs and XEDIT macros
- ▶ Bash scripts on the master image
- ▶ Bash scripts on the controller

B.1 z/VM REXX EXECs and XEDIT macros

This section lists z/VM REXX EXECs and XEDIT macros.

B.1.1 The CPFORMAT EXEC

Following is the code for the EXEC that formats multiple disks via **CPFMTXA** (described in section 4.6.1, “Formatting the paging volumes” on page 47):

```

/*-----+*/
/* EXEC: CPFORMAT - wrapper around CPFMTXA to format many DASD */
/*   retVal: 0 - success */
/*           1 - help was asked for or given */
/*           2 - user is not sure */
/*           3 - DASD (minidisk) range is not valid */
/*           4 - at least one DASD (minidisk) is reserved to MAINT */
/*-----+*/

/*-----
THE PROGRAM IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTIES OR
CONDITIONS OF ANY KIND, EITHER EXPRESS OR IMPLIED INCLUDING, WITHOUT
LIMITATION, ANY WARRANTIES OR CONDITIONS OF TITLE, NON-INFRINGEMENT,
MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.
NEITHER RECIPIENT NOR ANY CONTRIBUTORS SHALL HAVE ANY LIABILITY FOR
ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING WITHOUT LIMITATION LOST PROFITS), HOWEVER CAUSED
AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY,
OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF
THE USE OR DISTRIBUTION OF THE PROGRAM OR THE EXERCISE OF ANY RIGHTS

```

```

GRANTED HEREUNDER, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES
-----*/

firstChar = 'M' /* change this for an LPAR ID other than 'M' */
parse upper arg dasds "AS " type
if ((dasds = '') | (dasds = '?')) then call help
labelPrefix = getLabelPrefix(firstChar type)
numDasd = parseDasd(dasds)
answer = areYouSure(type)
if (answer = 'Y') then /* the user is sure */
do
    retVal = doFormat(labelPrefix numDasd type)
    call doReport
end
else
    retVal = 2
exit retVal

/*+-----+*/
help: procedure
/*+-----+*/
    parse source . . fn .
    say ''
    say 'Synopsis:'
    say ''
    say '  Format one or a range of DASD as page, perm, spool or temp disk space'
    say '  The label written to each DASD is V<t><xxxx> where:'
    say '    <t> is type - P (page), M (perm), S (spool) or T (Temp disk)'
    say '    <xxxx> is the 4 digit address'
    say ''
    say 'Syntax is:'
    say "                                     .-PAGE-."
    say "  >>--CPFORMAT--.-rdev-----.-AS---+-PERM-+------><"
    say "          | <-----< |         '-SPOL-'"
    say "          '-rdev1-rdev2-----'  "
    say ''
exit 1

/*+-----+*/
areYouSure: procedure
/*| Show minidisks, ask are you sure                                     |*/
/*| parm 1: type - PERM, PAGE, or SPOL                                   |*/
/*| retVal: firstChar - LPAR identifier, 'V' by default                   |*/
/*+-----+*/
    arg type
    say ''
    say 'WARNING - this will destroy data!'
    say 'ARE YOU SURE you want to format the DASD as' type 'space (y/n)?'
    parse upper pull answer
return substr(answer, 1, 1) /* from areYouSure */

/*+-----+*/
getLabelPrefix: procedure
/*| Return first two characters of label                                   |*/
/*| parm 1: firstChar - LPAR identifier, 'V' by default                   |*/
/*| retVal: the two character label prefix                                 |*/
/*+-----+*/
    arg firstChar type
    select
    when (type = PERM) then

```



```

    labelPrefix = firstChar||'M' /* for VM Minidisk */
when (type = PAGE) then
    labelPrefix = firstChar||'P' /* for VM Page */
when (type = SPOL) then
    labelPrefix = firstChar||'S' /* for VM Spool */
otherwise
    do
        say 'Error: "AS" must be present and type must be PERM, PAGE or SPOL'
        call help
    end /* otherwise */
end /* select */
return labelPrefix /* from getLabelPrefix */

/*+-----+*/
parseDasd: procedure expose dasdList.
/*| parse all dasd into an array verifying all are attached          |*/
/*| parm 1: dasds - the list of dasd passed in                      |*/
/*| retVal: number of DASD in dasdList                             |*/
/*+-----+*/
arg dasds
numDasd = 0
say ''
say 'Format the following DASD:'
do while (dasds <> '')
    parse upper var dasds dasd dasds
    dashPos = pos('-', dasd)
    if (dashPos = 0) then /* there is just one DASD */
        do
            numDasd = numDasd + 1
            dasdList.numDasd = dasd
            'CP Q MDISK' dasdList.numDasd 'LOCATION'
            if (rc <> 0) then
                do
                    say 'Return code from Q MDISK =' rc
                    say 'Are all DASD ATTached?'
                    exit 3
                end
            end
            call checkReserved(dasdList.numDasd)
        end /* do */
    else /* process the range of DASD */
        do
            startRange = substr(dasd, 1, dashPos - 1)
            endRange = substr(dasd, dashPos + 1, length(dasd) - dashPos)
            do i = x2d(startRange) to x2d(endRange)
                numDasd = numDasd + 1
                dasdList.numDasd = d2x(i)
                'CP Q MDISK' dasdList.numDasd 'LOCATION'
                if (rc <> 0) then
                    do
                        say 'Return code from Q MDISK =' rc
                        exit 3
                    end
                end
                call checkReserved(dasdList.numDasd)
            end /* do i */
        end /* else */
    end /* do while */
return numDasd /* from parseDasd */

/*+-----+*/
doFormat: procedure expose dasdList.

```

```

/*| Format all DASD specified using CPFMTXA                                */
/*| parm 1: labelPrefix - the two character label prefix                  */
/*| parm 2: numDasd - number of DASD in the array dasdList                */
/*| parm 3: type - the type of DASD format                                */
/*| retVal: 0 = success                                                    */
/*+-----+*/
arg labelPrefix numDasd type
'CP TERM MORE 1 1'
do i = 1 to numDasd
    label = getLabel(labelPrefix dasdList.i)
    call formatOne(dasdList.i type label)
end /* do i = */
'CP TERM MORE 50 10'
return 0 /* from doFormat */

/*+-----+*/
checkReserved: procedure
/*| Try copying an already formatted DASD then relabelling it            */
/*| parm 1: source                                                         */
/*| parm 2: target                                                         */
/*| parm 3: label                                                         */
/*+-----+*/
arg dasd
/* create a list of reserved dasd - this is somewhat hokey to be sure
   but it's better to be hokey than to format system minidisks! */
resvd1 = "0122 0123 0124 0125 0190 0191 0193 0194 019D 019E 0201 02A2"
resvd2 = "02A4 02A6 02C2 02C4 02CC 02D2 0319 03A2 03A4 03A6 03B2 03C2"
resvd3 = "03C4 03D2 0400 0401 0402 0405 0490 0493 049B 049E 04A2 04A4"
resvd4 = "04A6 04B2 04C2 04C4 04D2 0500 051D 05A2 05A4 05A6 05B2 05C2"
resvd5 = "05C4 05D2 05E5 05E6 06A2 06A4 06A6 06B2 06C2 06C4 06D2 07A2"
resvd6 = "07A4 07A6 07B2 07C2 07C4 07D2 0CF1 0CF2 0CF3"
reserved = resvd1 resvd2 resvd3 resvd4 resvd5 resvd6
if (index(reserved, dasd) <> 0) then /* MAINT minidisk - ABORT! */
do
    say 'Minidisk' dasd 'is a reserved MAINT minidisk'
    say 'This must be formatted manually using a different vaddr'
    exit 4
end /* if dasd is reserved */
return /* from checkReserved */

/*+-----+*/
doReport: procedure expose dasds
/*| Report on the newly labelled DASD                                    */
/*| retVal: 0 = success                                                  */
/*+-----+*/
'DETACH' dasds
'ATTACH' dasds '*'
say ''
say 'DASD status after:'
'CP Q MDISK' dasds 'LOCATION'
return 0 /* from doReport */

/*+-----+*/
formatOne: procedure
/*| Format a DASD via DDR                                                */
/*| parm 1: disk - the vaddr to be formatted                          */
/*| parm 2: type - PAGE, SPOL or PERM                                  */
/*| parm 3: label - the six character label                            */
/*+-----+*/

```

```

arg disk type label
queue 'FORMAT'
queue disk
queue '0 END'
queue label
queue 'YES'
queue type '0 END'
queue 'END'
'CPFMTXA'
return /* from formatOne */

/*+-----+*/
getLabel: procedure
/*| Compose the six character label of a minidisk |*/
/*| parm 1: labelPrefix - first two characters of label |*/
/*| parm 2: disk - vaddr of length 1, 2, 3 or 4 |*/
/*| return: the 6 character label |*/
/*+-----+*/
arg labelPrefix disk
diskLen = length(disk)
select
when (diskLen = 1) then /* insert 3 zeros */
label = labelPrefix||'000'||disk
when (diskLen = 2) then /* insert 2 zeros */
label = labelPrefix||'00'||disk
when (diskLen = 3) then /* insert a zero */
label = labelPrefix||'0'||disk
otherwise /* it must be length 4 or query would have failed */
label = labelPrefix||disk
end /* select */
return label /* from getLabel */

```

B.1.2 The CHPW52 XEDIT macro

Following is the code for the XEDIT macro that changes all passwords in the z/VM 5.2 USER DIRECT file:

```

/* CHPW52 XEDIT - change all passwords in z/VM 5.2 USER DIRECT file */

/*-----*/
THE PROGRAM IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTIES OR
CONDITIONS OF ANY KIND, EITHER EXPRESS OR IMPLIED INCLUDING, WITHOUT
LIMITATION, ANY WARRANTIES OR CONDITIONS OF TITLE, NON-INFRINGEMENT,
MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.
NEITHER RECIPIENT NOR ANY CONTRIBUTORS SHALL HAVE ANY LIABILITY FOR
ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING WITHOUT LIMITATION LOST PROFITS), HOWEVER CAUSED
AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY,
OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF
THE USE OR DISTRIBUTION OF THE PROGRAM OR THE EXERCISE OF ANY RIGHTS
GRANTED HEREUNDER, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES
-----*/

parse arg fn ft fm '(' options ')' newPass .
if (length(newPass) > 8) then
do
say "Error: new password must be 8 characters or fewer"
exit
end
say ''
say 'Changing all passwords to:' newPass

```

say ''

```
/* set some values */
'command set stay on'
'command set num on'
'command set nulls on'
'command set serial off'
'command set cmdline bottom'
'command set curline on 3'
'command set serial off'
'command set scale off'
'command set case m i'
'command set pre off'
'command set v 1 80'

/* change user ID passwords */
'command c/CMS1 CMS1/CMS1' newPass'/*'
'command c/LGLOPR LGLOPR/LGLOPR' newPass'/*'
'command c/MAINT MAINT/MAINT' newPass'/*'
'command c/CMSBATCH CMSBATCH/CMSBATCH' newPass'/*'
'command c/AVSVM AVSVM/AVSVM' newPass'/*'
'command c/TSAFVM TSAFVM/TSAFVM' newPass'/*'
'command c/VMSERVS VMSEVS/VMSEVS' newPass'/*'
'command c/VMSEVR VMSEVR/VMSEVR' newPass'/*'
'command c/GCS GCS/GCS' newPass'/*'
'command c/GCSXA GCSXA/GCSXA' newPass'/*'
'command c/SYSMAINT SYSMAINT/SYSMAINT' newPass'/*'
'command c/OPERATOR OPERATOR/OPERATOR' newPass'/*'
'command c/OP1 OP1/OP1' newPass'/*'
'command c/EREPR EREPR/EREPR' newPass'/*'
'command c/OPERATNS OPERATNS/OPERATNS' newPass'/*'
'command c/AUTOLOG1 AUTOLOG1/AUTOLOG1' newPass'/*'
'command c/DISKACNT DISKACNT/DISKACNT' newPass'/*'
'command c/OPERSYMP OPERSYMP/OPERSYMP' newPass'/*'
'command c/VMUTIL VMUTIL/VMUTIL' newPass'/*'
'command c/SYSDUMP1 SYSDUMP1/SYSDUMP1' newPass'/*'
'command c/5684042J 5684042J/5684042J' newPass'/*'
'command c/40SASF40 40SASF40/40SASF40' newPass'/*'
'command c/OSASF OSASF/OSASF' newPass'/*'
'command c/OSAMAIN OSAMAIN/OSAMAIN' newPass'/*'
'command c/OSADMIN1 OSADMIN1/OSADMIN1' newPass'/*'
'command c/OSADMIN2 OSADMIN2/OSADMIN2' newPass'/*'
'command c/OSADMIN3 OSADMIN3/OSADMIN3' newPass'/*'
'command c/P684096K P684096K/P684096K' newPass'/*'
'command c/RSCS RSCS/RSCS' newPass'/*'
'command c/XCHANGE XCHANGE/XCHANGE' newPass'/*'
'command c/RSCSDNS RSCSDNS/RSCSDNS' newPass'/*'
'command c/TCPMAINT TCPMAINT/TCPMAINT' newPass'/*'
'command c/5VMTCP20 5VMTCP20/5VMTCP20' newPass'/*'
'command c/TCPIP TCPIP/TCPIP' newPass'/*'
'command c/IMAP IMAP/IMAP' newPass'/*'
'command c/FTPSERVE FTPSERVE/FTPSERVE' newPass'/*'
'command c/SMTP SMTP/SMTP' newPass'/*'
'command c/NAMESRV NAMESRV/NAMESRV' newPass'/*'
'command c/REXEC REXEC/REXEC' newPass'/*'
'command c/RXAGENT1 RXAGENT1/RXAGENT1' newPass'/*'
'command c/X25IPI X25IPI/X25IPI' newPass'/*'
'command c/PORTMAP PORTMAP/PORTMAP' newPass'/*'
'command c/NDBPMGR NDBPMGR/NDBPMGR' newPass'/*'
```

```

'command c/NDBSRV01 NDBSRV01/NDBSRV01' newPass'/*'
'command c/SNMPQE SNMPQE/SNMPQE' newPass'/*'
'command c/SNMPD SNMPD/SNMPD' newPass'/*'
'command c/ROUTED ROUTED/ROUTED' newPass'/*'
'command c/LPSEVE LPSEVE/LPSEVE' newPass'/*'
'command c/SNALNKA SNALNKA/SNALNKA' newPass'/*'
'command c/VMNFS VMNFS/VMNFS' newPass'/*'
'command c/VMKERB VMKERB/VMKERB' newPass'/*'
'command c/ADMSERV ADMSERV/ADMSERV' newPass'/*'
'command c/UFTD UFTD/UFTD' newPass'/*'
'command c/BOOTPD BOOTPD/BOOTPD' newPass'/*'
'command c/TFTPD TFTPD/TFTPD' newPass'/*'
'command c/DHCPD DHCPD/DHCPD' newPass'/*'
'command c/MPROUTE MPROUTE/MPROUTE' newPass'/*'
'command c/SSLSEVE SSLSEVE/SSLSEVE' newPass'/*'
'command c/MONWRITE MONWRITE/MONWRITE' newPass'/*'
'command c/5VMDIR10 5VMDIR10/5VMDIR10' newPass'/*'
'command c/BLDNUC BLDNUC/BLDNUC' newPass'/*'
'command c/BLDCMS BLDCMS/BLDCMS' newPass'/*'
'command c/AUDITOR AUDITOR/AUDITOR' newPass'/*'
'command c/SYSMON SYSMON/SYSMON' newPass'/*'
'command c/VMRMSVM VMRMSVM/VMRMSVM' newPass'/*'
'command c/VMRMADMN VMRMADMN/VMRMADMN' newPass'/*'
'command c/5767002P 5767002P/5767002P' newPass'/*'
'command c/RACFVM RACFVM/RACFVM' newPass'/*'
'command c/RACFSMF RACFSMF/RACFSMF' newPass'/*'
'command c/RACMAINT RACMAINT/RACMAINT' newPass'/*'
'command c/AUTOLOG2 AUTOLOG2/AUTOLOG2' newPass'/*'
'command c/IBMUSER IBMUSER/IBMUSER' newPass'/*'
'command c/SYSADMIN SYSADMIN/SYSADMIN' newPass'/*'
'command c/BLDRACF BLDRACF/BLDRACF' newPass'/*'
'command c/5VMPTK20 5VMPTK20/5VMPTK20' newPass'/*'
'command c/PERFSVM PERFSVM/PERFSVM' newPass'/*'
'command c/5VMHCD20 5VMHCD20/4VMHCD40' newPass'/*'
'command c/CBDIODSP CBDIODSP/CBDIODSP' newPass'/*'
'command c/VSMSEVE VSMSEVE/VSMSEVE' newPass'/*'
'command c/IMAPAUTH IMAPAUTH/IMAPAUTH' newPass'/*'
'command c/DTCVSW1 DTCVSW1/DTCVSW1 ' newPass'/*'
'command c/DTCVSW2 DTCVSW2/DTCVSW2 ' newPass'/*'
'command c/MIGMAINT MIGMAINT/MIGMAINT' newPass'/*'
'command c/LNXMAINT LNXMAINT/LNXMAINT' newPass'/*'
'command c/BLDSEG BLDSEG/BLDSEG' newPass'/*'

/* change mindisk passwords */
'command c/ALL WRITE MULTIPLE/ALL' newPass newPass'/*'
'command c/ALL WTCPMAN MTCPMAN/ALL' newPass newPass'/*'
'command c/RADMSERV WADMSERV MADMSERV/' newPass newPass newPass'/*'
'command c/RAUDITOR WAUDITOR MAUDITOR/' newPass newPass newPass'/*'
'command c/RAUTOLOG WAUTOLOG MAUTOLOG/' newPass newPass newPass'/*'
'command c/RAVSOBJ WAVSOBJ MAVSOBJ/' newPass newPass newPass'/*'
'command c/RBATCH WBATCH MBATCH/' newPass newPass newPass'/*'
'command c/RBOOTPD WBOOTPD MBOOTPD/' newPass newPass newPass'/*'
'command c/RCATALOG WCATALOG/' newPass newPass'/*'
'command c/RCONTROL WCONTROL/' newPass newPass'/*'
'command c/RCRRLOG1 WCCRLOG1/' newPass newPass'/*'
'command c/RDATA WDATA/' newPass newPass'/*'
'command c/RDHCPD WDHCPD MDHCPD/' newPass newPass newPass'/*'
'command c/RDVF WDVF MDVF/' newPass newPass newPass'/*'
'command c/READ WRITE MULTIPLE/' newPass newPass newPass'/*'
'command c/READ WRITE/' newPass newPass'/*'

```

```
'command c/RFTPSERV WFTPSERV MFTPSERV/'newPass newPass newPass'/*'
'command c/RGCS      WGCS      MGCS/'newPass newPass newPass'/*'
'command c/RIMAP     WIMAP     MIMAP/'newPass newPass newPass'/*'
'command c/RLOG1     WLOG1/'newPass newPass newPass'/*'
'command c/RLOG2     WLOG2/'newPass newPass newPass'/*'
'command c/RLPSERVE  WLPSEVER  MLPSEVER/'newPass newPass newPass'/*'
'command c/RMAINT    WMAINT    MMAINT/'newPass newPass newPass'/*'
'command c/RMPROUTE  WMPROUTE  MMPROUTE/'newPass newPass newPass'/*'
'command c/RNAMESRV  WNAMESEV  MNAMESEV/'newPass newPass newPass'/*'
'command c/RNDBPMGR  WNDSEVER  MNDSEVER/'newPass newPass newPass'/*'
'command c/RNDBSRVO  WNDSEVER  MNDSEVER/'newPass newPass newPass'/*'
'command c/RPORTMAP  WPORTMAP  MPORTMAP/'newPass newPass newPass'/*'
'command c/RREXEC    WREXEC    MREXEC/'newPass newPass newPass'/*'
'command c/RROUTED   WROUTED   MROUTED/'newPass newPass newPass'/*'
'command c/RSERVER   WSERVER/'newPass newPass'/*'
'command c/RSMTMP    WSMTP     MSMTMP/'newPass newPass newPass'/*'
'command c/RSNALNKA  WSNALNKA  MSNALNKA/'newPass newPass newPass'/*'
'command c/RSNMPD    WSNMPD    MSNMPD/'newPass newPass newPass'/*'
'command c/RSNMPQE   WSNMPQE   MSNMPQE/'newPass newPass newPass'/*'
'command c/RSSLSEV   WSSLSEV   MSSLSEV/'newPass newPass newPass'/*'
'command c/RSYSMON   WSYSMON   MSYSMON/'newPass newPass newPass'/*'
'command c/RTCTPIP   WTCPIP    MTCPIP/'newPass newPass newPass'/*'
'command c/RTCPMAIN  WTCPMAN   MTCPMAN/'newPass newPass newPass'/*'
'command c/RTFTPD    WFTPD     MTFTPD/'newPass newPass newPass'/*'
'command c/RTSAF0BJ  WTSAF0BJ  MTSAF0BJ/'newPass newPass newPass'/*'
'command c/RUFTD     WUFTD     MUFTD/'newPass newPass newPass'/*'
'command c/RVMKERB   WVMKERB   MVMKERB/'newPass newPass newPass'/*'
'command c/RVMNFS    WVMNFS    MVMNFS/'newPass newPass newPass'/*'
'command c/RX25IPI   WX25IPI   MX25IPI/'newPass newPass newPass'/*'
'command c/R4TCPIP   W4TCPIP   M4TCPIP/'newPass newPass newPass'/*'
'command c/RDTCVSW1  WDTCVSW1  MDTCVSW1/'newPass newPass newPass'/*'
'command c/RDTCVSW2  WDTCVSW2  MDTCVSW2/'newPass newPass newPass'/*'
'command c/RCRRLOG2  WCRRLOG2/'newPass newPass'/*'
'command c/MR READ/'MR newPass'/*'
```

B.1.3 The LABEL520 EXEC

Following is the code for the EXEC that changes the system labels of a z/VM 5.2 system:

```
/*+-----+*/
/*| EXEC: LABEL520  wrapper around CPFMTXA to LABEL and ALLOC DASD |*/
/*|   retVal: 0 - success                                           |*/
/*|           1 - help was asked for or given                       |*/
/*|           2 - user is not sure                                  |*/
/*|           3 - DASD (minidisk) range is not valid                |*/
/*|           4 - at least one DASD (minidisk) is reserved to MAINT |*/
/*+-----+*/

/*-----*/
THE PROGRAM IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTIES OR
CONDITIONS OF ANY KIND, EITHER EXPRESS OR IMPLIED INCLUDING, WITHOUT
LIMITATION, ANY WARRANTIES OR CONDITIONS OF TITLE, NON-INFRINGEMENT,
MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.
NEITHER RECIPIENT NOR ANY CONTRIBUTORS SHALL HAVE ANY LIABILITY FOR
ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING WITHOUT LIMITATION LOST PROFITS), HOWEVER CAUSED
AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY,
OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF
THE USE OR DISTRIBUTION OF THE PROGRAM OR THE EXERCISE OF ANY RIGHTS
GRANTED HEREUNDER, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES
```

```

-----*/

parse upper arg res spl pag w01 w02 .
if (w02 = '') then call help

/* Construct the two character label prefix */
firstChar = 'M' /* change this for an LPAR ID other than 'M' */
labelPrefix = firstChar'V'

/* Construct the 5 labels */
resLabel = getLabel(labelPrefix res)
splLabel = getLabel(labelPrefix spl)
pagLabel = getLabel(labelPrefix pag)
w01Label = getLabel(labelPrefix w01)
w02Label = getLabel(labelPrefix w02)

/* Ask "Are you sure?" */
say 'The volumes are:'
'CP Q' res spl pag w01 w02
say ''
say 'The system volume labels will become:'
say resLabel splLabel pagLabel w01Label w02Label
say ''
say 'ARE YOU SURE you want to relabel the DASD (y/n)?'
parse upper pull answer
ansFirstChar = substr(answer, 1, 1)
if (ansFirstChar ^= 'Y') then exit 2

/* Label the 4 volumes: RES is 123, W01 is 124, W02 is 125, SPL is 122 */
'CP TERM MORE 1 1'
'CPFMTXA 123' resLabel 'LABEL'
'CPFMTXA 124' w01Label 'LABEL'
'CPFMTXA 125' w02Label 'LABEL'
'CPFMTXA 122' splLabel 'LABEL'

/* LINK the 520PAG volume which is $PAGE$ A03, label it, DETACH it */
'CP LINK $PAGE$ A03 A03 MR'
'CPFMTXA A03' pagLabel 'LABEL'
'CP DET A03'
'CP TERM MORE 50 10'
exit

/*+-----+*/
help: procedure
/*+-----+*/
  parse source . . fn .
  say ""
  say "Synopsis:"
  say ""
  say "Relabel the five system volumes (520RES, 520W01, ...) to VV<xxxx>"
  say "  where <xxxx> is the 4 digit address"
  say ""
  say "Syntax is:"
  say ""
  say "  >>---LABEL520--res--spl--pag--w01--w02----->>"
  say ""
  say "  where res, spl, pag, w01 and w02 are 4 digit virtual addresses"
  say "  of the volumes that z/VM 5.2 is installed onto"
  say ""
exit 1

```

```

/*+-----+*/
getLabel: procedure
/*| Compose the six character label of a minidisk |*/
/*| parm 1: labelPrefix - first two characters of label |*/
/*| parm 2: disk - vaddr of length 1, 2, 3 or 4 |*/
/*| return: the 6 character label |*/
/*+-----+*/
arg labelPrefix disk
if (DATATYPE(disk, 'X') = 0) then
do
say "Error:" disk "is not a hexadecimal number"
call help
end
diskLen = length(disk)
select
when (diskLen = 1) then /* insert 3 zeros */
label = labelPrefix||'000'||disk
when (diskLen = 2) then /* insert 2 zeros */
label = labelPrefix||'00'||disk
when (diskLen = 3) then /* insert a zero */
label = labelPrefix||'0'||disk
otherwise /* it must be length 4 or query would have failed */
label = labelPrefix||disk
end /* select */
return label /* from getLabel */

```

B.1.4 The LABEL520 XEDIT macro

Following is the code for the XEDIT macro that changes all passwords in the z/VM 5.2 USER DIRECT file:

```

/* LABEL520 - change '520xxx' labels in SYSTEM CONFIG or USER DIRECT */
/*-----*/
THE PROGRAM IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTIES OR
CONDITIONS OF ANY KIND, EITHER EXPRESS OR IMPLIED INCLUDING, WITHOUT
LIMITATION, ANY WARRANTIES OR CONDITIONS OF TITLE, NON-INFRINGEMENT,
MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.
NEITHER RECIPIENT NOR ANY CONTRIBUTORS SHALL HAVE ANY LIABILITY FOR
ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL
DAMAGES (INCLUDING WITHOUT LIMITATION LOST PROFITS), HOWEVER CAUSED
AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY,
OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF
THE USE OR DISTRIBUTION OF THE PROGRAM OR THE EXERCISE OF ANY RIGHTS
GRANTED HEREUNDER, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES
-----*/

firstChar = 'M' /* change this for an LPAR ID other than 'M' */
parse upper arg res spl pag w01 w02 .

parse upper arg fn ft fm '(' options ')' res spl pag w01 w02 .
if (w02 = '') then
do
say "5 arguments required - exiting"
exit
end
'command set stay on'
'command set num on'
'command set nulls on'
'command set serial off'

```



```
'command set cmdline bottom'
'command set curline on 3'
'command set serial off'
'command set scale off'
'command set case m i'
'command set pre off'
'command set v 1 80'
'command top'
'command c/520RES/'firstChar'V'res'/*'
'command c/520W01/'firstChar'V'w01'/*'
'command c/520W02/'firstChar'V'w02'/*'
'command c/520SPL/'firstChar'V'spl'/*'
'command c/520PAG/'firstChar'V'pag'/*'
```

B.2 Linux source code

This section lists source code that is common regardless of Linux distribution

B.2.1 Bash scripts on the controller

Following is the source code for the bash scripts that run on the controller

B.2.1.1 The nightly.sh script

Following is the content of the bash script /etc/cron.daily/nightly.sh. It runs scripts to backup important z/VM and Linux data.

```
#!/bin/bash
# -----
# For details on this code see the books "z/VM and Linux on IBM System z:
# The Virtualization Cookbook for <x>" on the Web at: http://linuxvm.org/present
# where <x> is "SLES 10" or "RHEL 5"
#
# This code is shipped under the Common Public License. See the file
# Common-Public-License.txt or http://www.opensource.org/licenses/cpl1.0.txt
# -----
#
# nightly.sh - do the following on the controller each night
#   run backupVM.sh to backup VM files
#   run backupLinux.sh to backup /etc/ directories on Linux
# -----
/sbin/backupVM.sh
/sbin/backupLinux.sh
```

B.2.1.2 The backupVM.sh script

Following is the content of the bash script /etc/cron.daily/nightly.sh. It does THIS

```
#!/bin/bash
# -----
# For details on this code see the books "z/VM and Linux on IBM System z:
# The Virtualization Cookbook for <x>" on the Web at: http://linuxvm.org/present
# where <x> is "SLES 10" or "RHEL 5"
#
# This code is shipped under the Common Public License. See the file
# Common-Public-License.txt or http://www.opensource.org/licenses/cpl1.0.txt
# -----
#
# backupVM.sh - do a backup of z/VM files by linking to important disks:
```

```

# MAINT 191 - USER DISKMAP
# MAINT 2CC - USER DIRECT
# MAINT CF1 - SYSTEM CONFIG
# TCPMAINT 198 - <systemID> TCP/IP, SYSTEM DTCPARMS
# TCPMAINT 592 - TCP/IP DATA
# AUTOLOG1 191 - PROFILE EXEC
# LNXMAINT 192 - * PARMFILE, * PARM-S10, SLES* *
# The system that this is run on should have the LNKNOPAS directory option so
# all the above minidisks can be linked via vmcp with no password necessary
#
#+-----+
function cpCmd()
# echo a CP command and invoke it via the vmcp module/command
# Arg 1-n: the command to issue
# Return: the command's return code
#+-----+
{
# parse output to get return code: awk -F# splits line at '#' with rc at end
output=`vmcp $@ 2>&1`
ret_val=0
ret_val=`echo $output | grep "Error: non-zero CP response" | awk -F# '{print $2}'`
return $ret_val
}

#+-----+
function linkAccess()
# link and access a minidisk
# Arg 1: the source disk user ID
# Arg 2: the source disk virtual device number
# Arg 3: placeholder for code readability
# Arg 4: the virtual device number to link the minidisk as
#+-----+
{
userID=$1
vaddr=$2
linkVaddr=$4
cpCmd QUERY VIRTUAL $linkVaddr
queryRC=$?
if [ $queryRC = 40 ]; then # linkVaddr is free
cpCmd LINK $userID $vaddr $linkVaddr RR
rc=$?
if [ $rc != 0 ]; then # can't link - punt
echo "Error: unable to link $userID $vaddr read-only"
echo "LINK $userID $vaddr $linkVaddr RR returned $rc"
exit
fi
else # linkVaddr is not free
echo "Error: Virtual address $linkVaddr is not free?"
echo "QUERY VIRTUAL $linkVaddr returned $queryRC"
fi
# activate new disk then sleep 1 second for CP to catch up
chccwdev -e $linkVaddr > /dev/null 2>&1
sleep 1
}

#+-----+
function getFile()
# get a file on a CMS disk
# Arg 1: the file or file pattern to get
# Arg 2: placeholder for code readability

```

```

# Arg 3: the virtual device number to detach
#+-----+
{
  file=$1
  vaddr=$3
  CMSdevice=`cat /proc/dasd/devices | grep $vaddr | awk '{print $7}'`
  cmsfscat -a -d /dev/$CMSdevice $file > $file
  rc=$?
  if [ $rc != 0 ]; then
    echo "Error: cmsfscat returned $rc backing up $file"
  else
    echo "Backing up $file seems to have succeeded"
  fi
}

#+-----+
function getFiles()
# get all files on a CMS disk
# Arg 1: the virtual device number to copy files from
#+-----+
{
  vaddr=$1
  CMSdevice=`cat /proc/dasd/devices | grep $vaddr | awk '{print $7}'`
  let i=0
  cmsfslst -d /dev/$CMSdevice | while read oneline
  do # first record is headers, second is "DIRECTOR", third is "ALLOCMAP"
    if ((i > 2)); then # we are into the CMS files
      fn=`echo $oneline | awk '{print $1}'`
      ft=`echo $oneline | awk '{print $2}'`
      cmsfscat -a -d /dev/$CMSdevice $fn.$ft > $fn.$ft
      rc=$?
      if [ $rc != 0 ]; then # error
        echo "Error: cmsfscat returned $rc backing up $fn.$ft"
      else
        echo "Backing up $fn.$ft seems to have succeeded"
      fi
    fi
    let i=i+1
  done
}

#+-----+
function relDetach()
# link and access a minidisk
# Arg 1: the virtual device number to detach
# Return: the command's return code
#+-----+
{
  chccwdev -d $1 > /dev/null 2>&1
  cpCmd DET $1
}

# main()
cd /backup/vm

# run the getVMinfo script to save some basic VM information
getVMinfo > zVMinfo.txt

# get USER DISKMAP from MAINT 191
linkAccess MAINT 191 as 1191

```

```

getFile USER.DISKMAP from 1191
relDetach 1191

# get USER DIRECT from MAINT 2CC
linkAccess MAINT 2CC as 12cc
getFile USER.DIRECT from 12cc
relDetach 12cc

# get SYSTEM CONFIG from MAINT CF1
linkAccess MAINT CF1 as 1cf1
getFile SYSTEM.CONFIG from 1cf1
relDetach 1cf1

# get TCPIP files from TCPMAINT 198
systemID=`vmcp q userid | awk '{print $3}'`
linkAccess TCPMAINT 198 as 1198
getFile $systemID.TCPIP from 1198
getFile SYSTEM.DTCPARMS from 1198
relDetach 1198

# get TCPIP DATA from TCPMAINT 592
linkAccess TCPMAINT 592 as 1592
getFile TCPIP.DATA from 1592
relDetach 1592

# get PROFILE EXEC from AUTOLOG1 191 - rename to different FT
linkAccess AUTOLOG1 191 as 2191
CMSdevice=`cat /proc/dasd/devices | grep 2191 | awk '{print $7}'`
cmsfscat -a -d /dev/$CMSdevice PROFILE.EXEC > PROFILE.EXECAUT1
relDetach 2191

# Get all files from LNXMAINT 192 which is our 191 disk
getFiles 191

```

B.2.1.3 The backupLinux.sh script

Following is the content of the bash script `/sbin/backupLinux.sh`. It loops through the directories under `/backup/linux/` and updates each `/etc/` directory via **rsync**:

```

#!/bin/bash
#
# -----
# For details on this code see the books "z/VM and Linux on IBM System z:
# The Virtualization Cookbook for <x>" on the Web at: http://linuxvm.org/present
# where <x> is "SLES 10" or "RHEL 5"
#
# This code is shipped under the Common Public License. See the file
# Common-Public-License.txt or http://www.opensource.org/licenses/cpl1.0.txt
# -----
#
BACKUP="/backup/linux"
cd $BACKUP
for i in *-on-*          # iterate through dirs with "-on-" in their names
do
    IP_addr=${i#Linux*-on-} # this chops the head off and grabs the IP address
    cd $BACKUP/$i          # change directory to next virtual server
    rsync -r --timeout=3 $IP_addr:/etc . > /dev/null 2>&1 # use rsync to backup
    rc=$?
    if [ $rc != 0 ]; then # error
        echo "Error: rsync returned $rc while backing up $i"
    fi
done

```

```
    else
        echo "Backing up $i seems to have succeeded"
    fi
done
```


Source code specific to Linux

C.1 Obtaining and using the Web material

The PDF of this book is on the Internet at:

<http://linuxvm.org/present/misc/virt-cookbook-RH5.pdf>

The files associated with this book are in a gzipped tar file at:

<http://linuxvm.org/present/misc/virt-cookbook-RH5.tgz>

Download the tar file to your NFS server and use it as is described in section 6.1. After untarring the file, you will have a directory named `virt-cookbook-RH5/` for RHEL 5, or `virt-cookbook-S10/` for SLES 10.

This section lists the source code specific to RHEL 5 which is only the `clone.sh` script.

C.2 The clone.sh script

This section lists the `clone.sh` script:

```
#!/bin/bash
#
# clone.sh <LinuxUserID> - clone a Linux server running under z/VM
#
# For details on how this script works see the book:
#   "z/VM and Linux on IBM System z: The Virtualization Cookbook"
#   on the Web at: http://linuxvm.org/present/misc/virt-cookbook-1.pdf
#
# -----
# THE PROGRAM IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS
# OF ANY KIND, EITHER EXPRESS OR IMPLIED INCLUDING, WITHOUT LIMITATION, ANY
# WARRANTIES OR CONDITIONS OF TITLE, NON-INFRINGEMENT, MERCHANTABILITY
# OR FITNESS FOR A PARTICULAR PURPOSE.
# NEITHER RECIPIENT NOR ANY CONTRIBUTORS SHALL HAVE ANY LIABILITY FOR ANY
# DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES
# (INCLUDING WITHOUT LIMITATION LOST PROFITS), HOWEVER CAUSED AND ON ANY THEORY
# OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
```

```

# NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OR
# DISTRIBUTION OF THE PROGRAM OR THE EXERCISE OF ANY RIGHTS GRANTED
# HEREUNDER, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES
# -----

#+-----+
function help()
# give help
#+-----+
{
    echo "Usage: clone [options] target_linux_ID"
    echo ""
    echo "  Clone Linux system from minidisk $sdisk to target_linux_ID"
    echo "  options:"
    echo "    -v or --verbose: verbose"
    exit 1
}

#+-----+
function process_arguments()
# give help
#+-----+
{
    verbose="off"
    if [ $# = 0 ]; then # user did not pass an argument
        echo "error: at least one argument is needed"
        echo ""
        help
    fi
    for arg in $*
    do
        case $arg in
            -v|--verbose)
                verbose="on"
                ;;
            *)
                clone_id=`echo $arg | tr '[a-z]' '[A-Z]'` # fold target user ID to upper
        case
                ;;
            esac
        done
        if [ $clone_id = "none" ]; then # new linux user ID was not passed
            echo "Error: new Linux user ID must be an argument"
            echo ""
            help
        fi
    }

#+-----+
function cp_cmd()
# echo a CP command and invoke it via the vmcp module/command
#   Arg1-n: the command to issue
#   Return: the command's return code
#+-----+
{
    echo "Invoking CP command: $@"
    # parse output to get return code: awk -F# splits line at '#' with rc at end
    output=`vmcp $@ 2>&1`
    echo "$output"
    ret_val=0
}

```



```

ret_val=`echo $output | grep "Error: non-zero CP response" | awk -F# '{print $2}'`
return $ret_val
}

#+-----+
function check_target_id()
# Verify user ID exists and is logged off
#+-----+
{
cp_cmd QUERY $clone_id
case $? in
0) # user ID is logged on or disconnected
echo "$clone_id user ID must be logged off"
exit 2
;;
3) # user ID does not exist
echo "$clone_id user ID does not exist"
exit 3
;;
45) # user ID is logged off - this is correct
;;
*) # unexpected
echo "$clone_id user ID must exist and be logged off"
exit 4
esac
}

#+-----+
function prepare_ipaddr()
# Prepare an IP address by adding a backslash before any "."s
# to make it 4 digits
# Arg 1: The IP address to be modified
# Return:
# The new value is written to the global variable new_ipaddr
#+-----+
{
new_ipaddr=`echo $1 | sed -e 's:\.:\\\.:g'`
}

#+-----+
function prepare_vaddr()
# Prepare a z/VM virtual address by folding to lower case and prepending leading zeros
# to make it 4 digits
# Arg 1: The vaddr to be modified
# Return:
# The new value is written to the global variable new_vaddr
#+-----+
{
new_vaddr=`echo $1 | tr '[A-Z]' '[a-z]'` # fold to lower case
let leadingZeros=4-`${#1}` # determine number of zeros to add
let i=0
while [ $i -lt $leadingZeros ]; do
new_vaddr="0$new_vaddr"
i=$((i+1))
done
}

#+-----+
function copy_disk()
# Try to use z/VM FLASHCOPY to copy one disk to another.

```

```

# Arg 1: Source minidisk vaddr
# Arg 2: the word "to"
# Arg 3: Target user ID
# Arg 4: Target virtual address
# Return code
# 0: success with FLASHCOPY
# 1: success with dasdfmt and dd
# 2: Target vaddr already in use?
# 3: CP LINK failed
# 4: unable to enable target minidisk
# 5: can't find source disk in /dev/dasd/devices
# 6: can't find target disk in /dev/dasd/devices
# 7: dasdfmt failed
# 8: dd failed
#+-----+
{
    ret_val=0
    source_mdisk=$1
    target_userid=$3
    target_vaddr=$4
    cp_cmd QUERY VIRTUAL $target_vaddr
    rc=$?
    if [ $rc != 40 ]; then
        echo "Error: CP QUERY VIRTUAL $target_vaddr failed with $rc"
        echo "The target device address is already in use"
        return 2
    fi
    cp_cmd LINK $target_userid $source_mdisk $target_vaddr MR
    rc=$?
    if [ $rc != 0 ]; then # LINK failed
        echo "Error: CP LINK $target_userid $source_mdisk $target_vaddr failed with $rc"
        return 3
    fi
    cp_cmd FLASHCOPY $source_mdisk 0 END $target_vaddr 0 END
    rc=$?
    if [ $rc != 0 ]; then # FLASHCOPY failed
        echo "FLASHCOPY $source_mdisk $target_vaddr failed with $rc"
        echo "Falling back to dasdfmt and dd copy"
# enable target disk
        sleep 1
        chccwdev -e $target_vaddr
        rc=$?
        if [ $rc != 0 ]; then # unable to enable target disk
            echo "Error: unable to enable $target_disk, rc from chccwdev = $rc"
            cp_cmd DETACH $target_vaddr
            return 4
        fi
# get device name of source disk
        source_dev=`cat /proc/dasd/devices | grep "$source_mdisk(ECKD)" | awk '{ print $7
    }'`
        if [ "$source_dev" = "" ]; then
            cat /proc/dasd/devices
            echo "Error: can't find $source_mdisk(ECKD) in /proc/dasd/devices"
            chccwdev -d $target_vaddr # clean up
            cp_cmd DETACH $target_vaddr
            return 5
        fi
# get device name of target disk
        target_dev=`cat /proc/dasd/devices | grep "$target_vaddr(ECKD)" | awk '{ print $7
    }'`

```

```

        if [ "$target_dev" = "" ]; then
            cat /proc/dasd/devices
            echo "Error: can't find $target_vaddr(ECKD) in /proc/dasd/devices"
            chccwdev -d $target_vaddr # clean up
            cp_cmd DETACH $target_vaddr
            return 6
        fi
# dasdfmt target disk
echo "Invoking command: dasdfmt -b 4096 -y -f /dev/$target_dev"
dasdfmt -b 4096 -y -f /dev/$target_dev
rc=$?
if [ $rc != 0 ]; then # dasdfmt failed
    echo "Error: dasdfmt -b 4096 -y -f /dev/$target_dev failed with $rc"
    chccwdev -d $target_vaddr # clean up
    cp_cmd DETACH $target_vaddr
    return 7
fi
# copy from source disk to target via dd
echo "Invoking command: dd bs=4096 if=/dev/$source_dev of=/dev/$target_dev"
dd bs=4096 if=/dev/$source_dev of=/dev/$target_dev
rc=$?
if [ $rc != 0 ]; then # dd failed
    echo "Error: dd bs=4096 if=/dev/$source_dev of=/dev/$target_dev failed with $rc"
    chccwdev -d $target_vaddr # clean up
    cp_cmd DETACH $target_vaddr
    return 8
fi
chccwdev -d $target_vaddr
echo "Copying disk via dasdfmt/dd succeeded ..."
ret_val=1 # success with dasdfmt and dd
fi # if FLASHCOPY failed
sync # sync disks
cp_cmd DETACH $target_vaddr
echo "Copying disk via FLASHCOPY succeeded ..."
return $ret_val
} # copy_disk()

#+-----+
function get_confinfo()
# Bring 191 minidisk online to be read by cmsfs and check for two CONF-RH5 files
#+-----+
{
    # recycle 191 to pick up latest changes
    chccwdev -d 191
    chccwdev -e 191
# sleep 1 # timing problem?
rc=$?
if [ $rc != 0 ]; then # unable to enable 191 disk
    echo "unable to enable 191, rc from chccwdev = $rc"
    exit 5
fi
CMSdisk=`lsdasd | grep 0191 | awk '{ print $7 }'`
cmsfsfst -d /dev/$CMSdisk | grep -i $clone_id | grep CONF-RH5
rc=$?
if [ $rc != 0 ]; then
    echo "Error: $clone_id CONF-RH5 not found on 191 minidisk. Exiting"
    exit 6
fi
# get informaton about target

```

```

export local $(cmsfscat -a -d /dev/$CMSdisk $clone_id.CONF-RH5)
target_hostname=$HOSTNAME
target_domain=${HOSTNAME#*.}
target_host=${HOSTNAME%}.${target_domain}
target_IP=$IPADDR
target_DNS=$DNS
target_GW=$GATEWAY
target_netmask=$NETMASK
target_network=$NETWORK
target_broadcast=$BROADCAST
prepare_vaddr $SUBCHANNELS
target_subchannels=$new_vaddr

# get information about source
source_guestID=`cat /proc/sysinfo | grep "VM00 Name" | awk '{ print $3 }'`
export local $(cmsfscat -a -d /dev/$CMSdisk $source_guestID.CONF-RH5)
source_hostname=$HOSTNAME
source_domain=${HOSTNAME#*.}
source_host=${HOSTNAME%}.${source_domain}
prepare_ipaddr $IPADDR
source_IP=$new_ipaddr
prepare_ipaddr $DNS
source_DNS=$new_ipaddr
prepare_ipaddr $GATEWAY
source_GW=$new_ipaddr
prepare_ipaddr $NETMASK
source_netmask=$new_ipaddr
prepare_ipaddr $NETWORK
source_network=$new_ipaddr
prepare_ipaddr $BROADCAST
source_broadcast=$new_ipaddr
prepare_vaddr $SUBCHANNELS
source_subchannels=$new_vaddr
}

#+-----+
function ask_are_you_sure()
# Ask "Are you sure?" - if not, then exit
#+-----+
{
    echo ""
    echo "WARNING!!: this will copy disk $sdisk to $clone_id 100"
    echo "New host name will be: $target_hostname"
    echo "New TCP/IP address will be: $target_IP"
    echo "Other network data is retrieved from $clone_id CONF-RH5 on 191 disk"
    echo -n "Are you sure you want to overwrite these disks (y/n): "
    read ans
    if [ $ans != "y" ]; then
        exit 7
    fi
    echo "Please enter a brief description of this server"
    read descr
}

#+-----+
function copy_system()
# copy master image on $sdisk (default 100) to target user ID
#+-----+
{
    echo "Copying $sdisk root file system to $clone_id ..."

```

```

copy_disk $sdisk to $clone_id 1100 # copy source to target root file system
rc=$?
if [ $rc -gt 1 ]; then # both FLASHCOPY and dasdfmt/dd failed
    echo "Copying disk failed with $rc"
    exit 9
fi
}

#+-----+
function modify_cloned_image()
# Mount newly copied system over /mnt/rhel5cloned and modify networking info
# Arg 1: target userid
# Arg 2: target minidisk
# Arg 3: target virtual device address
# Return code
# 0: success
#+-----+
{
    target_userid=$1
    target_mdisk=$2
    target_vaddr=$3
    echo "Mounting newly cloned image over $cloned_mnt_pt ..."
    cp_cmd LINK $target_userid $target_mdisk $target_vaddr MR
    rc=$?
    sleep 1
    if [ $rc != 0 ]; then # LINK failed
        echo "Fatal error: CP LINK $target_userid $target_mdisk $target_vaddr MR failed with
$rc"
        cp_cmd DET $target_vaddr
        exit 10
    fi
    if [ ! -d $cloned_mnt_pt ]; then
        mkdir $cloned_mnt_pt
        rc=$?
        if [ $rc != 0 ]; then
            echo "Fatal Error: mkdir $cloned_mnt_pt failed with $rc"
            cp_cmd DET $target_vaddr
            exit 10
        fi
    fi
    chccwdev -e $target_vaddr
    sleep 2
    rc=$?
    if [ $rc != 0 ]; then
        echo "Fatal error: chccwdev -e $target_vaddr failed with $rc"
        cp_cmd DET $target_vaddr
        exit 10
    fi
    cloned_DASD=`cat /proc/dasd/devices | grep "$target_vaddr(ECKD)" | awk '{ print $7 }'`
    if [ "$cloned_DASD" = "" ]; then
        cat /proc/dasd/devices
        echo "Fatal error: can't find $target_vaddr(ECKD) in /proc/dasd/devices"
        chccwdev -d $target_vaddr
        exit 10
    fi
    cloned_fs="/dev/${cloned_DASD}1"
    echo "Mounting $cloned_fs over $cloned_mnt_pt ..."
    mount $cloned_fs $cloned_mnt_pt
    rc=$?
    if [ $rc != 0 ]; then

```

```

        echo "Fatal error: mount $cloned_fs $cloned_mnt_pt failed with $rc"
        lsdasd
        cp_cmd DET $target_vaddr
        exit 10
    fi
    echo "Modifying cloned image under $cloned_mnt_pt ..."
    sed --in-place -e "s/$source_IP/$target_IP/g" \
        -e "s/$source_hostname/$target_hostname/g" \
        -e "s/$source_host/$target_host/g" $cloned_mnt_pt/etc/hosts
    sed --in-place -e "s/$source_hostname/$target_hostname/g" \
        -e "s/$source_GW/$target_GW/g" $cloned_mnt_pt/etc/sysconfig/network
    sed --in-place -e "s/$source_IP/$target_IP/g" \
        -e "s/$source_netmask/$target_netmask/g" \
        -e "s/$source_broadcast/$target_broadcast/g" \
        -e "s/$source_network/$target_network/g" \
        -e "s/$source_subchannels/$target_subchannels/g" \
        $cloned_mnt_pt/etc/sysconfig/network-scripts/ifcfg-eth0
    sed --in-place -e "s/$source_domain/$target_domain/g" \
        -e "s/$source_DNS/$target_DNS/g" $cloned_mnt_pt/etc/resolv.conf

# Regenerate SSH keys
echo "Regenerating SSH keys in $cloned_mnt_pt/etc/ssh/ ..."
rm $cloned_mnt_pt/etc/ssh/ssh_host*
ssh-keygen -t rsa -N "" -q -f $cloned_mnt_pt/etc/ssh/ssh_host_rsa_key
ssh-keygen -t dsa -N "" -q -f $cloned_mnt_pt/etc/ssh/ssh_host_dsa_key
ssh-keygen -t rsa1 -N "" -q -f $cloned_mnt_pt/etc/ssh/ssh_host_key

# Remove any old entry, then copy clone's public key to known_hosts file
echo "Adding $target_IP to known_hosts file"
cd /root/.ssh
if [ -f known_hosts ]; then
    grep -v $target_IP known_hosts > known_hosts.temp
    mv known_hosts.temp known_hosts
fi

# construct known_hosts entry with three fields: IP@ "ssh-rsa" clones_public_key
new_key=`cat $cloned_mnt_pt/etc/ssh/ssh_host_rsa_key.pub | awk '{ print $2 }'`
echo "$target_IP ssh-rsa $new_key" >> known_hosts

# clean up
sync # sync disks
umount $cloned_mnt_pt
chccwdev -d $target_vaddr
cp_cmd DETACH $target_vaddr
return 0
}

#+-----+
function make_backup_dir()
# Create a directory /backup/<VM-ID>-on-<IP.addr> if it doesn't exist
# e.g. LINUX04 with IP@ 129.40.178.44 would create /backup/LINUX04-on-129.40.178.44/
#+-----+
{
    if [ -d $backup_dir ]; then # main backup directory exists
        echo "Creating a directory under $backup_dir"
        cd $backup_dir
        backup_subdir=$clone_id-on-$target_IP
        if [ ! -d $backup_subdir ]; then # backup subdirectory does not exist
            mkdir $backup_subdir
            if [ ! $? = 0 ]; then # there was an error from mkdir command

```

```

        echo "Error creating directory $backup_dir/$backup_subdir/"
    else
        echo "Created directory $backup_dir/$backup_subdir/"
        echo $descr > $backup_subdir/descLog.txt
    fi
else # directory exists - create descLog.txt file
    echo $descr > $backup_subdir/descLog.txt
fi
fi
}

# main() # some important global variables
sdisk=0100                                # source disk
clone_id="none"                            # target user ID
was="no"
db2="no"
mq5="no"
umask 002                                # new dir/files set group write bit
cloned_mnt_pt="/mnt/rhel5cloned"           # directory of temporary mount point
backup_dir="/backup/linux"                # directory of Linux backups

process_arguments $@                      # process arguments passed by user
if [ $verbose = "on" ]; then set -vx; fi  # turn debug on
check_target_id                          # verify user ID to clone to
get_conffile_info                        # info about source and target
ask_are_you_sure                         # confirm disk overwrite
copy_system                             # copy disk $sdisk to target ID
modify_cloned_image $clone_id $sdisk 1100 # modify newly copied system
cp_cmd XAUTOLOG $clone_id               # bring new clone to life
make_backup_dir                          # make a backup directory
if [ $verbose = "on" ]; then set +vx; fi  # turn debug off
echo "Successfully cloned minidisk $sdisk to $clone_id"
echo "You should be able to ping $target_IP within one minute"
exit 0

```


Index

Symbols

\$ALLOC\$, z/VM user ID 54, 91, 133, 144
.htpasswd file 128
/backup/ directory 140
/etc/auto.master 107
/etc/cron.daily/ directory 112
/etc/fstab 106, 186
/etc/inittab file 113
/etc/modprob.conf 113
/etc/ntp.conf file 112
/etc/rsyncd.conf 111
/etc/samba/smb.conf file 175
/etc/samba/smbpasswd file 175
/etc/sudoers file 129
/etc/sysconfig/network-scripts/ifcfg-eth0 105, 120
/etc/trusted.hosts 111
/etc/yum.repos.d/ directory 107
/nfs/rhel5/ directory 125
/nfs/virt-cookbook-RH5/ directory 125
/proc/dasd/devices 106
/proc/sys/appldata/ directory 210
/rhel5master/ directory 117
/usr/share/doc/ directory 175

Numerics

3270 emulators 27, 41
520RES 36

A

Aduva's Onstage 4
Albert Einstein 4, 223
Alt-Tab sequence 30
Apache 161
 Enabling for SSL 164
 SSL module 164
Apache resources 165
appldata_mem module 210
appldata_net_sum module 210
appldata_os module 210
application development resources 178
application development server 177
APPLMON option 209
ARP=no 105, 120
ATTACH command 34
Attachmate Extra! 27
AUTOLOG1, z/VM user ID 230
automount 107

B

backup_vm script 224
Bill of materials 9

C

CHANGEPW XEDIT 60
CHANGEPW XEDIT macro 60
chapters
 in the book 7
chkconfig command 86, 109
choices made
 in the book 4
CHPW52 XEDIT 60
 source code 237
clone.sh script 140, 173, 178, 227
 description 140
 source code 249
Cloning
 block diagram 142
cloning 133
command
 TERM MORE 153
Common UNIX Printing System (CUPS) 173
Computer Associates
 VM Direct 4
 VM Monitor 197
 VM Secure 59
Computer Associates'
 Brightstor Enterprise Backup 227
Control Program 4
Controller 7, 89, 142
 Configuration 121
 Copying files to 122
 Disk partitioning 117
 Installing 116
 NTP server configuration 125
 Verify your changes 131
conventions
 command retrieval 12
 in the book 10
 naming backup files 11
 volume labeling 11
CP 4
cp -a command 122
CPACCESS command 43
CPFMTXA command 47
CPFORMAT EXEC 48, 143
 using it 48
CPSYNTAX 52
CPSYNTAX command 43
CUPS 177

D

DASD
 3390 5
 ECKD 5
 labelling convention 11
dasd= parameter

- in zipl.conf 113
- dasdfmt command
 - using in a for loop 182
- Data About z/VM and Linux (DAZL) 211
 - configuring Apache for 127
- DAZL
 - overall design 211
- dd command 140
- DEFINE STORAGE command 96, 152
- desktop 21
- df command 114
- DIRECTXA command 55, 60, 92, 145
- DirMaint 4
- Disaster recovery 223
- Disconnect Timeout 42
- Disconnect_Timeout 43
- DISKMAP command 53, 92
- distributions
 - 31-bit and 64-bit ix

E

- envelope files 72
- ext3 file system
 - creating 186

F

- FCONX LINUXUSR file 210
- fdasd command 115, 183
- Features statement 42
- FILELIST command 93
- Firewall
 - configuring 163
- FLASHCOPY command 91, 140–141
- FORMAT command 55
- formatting DASD fast 48
- FTP
 - site fix 80 subcommand 93
- FTP server 45

G

- getVMinfo script 224

H

- hardware resources 9
- HELP command 200
- HMC 29
 - CD-ROM/DVD 31
 - Load icon 35
 - Operating System Messages 46
 - Single Object Operations 30
 - SYSG 36
 - System Console (SYSC) 46
- htpasswd command 128
- httpd.conf 128
- Hummingbird Host Explorer 27
- hypervisor 4

I

- IBM Personal Communications 27
- IBM RACF 59
- IBM Tivoli Provisioning Manager 4
- IBM z/VM Performance Toolkit 197
 - monitor subcommand 207
- IBM's Tivoli Storage Manager (TSM) 227
- Incremental back up 223
- INDICATE command 198
- INDICATE LOAD command 198
- INDICATE QUEUES EXP command 199
- infrastructure
 - block diagram 6
 - design 5
- initial RAMdisk 93
- Innovation Data Processing's FDR/UPSTREAM 227
- Installatin
 - networking problem 105
- INSTPLAN 33
- INSTVM EXEC 38
- Integrated 3270 Console 30, 32
- IPL CMS 37, 96, 152
- IPWIZARD command 38

K

- kernel 93
- kickstart 149
 - clearpart option 151
 - Configuration file 150
 - Configuring controller 149
 - Using 152
 - zerombr option 151

L

- LABEL520 EXEC
 - source code 240
- LAMP 178
- LDAP
 - Configuring client 171
- LDAP service
 - Migrating users to 168
 - starting 168
- ldapadd command 173
- ldapdelete command 170
- ldapsearch command 168, 170
- Levanta 4
- Lightweight Directory Access Protocol (LDAP) 165
- Linux
 - Configuration file 94
 - Disaster recovery 223
 - Incremental back up 223
 - installing with kickstart 149
 - manual installation 5
 - monitoring 197, 209
 - monitoring from the kernel 209
- Linux distribution 165, 177
- Linux RMF PM Data Gatherer (rmfpms) 208
- LINUX01 133, 161
- LNXDFLT profile 90

- LNXMaint 53
 - copying files to 56
- LNXMaint 192 90, 224
- Load icon 35
- logical partition ix, 3
- logical volume 91
 - adding 181
- LPAR
 - requirements 9
- lsmod command 210
- lvcreate command 185
- lvdisplay command 185
- LVM
 - block diagram 184
 - physical extents 185

M

- MAINT 2CC 230
- MAINT CF1 230
- Map Network Drive 176
- Master image 89
 - Add additional RPMs 108
 - Configuration 105
 - Installation 95
 - Turn off unneeded services 109, 124
 - Verifying changes 114
- master image 7, 142
 - installation 95
- MDISK statement 53
- Minidisk cache (MDC) 198
- Minidisk passwords 59
- mke2fs command 186
- mkinitrd command 113
- modprobe command 210
- monitor stream support 209
- monitoring Linux 208–209
- mount command 121
- MySQL 178

N

- Network File System (NFS) 83
- Network Time Protocol daemon (NTPD) 112
- networking resources 10
- NFS
 - installation method 98
- NFS server
 - configuration on Linux PC 86
- nightly.sh 112
- ntpd command 112
- ntpd daemon 112
- ntpdate command 125
- ntpq command 126
- ntpttrace command 126

O

- OpenLDAP 165
 - configuring 167
- openmotif 108

- OPTION APPLMON 133, 144
- overlaps
 - searching for 54

P

- PADL Software Pty Ltd 168
- paging space 47
- paging volumes 47
 - location 49
- parameter file 93–94, 135
 - copying 145
 - copying for new user ID 135
- PARMFILE 94
- passwd command 175
- passwords
 - planning 13
- Performance Toolkit 201
- PERFSVM user ID 203
- philosophy of the book 4
- PHP 178
- physical extents 185
- planning 9
- Printing
 - configuration 177
- PROFILE EXEC
 - AUTOLOG1's 57, 92, 134, 230
 - common to Linux user IDs 95
 - LNXMaint's 56
 - PERFSVM's 207
- PROFILE LNXDFLT 90
- PROFILE TCPIP 45
- Programming 69
- PTF 70
- PUT2PROD command 38
- PuTTY 21
 - customizing 21
 - larger screen 24
 - potential security breach warning 121
- pvccreate command 184
- pvdisplay command 184
- Python 178

Q

- QUERY ALLOC MAP command 200
- QUERY CPLEVEL command 200
- QUERY DASD command 201
- QUERY NAMES command 59, 200
- QUERY OSA command 147, 201
- QUERY PROCESSORS command 200
- QUERY STORAGE command 200
- QUERY VIRTUAL ALL command 201
- QUERY VIRTUAL command 96
- QUERY VIRTUAL OSA command 96
- QUERY VIRTUAL STORAGE command 96
- QUERY VSWITCH ACCESSLIST command 147
- QUERY XSTOR command 200
- Quick3270 27

R

- RAMdisk 93
- Reader, z/VM's 93
- RealVNC 99
- reboot command 114, 131
- Recommended 69
- Red Hat Enterprise Linux (RHEL) 93–94
- Red Hat Network 155
 - Registering your system 155
 - Without Internet access 158
- RELEASE command 43
- RHEL 5
 - Installation 97
 - warning messages 97
- RHEL 5 configuration file 135
- RHEL 5 installation
 - bug workaround 113
- RHEL 5 user ID
 - parameter file 135
- RHEL5 EXEC 97
- RHEL5 user ID 90
 - bootstrap files 93
 - configuration file 94
 - creating 90
 - parameter file 93
 - second half of an install 105
- rhel5.initrd 93
- rhel5.kernel 93
- rmfpms 208
- rmfpms command 208
- rsyncd 111

S

- Samba 173–174
 - configuration 175
 - integrating with LDAP 176
- saved segments
 - rebuilding 67
- SCSI/FCP disks 5
- SecureAgent Software's SecureBackup 227
- service
 - autofs 107
 - httpd 130, 162
 - iptables 163
 - ldap 169
 - smb 176
 - vncserver 110
- services
 - turning off unneeded 109
- SET SIGNAL command 57
- SET SRM command 57
- SET VSWITCH command 92, 134
- SET VSWITCH GRANT command 93, 135, 147
- share /usr/ file system 5
- Shared File System (SFS) 44
- SHUTDOWN command 46
- SHUTDOWN REIPL command 52, 59
- SIGNAL SHUTDOWN
 - setting Linux to halt 113

- Single Object Operations 30
- sitar 108
- site fix 80, FTP subcommand 93
- slapadd command 169
- slappasswd command 167
- SLES9 89
- smbclient command 176
- smbpasswd command 175–176
- smbpasswd file 176
- software resources 10
- SSH
 - Configuring keys 126
 - key-based authentication 126
 - protocol 2 22
- ssh-keygen command 126
- SSL
 - with Apache 164
- Standalone Program Loader 36
- Storage Area Network (SAN) 5
- sudo command 129
- SuSE Linux Enterprise Server ix
- SWAPGEN EXEC 95
- swapon command 106
- SYSG 36
- system administration
 - roles 13
- SYSTEM CONFIG 43, 63, 230
 - customizing 42
- SYSTEM CONFIG file
 - adding PAGE and PERM disks 51
 - Features statement 42
- System Console (SYSC) 46
- SYSTEM DTCPARMS 230
- system shutdown 57
- system startup 57
- System status
 - DASD view 148
 - reviewing 148
- System z
 - virtualization capabilities 4
- System_Identifier_Default 42

T

- tar command 208
- TCP/IP
 - z/VM configuration 38
- TCP/IP resources 10
- TCPCMSU 53
- TCPIP Data 230
- TCPMAINT 198 230
- TCPMAINT 592 90, 230
- TERM MORE command 97
- TYPE command 94

U

- UM97510 75
- UM97520 75
- Universal Naming Convention (UNC) 176
- usability tests

- on the book 6
- USER DIRECT 230
- USER DIRECT file 53, 90, 144
 - APPLMON option 209
 - INCLUDE statement 90
 - profile 90
- user diskmap 92
- USER DISKMAP file 53
- User_Volume_Include 51, 144
- User_Volume_List 51
- useradd command 175
- userid() function 94

V

- VDISK 42
- Vdisk
 - allowing creation of 43
- VDISK swap 100, 106
- Velocity Software's ESALPS 197
- Veritas' Backup Exec 227
- vgcreate command 185
- virtual disk (VDISK) 42
- virtual NIC 90
- Virtual server
 - application development 177
 - File and print 173
 - LDAP 165
 - Web server 161
- Virtual servers
 - defining user IDs for 142
- virtual servers 4
- virtual switch (VSWITCH) 3, 42
- vmcp command 131
- vmcp module 127
- VMLINK command 50
- VNC 97
- VNC client 99
- VNC server
 - configuring 110
- volume group 185
- VSWITCH 3, 44, 47, 146

W

- which command 140
- worksheets
 - examples in the book 14

X

- XAUTOLOG command 44, 57, 92, 140
- XEDIT
 - "" prefix command 90, 144
 - ? subcommand 12
 - add subcommand 43
 - BOTTOM subcommand 43
 - CHANGE subcommand 61
 - FILE subcommand 43
 - PREFIX OFF subcommand 53
 - search subcommand (/) 42

- XEDIT command 41
- XEDIT PROFILE 41
- xinetd 108
- xstartup 110

Y

- yum
 - RPM GPG key 107
- yum command 107, 166
- yum -y command 174

Z

- z/VM
 - adding paging volumes 47
 - backing up to tape 61
 - cons=sysg 36
 - conventions 10
 - CPFMTXA command 47
 - customizing shutdown 57
 - customizing startup 57
 - DIRECTXA command 55
 - Disaster recovery 223
 - Disconnect Timeout 42
 - DISKMAP command 53
 - envelope files 72
 - FORMAT command 55
 - FTP server 45
 - HELP command 200
 - HIT RATIO 198
 - Incremental back up 223
 - INDICATE command 198
 - INDICATE QUEUES EXP command 199
 - INSTPLAN EXEC 33
 - INSTVM EXEC 38
 - Integrated 3270 Console 30
 - IPWIZARD command 38
 - latest PTFs 75
 - MIGRATE rate 198
 - monitoring 197
 - paging efficiency 49
 - PAGING rate 198
 - PUT2PROD command 38
 - QUERY ALLOC MAP command 200
 - QUERY CPLEVEL command 200
 - QUERY DASD command 201
 - QUERY NAMES command 200
 - QUERY OSA command 201
 - QUERY PROCESSORS command 200
 - QUERY STORAGE command 200
 - QUERY VIRTUAL ALL command 201
 - QUERY XSTOR command 200
 - reader 93
 - relabeling system volumes 61
 - RELEASE command 43
 - Restoring from tape 67
 - security issues 59
 - Servicing 69
 - SET SIGNAL command 57
 - SET VSWITCH command 134

- shuting down 46
- Standalone Program Loader 36
- STEAL value 199
- strengths 3
- system name 42
- TCP/IP configuration 38
- TCPIP at IPL time 43
- TERM MORE command 97
- TYPE command 94
- userid() function 94
- virtual switch 3
- VSWITCH 3
- XEDIT PROFILE 41
- XSTORE rate 198
- z/VM CPACCESS command 43
- z/VM QUERY NAMES command 59
- z/VM system
 - backup Copy 61
- z/VM user IDs
 - default password 38
- zipl command 113