



**Program Directory for  
z/VM  
System Delivery Offering**

Version 7

Program Number 5741-A10

for Use with  
z/VM SDO Version 6.2 and higher  
(with updates for 7.1.0)

Document Date: September 2018

G113-4375-00

---

**Note**

Before using this information and the product it supports, be sure to read the general information under the “Notices” Section.

This program directory, dated September 2018, applies to System Delivery Offering Version 7 (z/VM SDO) Program Number 5741-A10.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

◦ **Copyright International Business Machines Corporation 2011, 2018 All rights reserved.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

---

## Summary of Changes

SDO Licensed Program Product changes (service, upgrade, additions or deletions) are identified in the following change history.

### z/VM SDO

Product Number	Product Abbreviation	VRM	Change
Feature of 5654-A22	XL C/C++ 130 for zVM	V1R3.0	Documentation
5654-010	ACF/VTAM ESA	V4R2.0	Documentation
Feature of 5654-010	APPC APPL SUITE	V1R1.0	Documentation
5654-029	DITTO	V1R3.0	Documentation
5654-260	EREP	V3R5.0	Serviced
5684-042	ICKDSF	V1R17.0	Serviced
5684-043	ISPF	V3R2.0	Documentation
5684-123	ISPF/PDF	V3R2.0	Documentation
Feature of 5684-123	ISPF/PDF NLS	V3R2.0	Documentation
5695-013	REXX/370 Compiler	V1R4.0	Documentation
Feature of 5695-013	REXX/370 Compiler Kanji	V1R4.0	Documentation
5695-014	REXX/370 Library	V1R4.0	Documentation
Feature of 5695-014	REXX/370 Library Kanji	V1R4.0	Documentation
5696-234	HLASM	V1R6.0	Serviced
Feature of 5696-234	HLASM Toolkit	V1R6.0	Serviced
5697-F42	DB2 Server for VM	V7R5.0	Serviced
Feature of 5697-F42	DB2 Client for VM	V7R5.0	Serviced
5697-J05	Archive Manager for z/VM	V1	Updated
5697-J06	Backup and Restore Manager for z/VM	V1	Updated
5697-J08	Tape Manager for z/VM	V1	Documentation
5697-J10	Operations Manager for z/VM	V1	Updated
5698-A36	IBM Tivoli Omegamon XE on z/VM	V4R3.0	Updated
Feature of 5741-A07	DFSMS/VM	V2R2.1	Serviced
Updated for 6.4 release			
Updated for 7.1 release			



---

## Preface

This document is intended for the system programmer responsible for installation of IBM Licensed Program Products (Licensed Products). This document contains the following sections:

- 1.0, “Introduction”

This contains a brief description of the System Delivery Offering (SDO), what is included in the package and an explanation of the different install formats for the Licensed Products.

- 2.0, “z/VM SDO Installation Instructions”

This section explains how to get started with your SDO order. It explains verifying your order, publications to have available, and provides a checklist for the initial installation steps. It describes how to install the z/VM System, the RSU (Recommended Service Update) and SDO Enabling Feature.

- 3.0, “VMSES/E Licensed Product Installation Instructions”

This section contains general installation instructions for the VMSES/E Licensed Products.

- 4.0, “Semi-VMSES/E Licensed Product Installation Instructions”

This section identifies the considerations for the installation of Semi-VMSES/E Licensed Products

- 5.0, “VMSES/E Licensed Product Technical Notes”

This section provides technical installation and verification instructions for each VMSES/E Licensed Product.

- 6.0, “Semi-VMSES/E Licensed Product Technical Notes”

This section provides technical installation and verification instructions for each Semi-VMSES/E Licensed Product.

- Appendix A, “z/VM SDO IBM Licensed Program Products”

This appendix lists the z/VM SDO Licensed Products by product abbreviation and provides the product description and install format.

- Appendix B, “IBM Licensed Program Products Interdependencies”

This appendix lists the Prerequisites, Co-requisites and If-requisites of the Licensed Products in z/VM SDO.

- Appendix C, “DASD Requirements”

This appendix provides recommended sizes of the minidisks associated with each of the Licensed Products in z/VM SDO.

- Appendix D, “Saved Segments”

This appendix provides recommended sizes, locations and names of the saved segments associated with each of the Licensed Products in z/VM SDO.

- Appendix E, “Licensed Products Tapemaps”

This appendix provides tapemaps of stacked VMSES/E and Semi-VMSES/E tapes

## Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors.

Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you. Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

Site Counsel  
IBM Corporation  
2455 South Road  
Poughkeepsie, NY 12601-5400  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurement may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information may contain examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.



## COPYRIGHT LICENSE:

This information may contain sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

## Trademarks

IBM, the IBM logo, and [ibm.com](http://ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at IBM copyright and trademark information - United States ([www.ibm.com/legal/us/en/copytrade.shtml](http://www.ibm.com/legal/us/en/copytrade.shtml)).

The following terms are trademarks of other companies:

Adobe, the Adobe logo, PostScript and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries or both.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

SUSE, the Novell logo, and the N logo are registered trademarks of Novell, Inc. in the United States and other countries.

Red Hat, and the Shadowman logo are trademarks or registered trademarks of Red Hat, Inc. in the U.S. and other countries.

Other company, product, and service names may be trademarks or service marks of others.

---

## Table of Content

Summary of Changes .....	2
Preface .....	3
Notices .....	5
Trademarks .....	8
1.0 Introduction .....	13
1.1 z/VM System Delivery Offering .....	13
1.1.1 The z/VM System .....	13
1.1.2 Enabling Aid .....	15
1.1.3 z/VM SDO IBM Licensed Program Products .....	15
1.1.4 z/VM SDO Web Site .....	16
1.1.5 Basic Publications .....	17
1.1.6 Publications for Licensed Products .....	17
1.1.7 Optional Documentation .....	17
2.1 Checklist of z/VM SDO Installation Steps .....	18
2.2 Before You Begin .....	19
2.2.1 Verify Your Order .....	19
2.3 Program Support .....	20
2.3.1 Preventive Service Planning .....	20
2.3.2 Statement of Support Procedures .....	21
2.4 Installation of the z/VM System and Stacked RSU .....	21
2.4.1 z/VM Content .....	21
2.4.3 DASD Storage Requirements .....	26
2.4.4 Install the z/VM System .....	26
2.5 Plan for Licensed Product Interdependencies .....	27
2.6 Determine the Install Format of the Licensed Products .....	27
3.0 VMSES/E Licensed Product Installation Instructions .....	29
3.1 Checklist of the VMSES/E Licensed Products Installation Process .....	29
3.2 Allocate DASD and Userids .....	29
3.3 Prepare the VMSES/E Order for Installation .....	30
3.3.2 Prepare the Product Envelope Delivered from Internet .....	30
3.4 Install the z/VM SDO VMSES/E Licensed Product .....	30

<b>4.0</b>	<b>Semi-VMSES/E Licensed Product Installation Instructions</b>	31
4.1	Checklist for the Semi-VMSES/E Licensed Products Installation Process	31
4.2	Semi-VMSES/E Licensed Product Definition	32
4.3	Semi-VMSES/E Installation Overview and Planning	33
4.3.1	Plan for the Installation of the Semi-VMSES/E Licensed Product	33
4.3.2	Prepare the Semi-VMSES/E Order for Installation	33
4.3.3	Load Installation-Related Files from Tape	34
4.3.4	Allocate Resources for the Semi-VMSES/E Licensed Product	36
4.4	Install the Semi-VMSES/E Licensed Product	40
4.4.1	Install Using the VMFINS EXEC	40
4.4.2	Place IBM Licensed Program Product Into Production	43
<b>5.0</b>	<b>VMSES/E Licensed Product Technical Notes</b>	46
5.1	VMSES/E Licensed Product Specific Considerations	46
5.1.1	5654-A22 XL C/C++ 130 FOR Z/VM V1R3.0	46
5.1.2	5654-A23 IBM DEBUG TOOL FOR Z/VM V4R1.0	49
5.1.3	5654-010 ACF/VTAM ESA V4R2.0	51
5.1.4	5654-010 APPC APPL SUITE V1R1.0	55
5.1.5	5654-029 DITTO V1R3.0	58
5.1.6	5655-T13 IBM TIVOLI ZSECURE MANAGER FOR RACF V1R11.0	61
5.1.7	5668-723 GDDM-IVU V1R1.3	65
5.1.8	5668-801 GDDM-IMD V2R1.3	68
5.1.9	5668-812 GDDM-PGF V2R1.3	70
5.1.10	5684-042 ICKDSF V1R17.0	73
5.1.11	5684-168 GDDM/VM V3R2.0	75
5.1.12	5695-013 REXX/370 COMPILER V1R4.0	79
5.1.14	5695-014 REXX/370 LIBRARY V1R4.0	83
5.1.15	5695-014 REXX/370 LIBRARY KANJI V1R4.0	86
5.1.16	5696-234 HLASM V1R6.0	89
5.1.17	5696-234 HLASM TOOLKIT V1R6.0	93
5.1.18	5697-F42 DB2 SERVER FOR VM V7R5.0	96
5.1.19	5697-F42 DB2 DATA PROPAGATOR V7R4.0	99
5.1.20	5697-F42 DB2 QMF V7R2.0	102
5.1.21	5697-F42 DB2 CLIENT FOR VM V7R5.05	106
5.1.22	5697-J05 ARCHIVE MANAGER FOR Z/VM	109
5.1.23	5697-J06 BACKUP AND RESTORE MANAGER FOR Z/	109
5.1.24	5697-J08 TAPE MANAGER FOR Z/VM	109

5.1.25 5697-J10 OPERATIONS MANAGER FOR Z/VM.....	109
5.1.26 5698-A36 IBM TIVOLI OMEGAMON XE ON Z/VM V4R2.0 .....	109
5.1.27 5741-A07 DFSMS/VM V2R2.1 .....	112
5.1.28 5741-A07 DFSMS/VM KANJI V2R2.1 .....	115
6.0 Semi-VMSES/E Licensed Product Technical Notes.....	118
6.1 Semi-VMSES/E Licensed Product Specific Considerations .....	118
6.1.1 5654-260 EREP V3R5.0 .....	119
6.1.2 5684-043 ISPF V3R2.0.....	123
6.1.3 5684-123 ISPF/PDF V3R2.0 .....	129
6.1.4 5684-123 ISPF/PDF NLS V3R2.0 .....	138
6.1.5 5697-F42 DB2 RXSQL V7R1.0 .....	144
6.1.6 5697-F42 DB2 DATA RESTORE V7R3.0.....	149
6.1.7 5697-F42 DB2 CONTROL CENTER V7R3.0 .....	153
6.1.8 5697-F42 DB2 NLS VM HELP FILES V7R5.0 .....	157
6.1.9 5697-F42 DB2 CLIENT NLS VM HELP FILES V7R5.0 .....	161
Appendix A. z/VM SDO IBM Licensed Program Products .....	166
A.1 z/VM SDO Licensed Products Table .....	166
Appendix B. IBM Licensed Program Products Interdependencies .....	168
B.1 Requisite IBM Licensed Program Product Dependencies .....	168
B.1.1 Pre-Requisites (Install-Time Full Requisite).....	168
B.1.2 Co-Requisite (Run-time Full Requisite) .....	168
B.1.3 If-Requisites (Install-time and Run-time Part Requisites).....	168
B.2 z/VM SDO Licensed Product Requisites Table .....	169
Appendix C. DASD Requirements .....	171
C.1 z/VM SDO Licensed Product DASD Requirements.....	171
Appendix D. Saved Segments .....	178
D.1 z/VM SDO Program Product Segment Layout.....	178
D.2 Creating Saved Segments Utilizing the SDO Enabling Aid.....	179
Appendix E. Licensed Products Tapemaps .....	181
E.1 Stacked Tape for VMSES/E and Semi-VMSES/E Licensed Products.....	181
Appendix F. z/VM 6.2 Installation and Production Enablement Requirements .....	184
F.1 SSI-Enabled (Multisystem SSI Cluster) User ID Definitions .....	184
F.2 SSI-Enabled Real Device and Minidisk Management .....	184
F.3 Installation of Licensed Program Product into SFS Directories.....	185
F.4 z/VM 6.2 System Maintenance ID and System Disk Ownership.....	186
F.5 SSI-Enabled Environment LP Production Enablement Considerations.....	187

<b>Bibliography</b> .....	189
<b>Reader's Comments</b> .....	189

---

## 1.0 Introduction

Thank you for ordering the z/VM System Delivery offering (z/VM SDO, 5741-A10) package.

The person receiving this order should make sure everything on the Packing List was received. The *Read This First* letter (GI13-4372), Packing List, and the Media Report contain important information about the SDO installation and will be required by the system programmer.

The Packing List contains information about the media and the documentation sent. The Media Report describes the contents.

If there are any discrepancies between the package contents and the Packing List or if you have not received any part of your order, please call **IBM Software Manufacturing and Delivery** at the number indicated on the cover letter of the Packing List.

---

### 1.1 z/VM System Delivery Offering

The z/VM SDO Version 6 Release 2.0, program number 5741-A08 and higher, is the IBM® program offering for z/VM® that includes a single deliverable containing z/VM and a group of serviced IBM licensed program products. This document has been updated for z/VM SDO Version 7 Release 1.0, program number 5741-A10 however no products contained in this document are serviced beyond z/VM Version 6 Release 2.0, please refer to the specific product Program Directory for installation instructions and obtaining the latest service.

The z/VM SDO Licensed Product package contains:

- The z/VM System which is the VM operating system
- z/VM SDO Licensed Products

#### 1.1.1 The z/VM System

The z/VM System provides a highly flexible test and production environment which provides the capability for the installation and execution of additional IBM Licensed Products, the development and execution of applications and the ability to run full-function operating systems as guests. The z/VM System is a prebuilt VM operating system which is available on DVD or through electronic internet delivery. The DVD and the electronic internet delivery are in binary image format. ISO files are also available with the electronic internet delivery.

Note: Electronic Internet delivery of the z/VM System and IBM Licensed Products is only available when ordered through Shopz.



---

## 1.1.2 Enabling Aid

The Enabling Aid consists of files that contain information about the SDO Licensed Products such as Saved Segments, PUT/RSU/ESO levels for the products and sample directory entries. The Enabling Aid is no longer shipped with the SDO Product Order, it is now only available as an electronic internet download from the IBM Website at:

<http://www.vm.ibm.com/sdo>

## 1.1.3 z/VM SDO IBM Licensed Program Products

The following subsections describe the characteristics of the Licensed Products that are part of z/VM SDO.

**Note:**

Not all Licensed Products listed in this document can be ordered through the z/VM SDO. Those that are not available can be ordered with its Licensed Product ID number (PID). A list of orderable products can be found in Section 2.4.1.2 Product Packaging, under the heading "Changes to the z/VM System Delivery Offering (SDO)". For Example, to order DITTO you will use PID 5654-029. Contact your IBM Sales Representative for additional information.

Installation of the z/VM SDO Licensed Products is supported on 3390 DASD.

**Licensed Products may be in one of these install formats:**

1. **VMSES/E** are those products packaged in the IBM Standard VMSES/E Enabled format. One or more Licensed Products may be delivered on a stacked media, so it is important to refer to the Media Report for a product's location.
2. **Semi-VMSES/E** are products that were not originally in VMSES/E format but that have been put through an IBM Process that installs the product per the original IBM installation procedure and repackages the installed product in a VMSES/E enabled format. This provides for the installation of the product utilizing standard VMSES/E commands. One or more Licensed Products may be delivered on a stacked media, so it is important to refer to the Media Report for the product's location.

**Note:**

A **Semi-VMSES/E** product was previously called '**Pre-Install**' format; however, this term was misleading in that it may have indicated that the product was already installed. The name has been changed to better describe the install format type.

The term 'Pre-Install' may still appear on the Packing List or the Media Report, the Configurator, or Marketing Literature, but should be interpreted to mean Semi-VMSES/E.

### **1.1.4 z/VM SDO Web Site**

There is additional information about the z/VM SDO on the web site <http://www.vm.ibm.com/sdo/>. This site is maintained with the current z/VM SDO Program Directory (in PDF format), the list of SDO products, and information on applied service. This site also provides links to other useful z/VM information.

---

## 1.1.5 Basic Publications

The following basic publications are included with your order of the z/VM base product and will be useful during installation:

*z/VM Installation Guide*

*z/VM License Information*

Memo to Users for z/VM and its features are provided with your order.

## 1.1.6 Publications for Licensed Products

Program Directories for a number of the optional IBM SDO Licensed Products that you may have ordered may be found on the IBM z/VM website at:

<http://www.vm.ibm.com/library>

If the Program Directory is not available on the above website, it may be obtained from the IBM Knowledge Center website at:

<http://www.ibm.com/support/knowledgecenter/SSB27U>

## 1.1.7 Optional Documentation

Optional unlicensed documentation is supplied as PDF format with z/VM.

z/VM, including the priced feature Program Directories can be found at:

<http://www.vm.ibm.com/progdir>

Publications available in PDF format can be found via the IBM z/VM Internet Library at:

<http://www.vm.ibm.com/library>

Publications can also be found at the IBM Knowledge Center website at:

<http://www.ibm.com/support/knowledgecenter/SSB27U>

---

## 2.0 z/.1 Checklist of z/VM SDO Installation Steps

### 2.1 Checklist of z/VM SDO Installation Steps

Notes:

- *Perform the steps in order.*
- *Mandatory steps are preceded by squares (■).*
- *Optional steps are preceded by circles (○).*

---

#### ■ 2.2, Before You Begin

- ■ Verify Order with Packing List
- ■ Gather Publications Useful During Installation

#### ■ 2.3, Program Support

- ■ Obtain latest z/VM SDO and Licensed Product Install Bucket Information
- ■ Obtain the latest PSP information

#### ■ 2.4, Installation of the z/VM System and Stacked RSU

- ■ Review the z/VM Content
- ■ DASD Storage Requirements
- ■ Install the z/VM System and the RSU, referring to the z/VM Program Directory.

—If the SDO order includes Licensed Program Products in addition to the z/VM System, continue the installation with the following instructions. If there are no additional products, the installation of the z/VM System is complete.

#### ○ 2.5, Install the SDO Optional Products Enabling Aid (Optional)

#### ■ 2.6, Plan for Licensed Product Interdependencies

#### ■ 2.7, Determine the Install Format of the Licensed Products

For each VMSES/E Licensed Product repeat the following:

#### ■ 3.0, VMSES/E Licensed Product Installation Instructions

#### ■ 5.0, VMSES/E Licensed Product Technical Notes

■ For each Semi-VMSES/E Licensed Product repeat the following:

#### ■ 4.0, Semi-VMSES/E License Product Installation Instructions

#### ■ 6.0, Semi-VMSES/E Licensed Product Technical Notes

---

## 2.2 Before You Begin

Before you begin installing the z/VM SDO, verify that all program materials ordered have been received. Additionally, there are several publications and reference material that may be useful to have available during the installation.

---

### 2.2.1 Verify Your Order

Verify the physical media with the Packing List and Media Report to ensure that all DVDs and materials have been received. The Packing List includes information about the DVDs and the documentation. If for some reason you do not have all the media and the documentation specified in the Packing List, or if they are damaged, call the number specified on the cover letter of the Packing List. It may not be possible to install the Licensed Product if you are missing any of the material.

DVDs can be sorted first by using the information on the label. You will see headings similar to the following:

- z/VM Product Package for installation on 3390
- z/VM Stacked Recommended Service Upgrade
- z/VM SDO Version 7

The System DDR and RSU may be delivered on multiple DVDs so verify you have all in the sequence.

Under the barcode at the bottom of the label, will appear the reference number of the DVD, like \*WM6578354\*. Using only the numeric digits, 6578354, use this number to match the information on the Media Description Report under the column: Ref. No.

The Media Description Report describes the contents of the software ordered and tells which products are on the DVDs.

If you ordered Optional Licensed Program Products, most will be stacked on one of the DVDs labelled 'z/VM SDO Version 7'. If you received more than one Licensed Program Product DVD, you will need to refer to the Media Description Report and reference number from the DVD to determine the contents on each.

The actual number of DVDs you receive depends on the install format of the Licensed Program Products ordered. All VMSES/E and Semi-VMSES/E Licensed Program Products may be 'stacked' on the same media(s), with the possible exception the Fonts. This Program Product may be shipped separately.

If you ordered the AFP Fonts and the Program Product is shipped on a separate DVD(s), the DVD(s) will show the Program Product name on the label.

Prior to installation, please obtain the Program Directory for each Licensed Product you ordered on the IBM z/VM website at:

<http://www.vm.ibm.com/library>

There are a few products that do not have Program Directories or may have Installation Guides instead. Some products can be installed using only the directions in the *z/VM SDO Program Directory*. However, it is also possible that while installing a Licensed Product, you will be asked to refer to the product's Program Directory.

---

## 2.3 Program Support

For z/VM and the z/VM SDO Licensed Products, refer to the individual Licensed Product Program Directories for programming service details.

### 2.3.1 Preventive Service Planning

Before installing the z/VM SDO Package (the z/VM System, and the z/VM SDO Licensed Products), you should contact the IBM Support Center or use the Preventive Service Planning (PSP) facility in IBMLink (ServiceLink) to obtain the latest PSP information. The latest PSP Install buckets contain pertinent installation information, corrections to documentation and also may recommend additional service.

#### 2.3.1.1 z/VM SDO PSP Install Bucket Information

To obtain the PSP Install Buckets specific to z/VM SDO specify the following UPGRADE and SUBSET values pertaining to the level of the z/VM SDO being installed.

*Figure 1. PSP Upgrade and Subset ID*

RETAIN

COMPID	Release	Upgrade	Subset	Description
N/A	N/A	VMSDO	SDO <sub>vrm</sub>	SDO for z/VM

### **2.3.1.2 z/VM PSP Install Bucket Information**

Refer to the *z/VM Program Directory* for PSP Install Bucket information.

### **2.3.1.3 Licensed Products PSP Install Bucket Information**

- For PSP Install Bucket information for the Licensed Products, refer to the Program Support section of the individual Licensed Product's Program Directory. The Licensed Products orderable through the z/VM SDO are not being service refreshed as of z/VM 6.2. Service and new releases of these products will be available under the individual Licensed Product Numbers. Please verify that you have the latest level of service for each product. Some may be found under the link "z/VM SDO Optional Licensed Product Service" on the IBM VM Website.

<http://www.vm.ibm.com/sdo/sdozvm6.html>

You can find PSP bucket information and other service information on the z/VM Service Website:

<http://www.vm.ibm.com/service/>

## **2.3.2 Statement of Support Procedures**

Report any difficulties you have using this program to your IBM Support Center. If an Authorized Program Analysis Report (APAR) is required, the Support Center will provide the address to which any needed documentation can be sent.

## **2.4 Installation of the z/VM System and Stacked RSU**

### **2.4.1 z/VM Content**

The z/VM System is a pre-built VM system that serves as an installation platform for other IBM Licensed Products in the z/VM SDO package. The z/VM Installation Guide should be followed to load the system from the delivery media. Once loaded the z/VM System may be tailored to your individual requirements.

The pre-built VM system contains the following:

Prerequisite IBM licensed programs:

- EREP/VM, V3.5 (5654-260)

- ICKDSF for VM, V1.17 (5684-042) (includes ICKDSF Standalone release 17)
  - EREP and ICKDSF are pre-installed on the z/VM System Deliverable.

The z/VM System contains and includes the following components and facilities:

- AVS
  - Control Program (CP)
  - Conversational Monitoring System (CMS)
  - Dump Viewing Facility (DVF)
  - Group Control System (GCS)
  - HCD and HCM for z/VM
  - Language Environment® (LE)
  - REstructured eXtended eXecutor (REXX)
  - Transmission Control Protocol/Internet Protocol (TCP/IP)
  - Transparent Services Access Facility (TSAF)
  - VM Serviceability Enhancements Staged/Extended (VMSES/E)
  - SFS and CRR file pools
  - DASD Dump Restore (DDR) program
  - Translated CP and CMS message repositories
  - English and translated z/VM HELP files (translation no longer available after z/VM 6.4)
  - 3800 printer image library object code
  - 3800 printer image library source
- 

z/VM Optional Features:

- DirMaint™
- Performance Toolkit for VM™
- RACF Security Server for z/VM
- RSCS Networking for z/VM
- IBM Wave



## Notes

1. ICKDSF and EREP are not part of the z/VM product. They are separate prerequisite IBM licensed programs that are included in the z/VM System Image for convenience. Before using ICKDSF and EREP/VM you must be already licensed for them, or you must place orders for them to establish licenses.
2. The DirMaint, Performance Toolkit, RACF®, and RSCS optional features are included in the z/VM System Image for convenience. They are installed disabled. If you decide to use any of these features, you must place orders for them so that you can enable them.
3. The DFSMS/VM optional feature is not included in the z/VM System Image. If desired, DFSMS/VM must be ordered as a no-cost optional feature of the z/VM SDO.
4. The IBM z/VM Single System Image is included in the z/VM System Image as a no charge feature with the release of z/VM Version 7 Release 1.0.
5. The IBM Wave Feature is not included in the z/VM System Image. If desired, this priced feature must be ordered through the z/VM SDO. Service for the IBM Wave product is available through Fix Central instructions are provided with the product.

### 2.4.1.1 Hardware Requirements

The z/VM system operates on the IBM hardware as specified in the release announcement letter. To find a specific announcement letter go to <http://www.vm.ibm.com> and click on the z/VM release. Refer to the DEVICEnnnn Preventative Service Planning (PSP) bucket for the minimal MCL level and any required updates or PTFs.

### 2.4.1.2 Product Packaging

The z/VM System deliverable is available as:

- Binary image on DVD or internet delivery
- The restricted source and the PL/X source are not orderable or shipped with z/VM V7. Both will be available as no-charge downloads from IBM Resource Link at

<http://www.ibm.com/servers/resourceLink>

---

- If you are not registered with Resource Link™, you will be required to register for a user ID and password. You must also be licensed for z/VM and entitlement will be verified when you request the source code. After approval, you will receive instructions describing how to download the code.

- 
- Except for EREP the products/components/features are serviced on the stacked RSU. The stacked RSU will be updated and refreshed in the product install package. The naming convention for the stacked RSU is *VRnn* (ie. *VRnn*, where VR is the z/VM version, release and nn is incremented by one for each level built).

**Note:**

z/VM is the successor to IBM's VM/ESA® operating system. Some products and functions supported on z/VM and some publications might continue to use VM/ESA in their names.

### **Withdrawal of distribution medium**

z/VM V6.3 will be the last release of z/VM that will be available on tape. Subsequent releases will be available on DVD or electronically.

Distribution of the Recommended Service Update (RSU) on CD-ROM in Optical Media Attachment/2 (OMA/2) format has been discontinued.

### **Changes to the z/VM System Delivery Offering (SDO)**

The following changes have been included with z/VM 6.2 and higher:

- The Licensed Products orderable through the z/VM SDO are not being service refreshed as of z/VM 6.2. Service and new releases of these products will be available under the individual Licensed Product Numbers.
- The SDO Optional Enabling Aid Product files are valid for z/VM 6.2 and higher.
- The following Licensed Products are no longer orderable through the z/VM SDO. Those that are not available can be ordered under the individual IBM Licensed Product ID number. For Example to order APPC you will use PID 5654-010. Contact your IBM Sales Representative for additional information.
  - 5654-010 APPC APPL SUITE V1R1.0
  - 5697-F42 DB2 DATA PROPAGATOR V7R4.0
  - 5697-F42 DB2 NLS VM HELP FILES V7R5.0
  - 5697-F42 DB2 CLIENT NLS VM HELP FILES V7R5.0

With your Licensed Product order, you will receive a Program Directory for most of the Licensed Products ordered. There are a few products that do not have Program Directories or may have Installation Guides instead. Many of the SDO products can still be installed using the directions in this *z/VM SDO Program Directory*. However, it is also possible that while installing a Licensed Product, you will be asked to refer to the product's Program Directory.

- Virtualization technology and Linux enablement

z/VM V6.2 implemented multi-system virtualization clustering technology allowing up to four z/VM instances to be clustered together as members in a Single System Image (VMSSI). This multi-system virtualization clustering technology is a first for the mainframe. Members of a z/VM SSI cluster are managed, serviced and administered as a single system and share the following resources:

- User directory
- Minidisks
- SPOOL files
- Network device MAC addresses

Live Guest Relocation (LGR) is a function of a z/VM SSI cluster that provides the capability for a running Linux virtual machine to be moved transparently without disruption from one z/VM system to another within a Single System Image. Live Guest Relocation provides continuity for virtual server workloads during planned z/VM and machine outages, such as service and hardware upgrades.

- Technology exploitation

z/VM 7.1 provides support for the newest IBM Z® hardware technologies, z14 Models M01, M02, M03, M04, and ZR1. LinuxONE Rockhopper II, LinuxONE Emperor II, z13®, z13s®, IBM zEnterprise EC12 and IBM zEnterprise BC12. z/VM V7.1 includes an Architecture Level Set and requires IBM zEnterprise EC12 or BC12 or later systems.

z/VM 6.4 provides support for the IBM z13™, IBM z13s, LinuxONE Rockhopper, and LinuxONE Emperor.

- Withdrawal of Support for RPC-Based System Management APIs

With z/VM 6.1, IBM withdrew support for the RPC-based System Management APIs. This satisfied the statement of direction made in the IBM Software Announcement dated February 6, 2007. Sockets-based System Management APIs continue to be supported.

- Withdrawal of Kanji NLS Files

With z/VM 7.1, z/VM message repositories, help files and other panel or text files are not translated into Kanji.

SDO Packaging Changes from z/VM 5.4 that still applied for z/VM 6.1:

- Removal of Delivery of the SDO Enabling Aid with SDO Product Order

With z/VM 5.4, the SDO Enabling Aid feature was no longer shipped with the SDO Product Order, it was only available as an electronic Internet download from the IBM Website at

<http://www.vm.ibm.com/sdo>

### **z/VM Information Center**

IBM publishes the z/VM documentation in an IBM Knowledge Center here:

<http://www.ibm.com/support/knowledgecenter/SSB27U>

### **z/VM Collection DVD image**

The z/VM Collection Kit is no longer available after z/VM 6.3.

---

## **2.4.3 DASD Storage Requirements**

Refer to *z/VM Installation Guide* for the DASD storage requirements.

It is important to have page, spool, and temp space defined. Paging space, spooling space, and temporary minidisk space (PAGE, TEMP, and TDSK, respectively) are installation dependent. The amount of page space required depends on the number and size of logged-on virtual machines, processor size and workload. The amount of space needed for spooling and temporary minidisk requests will be dependent upon user demand and application requirements.

For more information on virtual machine DASD requirements and allocation for PAGE, TEMP, and TDSK, please refer to *z/VM CP Planning and Administration*.

## **2.4.4 Install the z/VM System**

Install the z/VM System prior to installing the Licensed Products.

1. Install the z/VM System using the appropriate steps in the *z/VM Installation Guide*. The stacked RSU will be installed as part of the z/VM installation.
  2. Install additional service, if noted in the Preventive Service Planning stage. This service is specified either in the z/VM Program Directory or the z/VM PSP Bucket.
  3. After the installation of the z/VM System and RSU, and other necessary configurations as stated in *z/VM Installation Guide*, return back to this point in the SDO Program Directory when you are ready to install the Licensed Products.
  4. If the SDO order includes licensed program products, continue the installation with the following instructions. If there are no additional products, the installation of the z/VM System and z/VM SDO is complete.
- 

## 2.5 Plan for Licensed Product Interdependencies

Many Licensed Products are dependent upon other Licensed Products for successful installation or in order for the product to execute correctly. Based on the Licensed Products to be installed, you should now plan for installation of any pre-requisite, co-requisite and if-requisites products. A pre-requisite product is one that is required to be installed before you install the Licensed Product, so you should also plan for the order the products should be installed.

See Appendix B, “IBM Licensed Program Products Interdependencies” on page 197 to verify the Pre-requisites, Co-requisites, and If-Requisites for the Licensed Products and plan for the order of installation.

When installing a Licensed Product that is a prerequisite to another previously installed Licensed Product(s), it is recommended that the other Licensed Product(s) be re-installed. Also, you may need to increase the space available on the minidisk, especially if the install process loads files to a common minidisk, such as the Product Code Disk (MAINT 19E)

### **Warning**

There is a possibility of losing customized files if a Licensed Product is reinstalled over an existing version.

## 2.6 Determine the Install Format of the Licensed Products

The instructions for installing Licensed Products depends on the install format of the product. To determine the install format of the product, refer to Appendix A, “z/VM SDO IBM Licensed Program Products”.

To install each Licensed Product, begin by following the general installation instructions for that Licensed Product's format. Then complete the installation by following the specific installation instructions for that Licensed Product in the Technical Notes.

- **VMSES/E**

- Chapter 3.0, “VMSES/E Licensed Product Installation Instructions”

- . Chapter 5.0, “VMSES/E Licensed Product Technical Notes”.

- **Semi-VMSES/E**

- Chapter 4.0, “Semi-VMSES/E Licensed Product Installation Instructions” .

- Chapter 6.0, “Semi-VMSES/E Licensed Product Technical Notes” .

---

## 3.0 VMSES/E Licensed Product Installation Instructions

The following is a brief description of the main steps for installing an z/VM SDO VMSES/E Licensed Product using VMSES/E. If you have any questions about using VMSES/E, refer to *z/VM VMSES/E Introduction and Reference*.

The z/VM System serves as an installation platform for other Licensed Products in the SDO package. After the installation of a base z/VM system, the Licensed Products can be installed.

---

### 3.1 Checklist of the VMSES/E Licensed Products Installation Process

Notes:

- *Perform the steps in order.*
- *Mandatory steps are preceded by squares (■).*
- *Optional steps are preceded by circles (○).*

---

**For each VMSES/E Licensed Product, perform the following installation steps**

- ■ **3.2, Allocate DASD and Userids**
- ■ **3.3, Prepare the VMSES/E Order for Installation**
- ■ **3.4, Install the z/VM SDO VMSES/E Licensed Product by following the instructions in the Technical Notes**

— ■ Install using the VMFINS command

— ■ Technical Notes may refer to additional instructions in the Licensed Product Program Directory

— ■ Re-save Saved Segments for some Licensed Products

— ■ Verify successful installation

**If the SDO order includes additional VMSES/E Licensed Products, repeat the installation steps in this checklist beginning at 3.2, Allocate DASD and Userids**

### 3.2 Allocate DASD and Userids

Appendix C, "DASD Requirements" on page 201 identifies the user IDs and minidisks necessary to install each of the Licensed Product. This information is provided to help plan for DASD storage and other requirements for the installation of these Licensed Products.

Create any required user IDs and minidisks before beginning the installation. Also, any newly created

minidisks must be formatted.

---

### 3.3 Prepare the VMSES/E Order for Installation

The IBM Licensed Program Product order can be fulfilled either by DVD or downloaded from the internet. In the next step, you will prepare the Product Envelope delivered via the internet for the installation.

#### 3.3.1 Prepare the Product Envelope Delivered from Internet

To install a product using a Product Envelope delivered from the Internet, follow the Installation Instructions provided with Shopz to upload the Product Envelope to the host VM system and de-compact it.

To identify the contents of your order, refer to the packing list provided by Shopz. Match the file names of the downloaded files, to the names listed under the heading 'Ref. No.'. The description will tell you the contents of your file. It may be helpful to rename this file to a descriptive name so that it is easily recognized for future reference. The file type must be renamed to SERVLINK.

##### **Example**

V6608454 TERS0028	* File name on Workstation
V6608454 BIN	* File received to VM as Binary Fixed 1024
HLASM SERVLINK	* De-compacted file and renamed to SERVLINK

After you have uploaded the Product Envelope to the VM host system in BINARY FIXED 1024 and de-compacted the file, you may install the product. When installing using a Product Envelope, the ENV option must be used with the VMFINS commands.

### 3.4 Install the z/VM SDO VMSES/E Licensed Product

To complete the installation process for a VMSES/E Licensed Product:

1. Review the Technical Notes for the product in the Chapter 5.0, "VMSES/E Licensed Product Technical Notes" on page 43. The Technical Notes will refer to the appropriate sections in the Licensed Product Program Directory and give additional important information about the product.
2. Follow the Installation Instructions in the Program directory of each Licensed Product.

##### **NOTE**



In the case of a conflict, the information provided in the Licensed Program Product's Program Directory overrides the information provided in this SDO Program Directory and in the *z/VM SDO Enabling Aid*.

The SDO Program Directory will refer to the Licensed Program Product Program Directory and/or other z/VM or Licensed Program Product documents when appropriate.

#### **Important Note for Product Envelopes**

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

*EXAMPLE: VMFINS INSTALL INFO (NOMEMO ENV HLASM*

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

*EXAMPLE: VMFINS INSTALL PPF 5696234J HLASM (PLAN NOMEMO ENV HLASM*

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

*EXAMPLE: VMFINS INSTALL PPF 5696234J HLASMT (NOMEMO NOLINK ENV HLASM*

---

## **4.0 Semi-VMSES/E Licensed Product Installation Instructions**

The following chapter describes the system environment required and explains how to install a Semi-VMSES/E Licensed Product.

The z/VM System serves as an installation platform for other Licensed Products in the SDO package. Licensed Products can be installed after the installation of base z/VM system.

### **4.1 Checklist for the Semi-VMSES/E Licensed Products Installation Process**

---

Notes:

- *Perform the steps in order.*
- *Mandatory steps are preceded by squares (■).*
- *Optional steps are preceded by circles (○).*

**For each Semi-VMSES/E Licensed Products, perform the following installation steps**

#### ■ 4.3, Semi-VMSES/E Installation Overview and Planning

- ■ 4.3.1, Plan for the Installation of the Semi-VMSES/E Licensed Product
- ■ 4.3.2, Prepare the Semi-VMSES/E Order for Installation
- ○ 4.3.3, Load Installation-Related Files from Tape
- ■ 4.3.4, Allocate Resources for the Semi-VMSES/E Licensed Product Choose from the following:
  - Install Directly to Default Production Minidisks
  - Install to Test Minidisks, Production Minidisks
  - Installing to Shared File System

#### ■ 4.4, Install the Semi-VMSES/E Licensed Product using the VMFINS command in conjunction with the instructions in the Technical Notes for the Licensed Product.

- ■ Install using the VMFINS command
- ■ Technical Notes may refer to additional instructions in the Licensed Product Program Directory
- ■ Re-save Saved Segments for some Licensed Products
- ■ Verify successful installation
- **If installed to PRETEST place Licensed Product files into production after testing**

**If the SDO order includes additional SEMI-VMSES/E Licensed Products, repeat the installation steps in this checklist beginning at 4.3, Semi-VMSES/E Installation Overview and Planning**

## 4.2 Semi-VMSES/E Licensed Product Definition

z/VM SDO Semi-VMSES/E Licensed Products are products that are not originally in VMSES/E format but have been installed using the IBM recommended defaults. Because installation files are created and many installation steps are already taken, this will reduce the time it will take to install this Licensed Product. The installation procedure (the Innnnnnn EXEC, where nnnnnnn is the Licensed Product number and the INSTFPP exec) are used to generate new files. All these files are delivered on the Semi-VMSES/E Licensed Product tape.

After this process, the files are in VMSES/E enabled format which is supported by VMFINS (the installation tool for VMSES/E). To install from a Semi-VMSES/E Licensed Product tape, the system must be at z/VM SDO Version 6 Release 4.0. The Innnnnnn EXEC has been used for each Licensed Product and will not be used again.

---

## 4.3 Semi-VMSES/E Installation Overview and Planning

The VMFINS EXEC will be used to install all Semi-VMSES/E Licensed Products. This exec is supplied as part of the VMSES/E component of z/VM and provides a consistent process for installing z/VM and Licensed Products. The VMFINS command syntax is given in Chapter 6.0, “Semi-VMSES/E Licensed Product Technical Notes” for each Licensed Product. Installations may be done from any user ID which has the authority to obtain write access to installation minidisks, write access to Software Inventory Disk (MAINT 51D), and read access to VMSES/E Build Disk (MAINT 5E5).

For a complete description of the VMFINS EXEC and its options, refer to:

*z/VM VMSES/E Introduction and Reference*

The step-by-step procedures that follow are in two column format. The steps to be performed are in bold large numbers. The commands associated with these steps are on the left-hand side of the page in bold print; additional information for a command may exist to the right of that command.

Each step of these installation instructions must be followed. Do not skip any step unless directed otherwise.

Throughout these instructions, the use of IBM-supplied default minidisk addresses and user IDs is assumed. If you use different user IDs, minidisk addresses, or SFS directories to install a Licensed Product, adapt these instructions as needed for your environment.

The sample console output results presented throughout these instructions may differ from those depicted here.

---

### 4.3.1 Plan for the Installation of the Semi-VMSES/E Licensed Product

Each Semi-VMSES/E Licensed Product can either be placed directly into production on the installation defaulted minidisks, can be installed first to “test” mode then to the production minidisks, or installed to the Shared File System (SFS) directories.

It's recommended that you install each Semi-VMSES/E Licensed Product in “test” mode, so that Licensed Product files are loaded to alternate (or “test”) minidisks, instead of directly into production. This will also help avoid problems if a previous version or level of the Licensed Product is currently in production on your system.

If you want to place a Licensed Product directly into production, you can do so by specifying a production-related component when you issue the VMFINS installation commands. The components that will allow this type of installation contain the string PRD at the end of the component name.

### 4.3.2 Prepare the Semi-VMSES/E Order for Installation

The IBM Licensed Program Product order can be fulfilled either by physical DVD or downloaded from the internet. In the next step, you will either mount the physical DVD or prepare the internet delivered Product Envelope for the installation.

### 4.3.2.1 Prepare the Product Envelope Delivered from Internet

To install a product using a Product Envelope delivered from the Internet, follow the Installation Instructions provided with Shopz to upload the Product Envelope to the host VM system and de-compact it. To identify the contents of your order, refer to the packing list provided by Shopz. Match the file names of the downloaded files, to the names listed under the heading 'Ref. No.'. The description will tell you the contents of your file. It may be helpful to rename this file to a descriptive name so that it is easily recognized for future reference. The file type must be renamed to SERVLINK.

#### Example

V6608454 TERS0028	* File name on Workstation
V6608454 BIN	* File received to VM as Binary Fixed 1024
EREP SERVLINK	* De-compacted file and renamed to SERVLINK

After you have uploaded the Product Envelope to the VM host system in BINARY FIXED 1024 and de-compacted the file, you may install the product. When installing using a Product Envelope, the ENV option must be used with the VMFINS commands. For instructions on uploading and de-compacting the files please refer to: <http://www.vm.ibm.com/install/prodinst.html>

#### Important Note for Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

*EXAMPLE: VMFINS INSTALL INFO (NOMEMO ENV EREP*

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

*EXAMPLE: VMFINS INSTALL PPF \$5654260 EREPPRD (PLAN NOMEMO ENV EREP*

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO ENV *envelope\_filename***

*EXAMPLE: VMFINS INSTALL PPF \$5654260 EREPPRD (NOMEMO ENV EREP*

### 4.3.3 Load Installation-Related Files from Tape

This step is optional. However, it is necessary to perform these steps if you are installing to SFS directories in order to get the resources needed for SFS.

The Installation-Related files include all the Memo-to-Users, various Licensed Product control files, including the Product Parameter file (PPF) and the PRODPART files. It will also create the VMFINS PRODLIST file which contains a list of Licensed Products on the installation tape. Although the VMFINS command is being used in this step, the product will **not** be loaded at this time.

To install information on the tape contents, perform the following steps.

---

**1** Log on to your Licensed Product installation user ID.

**cp link maint 5e5 5e5 rr**  
*read password*  
**access 5e5 b**

The 5E5 minidisk is where VMSES/E resides.

**Note:** The linking of VMSES/E Build Disk (MAINT 5E5) is only required if you are not installing from userid MAINT.

This user ID can be any ID that has read access to the VMSES/E Build Disk (MAINT 5E5) and write access to the Software Inventory Disk (MAINT 51D).

- 2** Ensure the tape is mounted and attached to the installation userid at virtual address 181.
- 3** Establish write access to the Software Inventory minidisk if it's not already linked R/W.

**cp link maint 51d 51d mr**  
*multi password*  
**access 51d d**

The Software Inventory Disk (MAINT 51D) is where the VMSES/E system-level Software Inventory and other Licensed Product dependent files reside.

**Note:** If another user already has the Software Inventory Disk (MAINT 51D) linked in write mode (R/W), you will obtain only read access (R/O) to this minidisk. If this occurs, you will need to have that user re-link the Software Inventory Disk (MAINT 51D) in read-only mode (RR), and then re-issue the above LINK and ACCESS commands. Do not continue with these procedures until a R/W link is established to the Software Inventory Disk (MAINT 51D).

- 4** Load Licensed Product-specific files to the Software Inventory Disk (MAINT 51D).

**a** If installing from a tape:

**vmfins install info (nomemo**

**b** If installing from a Product Envelope:

**vmfins install info (nomemo env *envelope\_filename***

---

The NOMEMO option will load memos from the tape but will not issue a prompt to send them to the system printer. Specify the MEMO option if you want to be prompted for printing the memo.

This command will perform the following:

- loads all of the Memo-to-Users
- loads various Licensed Product control files, including the Product Parameter file (PPF) and PRODPART files
- create the VMFINS PRODLIST on your A-disk. The VMFINS PRODLIST contains a list of Licensed Products on the installation tape.

```
VMFINS2767I Reading VMFINS DEFAULTS B for additional options
VMFINS2760I VMFINS processing started
VMFINS1909I VMFINS PRODLIST created on your A-disk
VMFINS2760I VMFINS processing completed successfully
Ready;
```

#### Notes:

1. Licensed Product files will **not** be loaded by the VMFINS command at this time.
  2. If you are installing one or more Licensed Products using SFS directories, you should review the information in Chapter 4.3.4.3, “Shared File System (SFS) Considerations” on page 35 before you continue with this step.
  3. If you change the PPF name, a default user ID, or other parameters associated with a given Licensed Product via a PPF override, you will need to use your changed values instead of those indicated (when appropriate), throughout the remainder of the installation process for that Licensed Product. For example, you will need to specify your PPF override file name instead of the name of the PPF file provided on the tape for certain VMSES/E commands.
  4. If you are not familiar with creating PPF overrides using VMFINS, you should review the 'Using the Make Override Panel' section in the chapter entitled “Using the VMFINS EXEC” of *z/VM VMSES/E Introduction and Reference* before you continue.
- 

### 4.3.4 Allocate Resources for the Semi-VMSES/E Licensed Product

Each Semi-VMSES/E Licensed Product can be placed directly into production on the default production minidisks, or can be installed first to “test” mode then to the production minidisks, or to Shared File System (SFS) directories.

If you are going to install directly to production minidisks, continue with Chapter 4.3.4.1, “Default Production Minidisks”.

If you plan to install first to Test minidisks, continue with Chapter 4.3.4.2, “Semi-VMSES/E Test Resource

Requirements.”

If you are installing to SFS, continue with Chapter 4.3.4.3, “Shared File System (SFS) Considerations”.

#### 4.3.4.1 Default Production Minidisks

The IBM-supplied default minidisk addresses and user IDs can be found in Appendix C, “DASD Requirements”. This Appendix lists all the z/VM SDO products and their DASD Requirements. If you performed the optional step in 4.3.3, “Load Installation-Related Files from Tape” on page 30, the resource information can be found in the PLANINFO file. Using this information, allocate the resources.

Once the default production minidisks have been allocated, continue the installation in Chapter 4.4, “Install the Semi-VMSES/E Licensed Product”.

#### 4.3.4.2 Semi-VMSES/E Test Resource Requirements

If you have decided to install Semi-VMSES/E Licensed Products on test minidisks, for each selected Licensed Product:

1. Add to your system directory a user ID called **PRETEST**. This user ID is used as a place holder for the test minidisks and will own all the alternate minidisks used in conjunction with the Semi-VMSES/E Licensed Products.
  2. Set up and format the appropriate minidisks listed in Figure 2. These minidisks must be set up and formatted before you begin the installation process. Additionally, they must be defined using addresses within the range 400 to 4FF, as indicated in Figure 2.
  3. The minidisks required for the Licensed Product must be allocated as well because some Licensed Products may have files placed on any one of the Licensed Product's minidisks (i.e. MAINT 319). Refer to Chapter Appendix C, “DASD Requirements” for a list of minidisk requirements.
  4. For features which have PRETEST addresses which are the same as the base, add the number of blocks needed for both the base and feature(s) to get the total number of blocks required for test installation.
- 

The installation will fail if the resource is not allocated (i.e. defined and formatted). Files which will eventually end up on end user disks, will be loaded to the test disk(s), and all others are loaded to the appropriate disk (memos, etc.). If the product has one or more features, it may use the same test minidisk as the base product.

In Chapter 6.0, “Semi-VMSES/E Licensed Product Technical Notes”, you will be given the **VMFINS** command to install the Licensed Product on the test minidisk(s). All of the Licensed Products end user files will be placed on the test minidisk(s).

Once you have completed testing, you will copy the files from the test minidisk to the “Related Production Disk” via the **VMFCOPY** command.

*Figure 2. PRETEST minidisk requirements*

Licensed Product Number	Description	PRETEST Minidisk	Size -CMS 4K blocks unless otherwise stated	Related Production Minidisk
5654-260	EREP	431	2250	MAINT 201
5684-043	ISPF	458	150	ISPVM 191
		459	6700	ISPVM 192
5684-123	ISPF PDF	457	6000	ISPVM 192
5684-123	ISPF PDF NLS	457	2700	ISPVM 192
5697-F42	DB2/VM	476	360	SQLMACH 198
		477	900	SQLMACH 199
		46A	1620	SQLDRR 191
		47C	3600	MSTRSRVO 195
		479	6660	5697F75A 193
5697-F42	DB2/VM Client Edition	476	360	SQLCLNT 198
		477	900	SQLCLNT 199
		46A	1620	SQLDRR 191
		47C	3600	MSTRSRVO 195
		47E	6660	5697F75C 193

Once the test and default minidisks have been allocated, continue the installation in Chapter 4.4, "Install the Semi-VMSES/E Licensed Product".

---

#### 4.3.4.3 Shared File System (SFS) Considerations

This section provides basic information about changes to these instructions you will need to make if you plan to install any Semi-VMSES/E Licensed Product using SFS directories. However, you may need to make additional changes or adjustments, based on the actual Licensed Product(s) you are installing in this manner.

In general, you will need to adapt any minidisk-specific instructions and concepts to account for an SFS environment. And, when issuing a VMFINS command, you will need to specify an SFS-related component name instead of those established for a minidisk environment (SFS-related component names use the string `SFS` as part of the component name.).

You'll also need to obtain the SFS storage requirements for each Licensed Product using the PLAN option of the VMFINS command; this option will create a `$NNNNNNN PLANINFO` file that contains this information.

**Note:** VMSYS is the filepool name used in the supplied PPF for both test and production SFS installations.

After the appropriate planning information is available (within the `$NNNNNNN PLANINFO` file), you will



need to do the following:

- 1 Determine the number of 4K blocks that are required for the SFS directories you will use. Refer to the \$NNNNNNNN PLANINFO file and add up the 4K blocks required for each SFS directory you plan to use. This will give you the total number of 4K blocks required. You should also keep track of the 4K block requirements for each user ID as well.

You'll need this information if you need to enroll any Licensed Product user IDs in the VMSYS filepool, or if you need to increase the space allocated to an existing user ID.

**Note:** If you have created your own PPF override file, you should use your PPF name instead of \$NNNNNNNN.

- 2 Enroll any required Licensed Product user IDs in the VMSYS filepool by using the ENROLL USER command:

```
ENROLL USER userid VMSYS (BLOCKS blocks)
```

where *userid* is the actual user ID to be enrolled and *blocks* is the number of 4K blocks required for this user ID, that you calculated previously.

**Note:** The ENROLL USER must be issued from a user ID that is an administrator for the VMSYS filepool.

- 3 Determine if there are enough blocks available in the filepool to install the Licensed Product. This information can be obtained by using the QUERY FILEPOOL STATUS command. Near the end of the output from this command is a list of minidisks in the filepool and the number of blocks free. If the number of available blocks is smaller than the total available 4K blocks needed for this Licensed Product, you will need to add space to the filepool. See the *z/VM CMS File Pool Planning, Administration, and Operation* manual for information on adding space to a filepool.
- 4 Create the subdirectories listed in the \$NNNNNNNN PLANINFO file using the CREATE command with the DIRECTORY option.

**set filepool vmsys:  
create directory *dirid***

*dirid* is the name of the SFS directory you are creating, such as:

```
CREATE DIRECTORY dirid
```

If necessary, see the *z/VM CMS Commands and Utilities Reference* for more information about the CREATE DIRECTORY command.

**Note:** Subdirectories, when required, must be created from the respective user IDs.

- 5 Give SFS READ (and in some cases, WRITE) authority for each directory to those user IDs for which it's appropriate, using the GRANT AUTHORITY command.

**grant auth** *dirid to userid (authority*

If necessary, see the *z/VM CMS Commands and Utilities Reference* for more information about the GRANT AUTHORITY command.

---

## 4.4 Install the Semi-VMSES/E Licensed Product

### Notes:

Before you continue with the installation process, ensure you have completed the following:

1. Added all of the required user ID directories to the system directory.
2. Changed the passwords for all added user IDs from xxxxx to valid passwords, in accordance with your security guidelines.
3. Placed the new directories on-line using VM/Directory Maintenance (DIRMAINT) or an equivalent CP directory maintenance method.
4. Formatted any newly created minidisks or created SFS directories.

### NOTE

In the case of a conflict, the information provided in the Licensed Program Product's Program Directory overrides the information provided in this SDO Program Directory. The SDO Program Directory will refer to the Licensed Program Product Program Directory and/or other z/VM or Licensed Program Product documents when appropriate.

### 4.4.1 Install Using the VMFINS EXEC

- 1** Log on to the product installation user ID.
- 2** Establish write access to the **MAINT 51d** and **5e5**, if it's not already linked R/W.

```
cp link maint 5e5 5e5 rr
read password
cp link maint 51d 51d mr
multi password
```

The Software Inventory Disk (MAINT 51D) is where the VMSES/E system-level Software Inventory files reside.

- 3** Create a PROFILE EXEC that will contain **ACCESS** commands for the VMSES/E Build Disk (MAINT 5E5) and Software Inventory Disk (MAINT 51D), or add these commands to the existing PROFILE EXEC.

```
xedit profile exec a
====> input /**/
```

```
====> input 'ACCESS 5E5 B'
====> input 'ACCESS 51D D'
====> file
```

- 4** Use the profile to access the VMSES/E Build Disk (MAINT 5E5) and Software Inventory Disk (MAINT 51D).

#### profile

- 5** Ensure the tape is mounted and attached to the installation user ID at virtual address 181. The VMFINS EXEC requires the tape drive to be at virtual address 181.

**Note:** Please be aware that if you have more than one tape, that they are independent of each other. Therefore, you must mount the tape on which the Licensed Product is loaded.

- 6** Install the Licensed

Product. **Notes:**

- a. If you have already created a PPF override file, you should specify your override file name after the **PPF** keyword for the following VMFINS command.
- b. You may be prompted for additional information during VMFINS INSTALL processing depending on your installation environment. If you are unsure how to respond to a prompt, refer to the “Installing Products with VMFINS” and “Install Scenarios” chapters in the *z/VM VMSES/E Introduction and Reference* to decide how to proceed.

**Note!**

The specific command for each product can be found in Chapter 6.0, “Semi-VMSES/E Licensed Product Technical Notes” on page 147.

**a** If installing from a tape:

```
vmfins install ppf ppfname {compid | compidsfs | compidprd | compidsfsprd} (nomemo
```

**b** If installing from a Product Envelope:

```
vmfins install ppf ppfname {compid | compidsfs | compidprd | compidsfsprd} (nomemo env
envelope_filename
```

Use *compid* if you are installing using test minidisks and **not** placing this Licensed Product

directly into production.

Use *compidsfs* if you are installing using test SFS directories and **not** placing this Licensed Product directly into production.

Use *compidprd* if you are installing using minidisks and you **are** placing this Licensed Product directly into production.

Use *compidsfsprd* if you are installing using SFS directories and you **are** placing this Licensed Product directly into production.

**Note:** If you have created your own PPF override file, you should use your PPF name instead of \$NNNNNNN.

LINK is the default option on the VMFINS INSTALL command. The LINK option should be utilized so that required minidisks not owned by the installation user ID will be available. VMFINS will attempt to link to these minidisks, and will access them in the appropriate order.

```
VMFINS2767I Reading VMFINS DEFAULTS B for additional options VMFINS2760I
VMFINS processing started
VMFINS2601R Do you want to create an override for :PPF $NNNNNN COMPID
           $nnnnnn%COMPID?
           Enter 0 (No), 1 (Yes) or 2 (Exit)
```

**0**

Enter 0 to bypass creating an override.

Enter 1 to create an override, change the PPF name, and change minidisk definitions.

Enter 2 to exit the VMFINS exec.

```

VMFINS2603I Processing product :PPF $MNNNNN COMPID :PRODID $nnnnnn
VMFEQ2805I Product :PPF $MNNNNN COMPID :PRODID $nnnnnr%COMPID
requisite checking
VMFINI2603I Installing product :PPF $MNNNNN COMPID :PRODID $nnnnnn
VMFSET2760I VMFSETUP processing started for $nnnnnn COMPID
VMFUTL2205I Minidisk|Directory Assignments:
String      Mode Stat Vdev Label/Directory
VMFUTL2205I string      fm      R/W dev  label
.
VMFUTL2205I ----- A      R/W 191  INS191
VMFUTL2205I ----- B      R/O 5E5  MNT5E5
VMFUTL2205I ----- D      R/W 51D  MNT51D
VMFUTL2205I ----- S      R/O 190  MNT190
VMFUTL2205I ----- Y/S   R/O 19E  MNT19E
VMFSET2760I VMFSETUP processing completed successfully
VMFREC2760I VMFREC processing started
VMFREC1851I (1 of nm) VMFRCALL processing tapefile
VMFRCA2159I Loading part(s) to string dev (fm)
VMFRCA2159I Loaded nn part(s) to string dev (fm)
.
VMFREC1851I (nm of nm) VMFRCALL processing tapefile
VMFRCA2159I Loading part(s) to string dev (fm)
VMFRCA2159I Loaded nn part(s) to string dev (fm)
VMFREC2760I VMFREC processing completed successfully
VMFINI2603I Product installed
VMFINS2760I VMFINS processing completed successfully
Ready;

```

- 7** Review the install message log (\$VMFINS \$MSGLOG). If necessary, correct any problems before going on. For information about handling specific installation messages, see the appropriate z/VM manual.

## vmfview install

### 4.4.2 Place IBM Licensed Program Product into Production

If you did not install this Licensed Product directly into production, you should verify that its components operate satisfactorily within your environment, using the appropriate PRETEST alternate minidisks, and Licensed Product documentation. When you have completed your testing, you should resume with the steps described below.

**Notes:**

1. The following steps should be done from the MAINT user ID, with links to the required installation minidisks, so that appropriate CMS shared segments can be re-saved, when necessary.
2. You will need to repeat steps 2 and 3 for each pair of test/production minidisks that are associated with this Licensed Product.

**1** Log on to the **MAINT** user ID.

**2** Link and access the appropriate test build (PRETEST 4xx) and production build minidisks. With regard to the latter minidisk, note the following:

- The production minidisk only needs to be linked if it's not a MAINT-owned minidisk.
- If another user already has the production minidisk linked in write mode (R/W), you will obtain only read access (R/O) to this minidisk. If this occurs, you will need to have that user re-link this minidisk in read-only mode (RR), and then re-issue the appropriate LINK and ACCESS commands. Do not continue with these procedures until a R/W link is established to this minidisk.

**cp link PRETEST 4xx addr1 wr multi password**

- *addr1* is an available minidisk address on the MAINT user ID. *4xx* is the address of the PRETEST test build minidisk where Licensed Product files were loaded to during installation

**cp link userid prdaddr addr2 mr multi password**

*addr2* is an available minidisk address on the MAINT user ID. *prdaddr* is the address of the *userid* production build minidisk where Licensed Product files are to be copied.

**Note:** If you are already on the MAINT *userid* and have R/W access to the *prdaddr* minidisk, you do not need to do the **cp link**.

**access addr1 e**

**access addr2 f**

If *userid prdaddr* is a MAINT owned minidisk, use *prdaddr* instead of *addr2*.

**3** Copy the Licensed Product files from the test build minidisk (PRETEST 4xx) to the corresponding production build minidisk. (*userid prdaddr*).

**vmfcopy \* \* e = = f2 (prodid ppfname%compid olddate replace**

The VMFCOPY command will update the VMSES PARTCAT file on the *prdaddr* minidisk.

The time required for the VMFCOPY command will vary depending upon the number of files being copied.

**Note:**

If you have copied files to the MAINT Product Code Disk (MAINT 19E) ("Y"-disk), you will need to re-save the appropriate CMS shared segment to return this minidisk to "shared" status. If you have copied files to the MAINT AMENG Help Disk (MAINT 19D) (CMS HELP disk) you may need to re-save the CMS HELP saved segment as well. See the *z/VM Service Guide* for detailed information about how these saved segments should be saved on your system.

## 5.0 VMSES/E Licensed Product Technical Notes

This chapter provides technical considerations for the z/VM SDO VMSES/E Licensed Products. After you have followed the general instructions for VMSES/E products, from 3.0, “VMSES/E Licensed Product Installation Instructions” on page 23, locate the specific Licensed Product in this chapter to complete the installation. Products are ordered in this section by product number.

### NOTE

In the case of a conflict, the information provided in the Licensed Program Product's Program Directory overrides the information provided in this SDO Program Directory and in the *z/VM SDO Enabling Aid*.

The SDO Program Directory will refer to the Licensed Program Product Program Director and/or other z/VM or Licensed Program Product documents when appropriate.

## 5.1 VMSES/E Licensed Product Specific Considerations

---

### 5.1.1 5654-A22 XL C/C++ 130 FOR Z/VM V1R3.0

#### 5.1.1.1 PUT/ESO Applied

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6* webpage.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

#### 5.1.1.2 Service Excluded

None.

#### 5.1.1.3 Pre-Requisite Service

None.

---

#### 5.1.1.4 Co-Requisite Service



None.

### 5.1.1.5 If-Requisite Service

None.

### 5.1.1.6 Product Manuals

Form Number	Publication Title
GI11-2899	Program Directory for IBM XL C/C++ for z/VM
SC09-7625	XL C/C++ for z/VM User's Guide
SC09-7624	XL C/C++ for z/VM Run-Time Library Reference
SC09-4815	C/C++ Language Reference
GC09-4819	z/OS C/C++ Messages
SC09-4767	z/OS C/C++ User's Guide
GC09-4913	z/OS C/C++ Compiler and Run-Time Migration Guide
SC09-4765	z/OS C/C++ Programming Guide
SA22-7820	z/OS C courses
SA22-7821	z/OS C/C++ Run-Time Library Reference
GA22-7560	z/OS Language Environment Debugging Guide
SA22-7566	z/OS Language Environment Run-Time Messages

### 5.1.1.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV** *envelope\_filename*

**VMFINS INSTALL PPF** *ppfname compid* (**PLAN NOMEMO ENV** *envelope\_filename*

**VMFINS INSTALL PPF** *ppfname compid* (**NOMEMO NOLINK ENV** *envelope\_filename*

#### WARNING:

You **cannot** install both C/C++ Compiler (5654-A22) and IBM C Compiler for VM/ESA (5654-033) on the same system, both targeting the MAINT 19E disk. These two products have identically named files that would overwrite each other yielding unpredictable results. These identical files are:

**CC EXEC**

**CDSECT EXEC**

**LOCALDEF EXEC**

**CC HELPCMS**

**CDSECT HELPCMS**

**LOCALDEF HELPCMS**

**CBCDSECT MODULE**

#### Important Note for Product Installation

The 29E disk has been increased in size. Please verify you have the correct size before installation.

IBM XL C/C++ for z/VM is in VMSES/E format and cannot be installed using INSTFPP.

Refer to the *Program Directory for IBM XL C/C++ for z/VM* in the section entitled "Installation Instructions" for the steps to install IBM XL C/C++ using VMSES/E.

For customization instructions, please refer to the section entitled "Customization of Compile-Time Options" in the *Program Directory for IBM XL C/C++ for z/VM*

For instructions on applying service to IBM XL C/C++ for z/VM, please refer to the *Program Directory for IBM XL C/C++ for z/VM*, section 7 .0, entitled "Service Instructions."

### 5.1.1.8 DCSS Information

Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" for more information.

Refer to the *Program Directory for IBM XL C/C++ for z/VM* in the section 8.0 entitled "Define and Build The XL C/C++ for z/VM Compiler Saved Segment". for the steps on Saved Segments.

### 5.1.1.9 Verification

Verification of XL C/C++ is done automatically during installation.

You can run the installation verification manually by issuing the following:

**v5654A22**

## 5.1.2 5654-A23 IBM DEBUG TOOL FOR Z/VM V4R1.0

### 5.1.2.1 PUT/ESO Applied

The product is at service level ESO0809.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO* webpage.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 5.1.2.2 Service Excluded

None.

### 5.1.2.3 Pre-Requisite Service

None.

### 5.1.2.4 Co-Requisite Service

None.

---

### 5.1.2.5 If-Requisite Service

None.

### 5.1.2.6 Product Manuals

Form Number	Publication Title
GC18-9387	Licensed Program Specifications for Debug Tool

G110-8669	Program Directory for Debug Tool for z/VM
SC18-9388	Debug Tool for z/VM: User's Guide

### 5.1.2.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

**Other Program Product Requirements** Depending on the product being verified, at least one of the following (at level specified or higher):

**IBM COBOL for OS/390 & VM V2R1 (5648-A25)**

**PL/I for MVS & VM V1R1.1 (5688-235)**

**IBM XL C/C++ for z/VM V1R2 (5654-A22)**

Debug Tool for z/VM is in VMSES/E format and cannot be installed using INSTFPP.

Refer to the *Program Directory for IBM Debug Tool for z/VM* in the section entitled "Installation Instructions" for the steps to install IBM Debug Tool for z/VM using VMSES/E.

For instructions on applying service to IBM Debug Tool for z/VM, please refer to the *Program Directory for IBM Debug Tool for z/VM*, section 7.0, entitled "Service Instructions."

### 5.1.2.8 DCSS Information

Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" on page 211 for more information.

Refer to the *Program Directory for IBM Debug Tool for z/VM* in the section entitled "Define and Build the IBM Debug Tool for z/VM Saved Segments Using VMSES/E" for the steps on Saved Segments.

### 5.1.2.9 Verification

Verification of Debug Tool is done automatically during installation.

You can run the installation verification manually by issuing the following:

**V5654A23**

**Important Note for Verifying with C/C++ on z/VM**

You should have a minimum of 128M virtual storage when running the verification exec (V5654A23) on a z/VM system and choose to include the C/C++ compiler either implicitly or explicitly (with the **ALL** option).

**5.1.3 5654-010 ACF/VTAM ESA V4R2.0****5.1.3.1 PUT/ESO Applied**

The product is at service level ESO1011.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO* webpage.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

**5.1.3.2 Service Excluded**

None.

**5.1.3.3 Pre-Requisite Service**

None.

**5.1.3.4 Co-Requisite Service**

Product Number	PTF	APAR	Product Description
5664-280	UV55517	VM52524	VTAM V3R4 VM/SP
5684-095	UV55515	VM52522	VTAM V3R4 VM/ESA
5684-112	UM59196	VM59196	AVS
5684-112	UM26835	VM58989	CP
5684-112	UM26882	VM58859	CP

**5.1.3.5 If-Requisite Service**

Product Number	PTF	APAR	Product Description
----------------	-----	------	---------------------

5654-010	UV59166	VM59197	VTAM V4R2 VM/ESA
5654-010	UV59178	VM59198	VTAM V4R2 VM/ESA

### 5.1.3.6 Product Manuals

Form Number	Publication Title
GI10-8154	Program Directory for ACF/VTAM
GC31-8114	Overview of VTAM V4R2 for VM/ESA and VSE/ESA
SC31-7122	Planning for Netview, NCP, and VTAM
SC31-7123	Planning Integrated Networks
SX75-0092	Planning Aids: Pre-installation Planning Checklist
GC31-6558	VTAM Glossary for V4R2 for MVS/ESA, VM/ESA, and VSE/ESA
GC31-6490	VTAM Licensed Program Specifications
SC31-6493	VTAM Messages and Codes
GC31-8071	VTAM Migration Guide
SC31-6494	VTAM Network Implementation Guide
SC31-6495	VTAM Operation
SX75-0205	VTAM Operation Quick Reference
GC31-8089	VTAM Release Guide
SC31-6498	VTAM Resource Definition Reference
SK2T-2007	Estimating Storage for VTAM
SC31-6496	VTAM Programming
SC31-6497	VTAM Programming for LU6.2
SC31-6499	VTAM Resource Definition Samples
LY43-0063	VTAM Customization
LY43-0103	VTAM Data Areas for VM/ESA
LY43-0065	VTAM Diagnosis

### 5.1.3.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of

several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

## **DASD Storage Requirements And User ID Definitions**

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO* webpage.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO* webpage.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### **Installation Guidelines**

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

#### Notes:

If you did not receive a password with your product to bring it up as Client Server, Multi Domain, or Interenterprise you will need to contact the Key Registration Center.

After you place your order, you will receive your password, which you need to start VTAM®. In most cases, you must update your VM startup EXEC with your IBM customer number and your VTAM password for the package you have ordered. If you start VTAM with the IBM supplied sample startup EXEC (found on the samples disk), VTAM is initialized as Client/Server. If you have ordered MultiDomain or InterEnterprise, before you can start VTAM, you must edit the sample startup EXEC and replace the default customer number and VTAM password (specified on the VTAM START command) with your customer number and VTAM password obtained separately from IBM. For further information and instructions, see "PROFILE for the VTAM Virtual Machine" in the *VTAM Network Implementation Guide*.

For installation instructions, please refer to the Installation Instructions section of the *Advanced Communications Function For Virtual Telecommunications Access Method Program Directory* and Installing VTAM under VM of the *VTAM Network Implementation Guide*.

NOTE: The following minidisks for 5654010A have increased:

2D2 disk has increased to 15000 4K blocks. (100 cylinders of 3380 DASD or 84 cylinders of 3390 DASD.)

401 disk has increased to 1200 4K blocks. (8 cylinders of 3380 DASD or 7 cylinders of 3390 DASD.)

402 disk has increased to 1200 4K blocks. (8 cylinders of 3380 DASD or 7 cylinders of 3390 DASD.)

For customization instructions, please refer to *VTAM Customization*.

For service instructions, please refer to the Service Instructions section of the *Advanced Communications Function For Virtual Telecommunications Access Method Program Directory* and Applying Service of the *VTAM Network Implementation Guide*.



### **5.1.3.8 DCSS Information**

Refer to Define and Build the VTAM V4R2 for VM/ESA Saved Segments Using VMSES/E section of the *Advanced Communications Function For Virtual Telecommunications Access Method Program Directory*. Please note that the segment range is based on the segment layout as defined and distributed as part of the SDO package. See Appendix D, "Saved Segments" for more information.

### **5.1.3.9 Verification**

For verification instructions, please refer to the Verifying the Installation section of the *VTAM Network Implementation Guide*.

---

## **5.1.4 5654-010 APPC APPL SUITE V1R1.0**

---

### **5.1.4.1 PUT/ESO Applied**

The product is at service level ESO9807.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6* webpage.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **5.1.4.2 Service Excluded**

None.

### **5.1.4.3 Pre-Requisite Service**

### **5.1.4.4 Co-Requisite Service**

### **5.1.4.5 If-Requisite Service**

None.

#### 5.1.4.6 Product Manuals

Form Number	Publication Title
GI10-9617	Program Directory for APPC Application Suite for VM/ESA
SC31-6532	APPC Application Suite User's Guide
SC31-6533	APPC Application Suite Administration
SC31-6534	APPC Application Suite Programming

#### 5.1.4.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

---

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### **Installation Guidelines**

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

### **Installing Licensed Products Utilizing Product Envelopes**

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

## **OTHER PROGRAM PRODUCT REQUIREMENTS**

### **IBM C370 LIBRARY 5688-188**

For installation instructions, please refer to the Installation Instructions section of the *APPC Application Suite for VM/ESA Program Directory*.

For customization instructions, please refer to *APPC Application Suite Administration Guide* .

For service instructions, please refer to the Service Instructions section of the *APPC Application Suite for VM/ESA Program Directory* .

**Notes:**

When setting up your SERVERS (eg. ANAME, A3270) use the Administration Guide for the correct setup. The VTAM PRODPART file has a different setup and should not be used.

**5.1.4.8 DCSS Information**

None.

**5.1.4.9 Verification**

None.

**5.1.5 5654-029 DITTO V1R3.0**

**5.1.5.1 PUT/ESO Applied**

The product is at service level ESO1105.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO* webpage.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

**5.1.5.2 Service Excluded**

None.

**5.1.5.3 Pre-Requisite Service**

None.

**5.1.5.4 Co-Requisite Service**

None.

**5.1.5.5 If-Requisite Service**

None.

**5.1.5.6 Product Manuals**

Form Number	Publication Title
GI10-0438	Program Directory for DITTO/ESA for VM

GC26-9598	DITTO/ESA Installation and Customization Guide
GH19-8223	DITTO/ESA Release 3 Licensed Program Specifications
GH19-8222	Introducing DITTO/ESA Release 3
SH19-8221	DITTO/ESA Release 3 User's Guide and Reference
SX11-6110	DITTO/ESA Release 3 Reference Summary

### 5.1.5.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

---

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program

#### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### Installation Guidelines

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

DITTO/ESA is in VMSES/E format and cannot be installed using INSTFPP.

Refer to the *Program Directory for Data Interfile Transfer, Testing, and Operations Utility / ESA* section entitled "Installation Instructions" for the steps to install DITTO/ESA using VMSES/E.

#### 5.1.5.8 DCSS Information

None.

#### 5.1.5.9 Verification

To verify the installation of DITTO/ESA, perform the following steps:

1. Logon to a CMS user ID that is enabled to access and use DITTO/ESA.
2. Enter DITTO after Ready; appears on your CMS terminal.
3. The first time you invoke DITTO/ESA a copyright panel appears. Press the cancel key(F12) to continue.
4. The DITTO/ESA for VM Release 3 main menu should appear.
5. Press the menu key(F2) to flip between the task selection menu and the primary function menu. You

may decide later on your preference for daily operation.

6. Enter NEWS in the entry field or in the command line. Please read the information presented and then press the exit key to return to the menu.
7. Enter LVL in the entry field or in the command line. The information presented tells you the release and service level of DITTO/ESA.
8. Press the exit key to end the DITTO/ESA session.

---

## **5.1.6 5655-T13 IBM TIVOLI ZSECURE MANAGER FOR RACF V1R11.0**

---

### **5.1.6.1 PUT/ESO Applied**

The product is at service level ESO1010.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **5.1.6.2 Service Excluded**

None.

### **5.1.6.3 Pre-Requisite Service**

None.

### **5.1.6.4 Co-Requisite Service**

None.

### **5.1.6.5 If-Requisite Service**

None.

### **5.1.6.6 Product Manuals**

<b>Form Number</b>	<b>Publication Title</b>
GI11-7865	IBM zSecure Manager for RACF z/VM Program Directory
GC23-7984	IBM zSecure Manager for RACF z/VM License Information
Z125-6011	IBM International Program License Agreement (IPLA)

LC27-2781	IBM zSecure Manager for RACF z/VM: User Reference Manual
LCD7-1387	IBM Tivoli zSecure Suite Documentation CD

### 5.1.6.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters in the z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>



### Installation Guidelines

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements" on page 201.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

### 5.1.6.8 Installation Instructions for zSecure Manager

For installation instructions for IBM Tivoli zSecure Manager for RACF z/VM please refer to the '6.0 Installation Instructions' Section in the *Program Directory for IBM Tivoli zSecure Manager for RACF z/VM Version 1 Release 11.0*.

Please note that 'Step 1' of Section '6.4.2 BUILD the Tivoli zSecure Manager for RACF z/VM CKRCARLA LOADLIB' will be skipped if ISPF/DM is not installed on the system. However, the remaining Steps in Section 6.4.2 must be performed and the CKRCARLA LOADLIB rebuilt.

### 5.1.6.9 Service Instructions for zSecure Manager

For instructions on applying service to IBM Tivoli zSecure Manager for RACF z/VM please refer to the *Program Directory for IBM Tivoli zSecure Manager for RACF z/VM* section 7.0, entitled 'Service Instructions'

### **Important Note for Product Service**

The first paragraph in Section '7.2.5 Build Serviced Objects' incorrectly states:

'If ISPF/DM is not installed, Step 1 does not have to be performed.'

Step 1 'Rebuild IBM Tivoli zSecure Manager for RACF z/VM serviced part' **must always be performed.**

If ISPF/DM is not installed, the following steps required to link and access the ISPF/DM product code disk do not have to be performed.

release C

link ispfvm idev zdev rr

access zdev C

### **5.1.6.10 Execution Requirements for zSecure Manager**

The following program products are required to allow for Tivoli zSecure Manager for RACF z/VM to execute with full functionality -

ISPF/DM version 3 release 2 or later

zSecure Manager will execute without ISPF/DM being installed, however the zSecure panels will not be available.

ISPF/PDF is not required to provide for a full function zSecure Manager. ISPF/PDF however will allow for the utilization of z/VM capabilities such as Browse and Edit.

### **5.1.6.11 Configuration of zSecure Manager**

zSecure Manager may be utilized from any ID on the System that has been correctly configured. In order to execute zSecure Manager, the ID requires a Read link to the 5655T13B 200 disk.

A copy of the zSecure Documentation DVD is included with each order of zSecure. The DVD contains the Tivoli zSecure Documentation Suite which includes the following manuals for IBM Tivoli zSecure Manager for RACF z/VM:

SC27-2782 IBM zSecure Manager for RACF z/VM: Installation and Deployment Guide

GC23-9747 IBM Tivoli zSecure Messages

Detailed information on the configuration of IBM Tivoli zSecure Manager for RACF z/VM may be found in the *IBM Tivoli zSecure Manager for RACF z/VM Installation and Deployment Guide*

Additional information on IBM Tivoli zSecure Manager for RACF z/VM may be found at the following IBM Tivoli zSecure WebSite:

<http://www.ibm.com/software/tivoli/products/zsecure/>

### **5.1.6.12 DCSS Information**

None.

### 5.1.6.13 Verification

There is no verification program for IBM Tivoli zSecure Manager for RACF z/VM

---

## 5.1.7 5668-723 GDDM-IVU V1R1.3

### 5.1.7.1 PUT/ESO Applied

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 5.1.7.2 Service Excluded

None.

### 5.1.7.3 Pre-Requisite Service

None.

### 5.1.7.4 Co-Requisite Service

None.

### 5.1.7.5 If-Requisite Service

None.

### 5.1.7.6 Product Manuals

Form Number	Publication Title
GC33-1802	Program Directory for GDDM/VM

Form Number	Publication Title
SC33-0479	GDDM Image View Utility

### 5.1.7.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service

environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### **DASD Storage Requirements And User ID Definitions**

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### Installation Guidelines

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements" on page 201.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

### IMPORTANT NOTE:

The Program Directory for GDDM-IVU Section 6.13 mistates when to Update the Build Status Table. This needs to be done BEFORE Section 6.12: Place GDDM into Production

You will need to run it after the following sections:

1. 6.5 Install GDDM/VM using the VMFINS EXEC, Step 4
2. 6.7 Install GDDM-PGF using the VMFINS EXEC, Step 4
3. 6.8 Install GDDM-IMD using the VMFINS EXEC, Step 4
4. 6.9 Install GDDM-IVU using the VMFINS EXEC, Step 4

You can use the tables listed in Section 6.13 for reference as to what the syntax of the VMFINS command should be.

GDDM-IVU is in VMSES/E format and cannot be installed using INSTFPP.

Refer to the *Program Directory for GDDM/VM* in the section entitled "6.0 Install GDDM/VM using the VMFINS EXEC" for the steps for installing GDDM-IVU using VMSES/E.

Refer to the *Program Directory for GDDM/VM* in the section entitled "7.0 Service Instructions" for information on applying service to GDDM-IVU using VMSES/E.

### **5.1.7.8 DCSS Information**

Refer to "Using GDDM saved segments" section of the *GDDVM/VM Program Directory*

Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" for more information.

### **5.1.7.9 Verification**

GDDM/VM and GDDM/VM NLS (US ENGLISH) feature must be installed prior to verifying the installation of GDDM-IVU. Consult **Testing GDDM-IVU Installation, Chapter 9** in the *Program Directory for GDDM/VM* for instructions to run the verification.

## **5.1.8 5668-801 GDDM-IMD V2R1.3**

### **5.1.8.1 PUT/ESO Applied**

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **5.1.8.2 Service Excluded**

None.

### **5.1.8.3 Pre-Requisite Service**

None.

### **5.1.8.4 Co-Requisite Service**

None.

---

### **5.1.8.5 If-Requisite Service**

None.

### 5.1.8.6 Product Manuals

Form Number	Publication Title
GC33-1802	Program Directory for GDDM/VM
SC33-0338	GDDM Interactive Map Definition

### 5.1.8.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (PLAN NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (NOMEMO NOLINK ENV envelope\_filename**

#### IMPORTANT NOTE

The Program Directory for GDDM-IMD Section 6.13 mistakes when to Update the Build Status Table. This needs to be done BEFORE Section 6.12: Place GDDM into Production

You will need to run it after the following sections:

1. 6.5 Install GDDM/VM using the VMFINS EXEC, Step 4
2. 6.7 Install GDDM-PGF using the VMFINS EXEC, Step 4
3. 6.8 Install GDDM-IMD using the VMFINS EXEC, Step 4
4. 6.9 Install GDDM-IVU using the VMFINS EXEC, Step 4

You can use the tables listed in Section 6.13 for reference as to what the syntax of the VMFINS

GDDM-IMD is in VMSES/E format and cannot be installed using INSTFPP.

Refer to the *Program Directory for GDDM/VM* in the section entitled "6.0 Install GDDM/VM using the VMFINS EXEC" for the steps for installing GDDM-IMD using VMSES/E.

Refer to the *Program Directory for GDDM/VM* in the section entitled "7.0 Service Instructions" for information on applying service to GDDM-IMD using VMSES/E.

#### **5.1.8.8 DCSS Information**

Refer to "Using GDDM saved segments" section of the *Program Directory for GDDVM/VM*

Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" on page 211 for more information.

#### **5.1.8.9 Verification**

GDDM/VM and GDDM/VM NLS (US ENGLISH) feature must be installed prior to verifying the installation of GDDM-IMD. Consult **Testing GDDM-IMD Installation, Chapter 9** in the *Program Directory for GDDM/VM* for instructions to run the verification.

### **5.1.9 5668-812 GDDM-PGF V2R1.3**

#### **5.1.9.1 PUT/ESO Applied**

The product is at service level ESO0003.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

#### **5.1.9.2 Service Excluded**

None.

#### **5.1.9.3 Pre-Requisite Service**

None.

#### **5.1.9.4 Co-Requisite Service**

None.



### 5.1.9.5 If-Requisite Service

None.

### 5.1.9.6 Product Manuals

Form Number	Publication Title
GC33-1802	Program Directory for GDDM/VM
SC33-0328	GDDM-PGF Interactive Chart Utility

Form Number	Publication Title
SC33-0913	GDDM-PGF Application Programming Guide
SC33-0333	GDDM-PGF Application Programming Reference
SC33-0330	GDDM-PGF Vector Symbol Editor
SC33-1776	GDDM-PGF OPS User's Guide

### 5.1.9.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

---

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:  
<http://www.vm.ibm.com/sdo/>

## Installation Guidelines

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

## Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename* VMFINS INSTALL PPF  
*ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

**IMPORTANT NOTE:** The Program Directory for GDDM-PGF Section 6.13 mistates when to Update the Build Status Table. This needs to be done BEFORE Section 6.12: Place GDDM into Production

You will need to run it after the following sections:

1. 6.5 Install GDDM/VM using the VMFINS EXEC, Step 4
2. 6.7 Install GDDM-PGF using the VMFINS EXEC, Step 4
3. 6.8 Install GDDM-IMD using the VMFINS EXEC, Step 4
4. 6.9 Install GDDM-IVU using the VMFINS EXEC, Step 4

You can use the tables listed in Section 6.13 for reference as to what the syntax of the VMFINS command should be.

GDDM-PGF is in VMSES/E format and cannot be installed using INSTFPP. Refer to the *Program Directory for GDDM/VM*, Chapter 6.0, "Installation Instructions" and Chapter 7.0, "Service Instructions", for

the steps to install and apply service to GDDM-PGF using VMSES/E.

### 5.1.9.8 DCSS Information

Refer to “Using GDDM saved segments” section of the *Program Directory for GDDVM/VM*

Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, “Saved Segments” on page 211 for more information.

### 5.1.9.9 Verification

GDDM/VM and GDDM/VM NLS (US ENGLISH) feature must be installed prior to verifying the installation of GDDM-PGF. Consult **Testing GDDM-PGF Installation, Chapter 9** in the *Program Directory for GDDM/VM* for instructions to run the verification.

---

## 5.1.10 5684-042 ICKDSF V1R17.0

### 5.1.10.1 PUT/ESO Applied

The product is at service level ESO1201.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 5.1.10.2 Service Excluded

None.

### 5.1.10.3 Pre-Requisite Service

None.

### 5.1.10.4 Co-Requisite Service

None.

---

### 5.1.10.5 If-Requisite Service

None.

### 5.1.10.6 Product Manuals

Form Number	Publication Title
G110-4514-02	Program Directory for Device Support Facilities (ICKDSF)
GC26-3946-21	Device Support Facilities Release 17 System Control Program Specifications
GC35-0033-24	Device Support Facilities User's Guide and Reference Release 17

### 5.1.10.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

ICKDSF is in VMSES/E format and cannot be installed using INSTFPP.

Refer to the *Program Directory for Device Support Facilities (ICKDSF)* in chapter 6.0 entitled "Installation Instructions" for the steps to install ICKDSF using VMSES/E.

Refer to the *Program Directory for Device Support Facilities (ICKDSF)* in chapter 8.0 entitled "The Stand-Alone Program" to see how to create the stand-alone ICKDSF IPL tape.

### **Important Installation Note**

PTFs UK61061, UK70218, UK70052, UK68685, UK67626, UK70553, UK71584 and UK74445 have made product enhancements or Publication Changes to the *Device Support Facilities (ICKDSF) User's Guide and Reference Release 17* (GC35-0033-39)

Please refer to the 'MEMO TO USERS' ( ':UMEMO.' ) section of the following files for information regarding these changes: 'UK61061 \$PTFPART' 'UK70218 \$PTFPART' 'UK70052 \$PTFPART' 'UK68685 \$PTFPART' 'UK67626 \$PTFPART' 'UK70553 \$PTFPART' 'UK71584 \$PTFPART' 'UK74445 \$PTFPART' These files may be found on the maintenance ID '5684042J' 2D2 disk.

### **5.1.10.8 DCSS Information**

None.

### **5.1.10.9 Verification**

To run the verification program issue:

**v5684042**

---

## **5.1.11 5684-168 GDDM/VM V3R2.0**

---

### **5.1.11.1 PUT/ESO Applied**

The product is at service level ESO0603.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **5.1.11.2 Service Excluded**

### **5.1.11.3 Pre-Requisite Service**

None.

### **5.1.11.4 Co-Requisite Service**

None.

### 5.1.11.5 If-Requisite Service

None.

### 5.1.11.6 Product Manuals

Form Number	Publication Title
GC33-0866	GDDM General Information
SC33-0875	GDDM User's Guide
SC33-0867	GDDM Base Application Programming Guide
SC33-0868	GDDM Base Application Programming Reference
SC33-0870	GDDM Diagnosis
SC33-0869	GDDM Messages
SC33-0871	GDDM System Customization and Administration
SC33-0920	GDDM Using the Image Symbol Editor
GC33-0876	GDDM Series Licensed Program Specifications
GC33-1802	Program Directory for GDDM/VM
LY33-6080	How to activate GDDM-REXX

### 5.1.11.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the

IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

#### **Installation Guidelines**

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements" on page 201.

#### **Installing Licensed Products Utilizing Product Envelopes**

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

## IMPORTANT NOTE

The Program Directory for GDDM/VM Section 6.13 mistates when to Update the Build Status Table. This needs to be done BEFORE Section 6.12: Place GDDM into Production

You will need to run it after the following sections:

1. 6.5 Install GDDM/VM using the VMFINS EXEC, Step 4
2. 6.7 Install GDDM-PGF using the VMFINS EXEC, Step 4
3. 6.8 Install GDDM-IMD using the VMFINS EXEC, Step 4
4. 6.9 Install GDDM-IVU using the VMFINS EXEC, Step 4

You can use the tables listed in Section 6.13 for reference as to what the syntax of the VMFINS command should be.

GDDM is in VMSES/E format and cannot be installed using INSTFPP. Refer to the *Program Directory for GDDM/VM*, Chapter 6.0, "Installation Instructions", for the steps to install GDDM using VMSES/E.

GDDM-PCLK and GDDM-OS/2 Link are shipped as part of GDDM/VM. If you want to make them available to your systems, refer to *GDDM System Customization and Administration (SC33-0871)*.

GDDM-REXX is also shipped as part of GDDM/VM. To activate GDDM-REXX refer to *How to activate GDDM-REXX (LY33-6080)*. To save the DCSS for GDDM-REXX see instructions in the "DCSS Information" section of this document.

Refer to *GDDM System Customization and Administration* to customize GDDM/VM.

Refer to the *Program Directory for GDDM/VM*, Chapter 7.0 "Service Instructions", for information on applying service to GDDM using VMSES/E.

### 5.1.11.8 DCSS Information

Refer to "Using GDDM saved segments" section of the *GDDM/VM Version 3 Program Directory*

Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" on page 211 for more information.

### 5.1.11.9 Verification

The verification will be run automatically at the end of the **vmfins build** step if you have GDDM/VM US English National Language Support installed or have a GDDM user default specification for NATLANG telling GDDM to use a different language. Consult the *Program Directory for GDDM/VM*, **Chapter 9.0 "Testing GDDM Installation"**, for instructions to run the verification separately. Note that step 4 of the



**Testing GDDM/VM Base** section documents a process for setting the User Control Key to something other than the default of PA3. This may be necessary if the keyboard does not have a PA3 key, or if the PA3 key is already used by another application. If it is necessary to follow this step, you can facilitate this by creating a **PROFILE ADMDEFS** file, if one does not already exist. Then insert the following line into that file as indicated, making sure that there is a space in col 1. This line is an example of how to define the PF1 key to function as the User Control Key:

```
ADMNICK FAM=1, PROCOPT=((CTLKEY,1,1))
```

## 5.1.12 5695-013 REXX/370 COMPILER V1R4.0

### 5.1.12.1 PUT/ESO Applied

The product is at service level ESO0507.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

---

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 5.1.12.2 Service Excluded

None.

### 5.1.12.3 Pre-Requisite Service

None.

### 5.1.12.4 Co-Requisite Service

None.

### 5.1.12.5 If-Requisite Service

None.

### 5.1.12.6 Product Manuals

Form Number	Publication Title
SH19-8160	IBM Compiler and Library for REXX on zSeries User's Guide and Reference Version 1 Release 4
SH19-8179	IBM Compiler and Library for REXX on zSeries Diagnosis Guide Version 1 Release 4

### 5.1.12.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

For installation instructions, please refer to chapter 6 of the *Program Directory for IBM COMPILER for REXX on zSeries*.

### 5.1.12.8 DCSS Information

None.

### 5.1.12.9 Verification

Verification could be started automatically by the installation exec or manually by entering:

**v5695013**

## 5.1.13 5695-013 REXX/370 COMPILER KANJI V1R4.0

### 5.1.13.1 PUT/ESO Applied

The product is at service level ESO0404.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional*

*Licensed Product Service* section on the *z/VM SDO V6* webpage.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

### **DASD Storage Requirements And User ID Definitions**

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the *z/VM* Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO* webpage.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6* webpage.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

#### **5.1.13.2 Service Excluded**

None.

#### **5.1.13.3 Pre-Requisite Service**

None.

#### **5.1.13.4 Co-Requisite Service**

None

#### **5.1.13.5 If Requisite Service**

Form Number	Publication Title
GI19-0029	Program Directory for IBM Compiler for REXX on zSeries Release 4.0

None

### 5.1.13.6 Product Manuals

### 5.1.13.7 Installation

With z/VM 6.2 a number of changes were introduced in the System Maintenance and Service Environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI Ready or SSI Enabled) Chapter 28. *Converting a z/VM System to a Single Member z/VM SSI Cluster and Chapter 25 Setting up z/VM Single System Image Clusters in the z/VM CP Planning and Administration manual should be reviewed.*

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in *Chapter 2 System Changes in the z/VM Migration Guide.*

*Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and production enablement of Licensed Program Products.* This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### Installation Guidelines

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, “DASD Requirements” on pag.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (PLAN NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (NOMEMO NOLINK ENV envelope\_filename**

For installation instructions, please refer to Appendix A. 'Install NLS Japanese (Kanji) Feature with VMSES/E in the *Program Directory for IBM COMPILER for REXX on zSeries*.

- **Note:**

1. The Program Directory indicates that 'the Japanese (Kanji) feature is located on the REXX Compiler base tape.' Since the time that this was written, IBM has changed the procedure utilized to create Product Tapes. Please check the documentation provided with your order to determine which tape contains the Japanese feature.
2. Step 3 'Install the Japanese feature' is missing several of the steps required to load the REXX Compiler Japanese Feature control files to the 51D disk. The following steps must be executed to load the Japanese Feature:

**vmfins install info (nomemo**

**vmfins install ppf 5695013J {rexxc|rexxcsfs}(plan nomemo**

**vmfins install ppf 5695013J {rexxc|rexxcsfs}(nomemo nolink**

**vmfins build ppf 5695013J {rexxc|rexxcsfs}(serviced nolink**

- Use **rexxc** if installing using minidisks or
- Use **rexxcsfs** if installing using SFS

#### 5.1.13.8 DCSS Information

None.

#### 5.1.13.9 Verification

There is no verification routine for the Japanese Feature of the REXX Compiler.

### 5.1.14 5695-014 REXX/370 LIBRARY V1R4.0

#### 5.1.14.1 PUT/ESO Applied

The product is at service level ESO0505.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

#### 5.1.14.2 Service Excluded

None.

#### 5.1.14.3 Pre-Requisite Service

None.

#### 5.1.14.4 Co-Requisite Service

None.

#### 5.1.14.5 If-Requisite Service

None.

#### 5.1.14.6 Product Manuals

Form Number	Publication Title
SH19-8179	IBM Compiler and Library for REXX on zSeries Diagnosis Guide Version 1 Release 4
SH19-8160	IBM Compiler and Library for REXX on zSeries Users Guide and Reference Version 1 Release 4
GI19-0027	Program Directory for IBM Library for REXX on zSeries Release 4.0

#### 5.1.14.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### DASD Storage Requirements And User ID Definitions

System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

#### **Installation Guidelines**

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements" on page 201.

#### **Installing Licensed Products Utilizing Product Envelopes**

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

For installation instructions, please refer to Chapter 6 of the *Program Directory for IBM Library for REXX on z/Series*.

### 5.1.14.8 DCSS Information

Please note if you are going to utilize the REXX Library segment, the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" on page 211 for more information.

If the REXX Library segment is defined in the range 20000-3FFFF, the z/VM 6.1 SAMPI VM Guard Server, VSMGUARD, will fail initialization with:

```
DMSITP143T Data exception occurred at B2D00002 in system routine  
DMSRTPRC; re-IPL CMS
```

in a call to routine DMSSIDM from the exec DMSWSSMI. The error is the result of the EAGRTSEG REXX Library Segment being overlaid by the SMAPI VM Guard Server Segment VSMDCSS.

When creating the REXX Library segment, be sure that your machine's virtual storage is sufficient. For the SDO recommended segment range, your machine's virtual storage size should be 2048M.

For additional information on the REXX Library segment, please refer to the section Define and Build the REXX Library Saved Segment of the *IBM Library for REXX on z/Series Program Directory*.

### 5.1.14.9 Verification

Verification could be started automatically by the installation exec or manually by entering:

**v5695014**

## 5.1.15 5695-014 REXX/370 LIBRARY KANJI V1R4.0

### 5.1.15.1 PUT/ESO Applied

The product is at service level ESO0404.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.



### 5.1.15.2 Service Excluded

None.

### 5.1.15.3 Pre-Requisite Service

None.

### 5.1.15.4 Co-Requisite Service

None.

### 5.1.15.5 If-Requisite Service

None.

### 5.1.15.6 Product Manuals

Form Number	Publication Title
GI19-0027	Program Directory for IBM Library for REXX on zSeries Release 4.0

### 5.1.15.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

#### **Installation Guidelines**

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

#### **Installing Licensed Products Utilizing Product Envelopes**

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

### Important Note for Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

For installation instructions, please refer to Appendix B. 'Install NLS Japanese (Kanji) Feature with VMSES/E in the *Program Directory for IBM LIBRARY for REXX on zSeries*.

- **Note:**

1. The Program Directory indicates that 'the Japanese (Kanji) feature is located on the REXX Library base tape.' Since the time that this was written, IBM has changed the procedure utilized to create Product Tapes. Please check the documentation provided with your order to determine which tape contains the Japanese feature.
2. Step 3 'Install the Japanese feature' is missing several of the steps required to load the REXX Library Japanese Feature control files to the 51D disk. The following steps must be executed to load the Japanese Feature:

**vmfins install info (nomemo**

**vmfins install ppf 5695014J {rexxl|rexxlsfs}(plan nomemo**

**vmfins install ppf 5695014J {rexxl|rexxlsfs}(nomemo nolink**

**vmfins build ppf 5695014J {rexxl|rexxlsfs}(serviced nolink**

- Use **rexxl** if installing using minidisks or
- Use **rexxlsfs** if installing using SFS

### 5.1.15.8 DCSS Information

None.

### 5.1.15.9 Verification

There is no verification routine for the Japanese Feature of the REXX Library.

### 5.1.16 5696-234 HLASM V1R6.0

### 5.1.16.1 PUT/ESO Applied

The product is at service level ESO1201.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 5.1.16.2 Service Excluded

### 5.1.16.3 Pre-Requisite Service

None.

---

### 5.1.16.4 Co-Requisite Service

None.

### 5.1.16.5 If-Requisite Service

None.

### 5.1.16.6 Product Manuals

Form Number	Publication Title
GC26-4944	High Level Assembler for z/OS & z/VM & z/VSE Licensed Program Specifications
SC26-3494	High Level Assembler for z/OS & z/VM & z/VSE Installation and Customization Guide Release 6
SC26-4940	High Level Assembler for z/OS & z/VM & z/VSE Language Reference
SC26-4941	High Level Assembler for z/OS & z/VM & z/VSE Programmers Guide
GC26-4943	High Level Assembler for z/OS & z/VM & z/VSE General Information

## 5.1.16.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

See the IBM HLASM Installation and Customization Guide for installation instructions.

IBM High Level Assembler V1R6.0 is VMSES/E enabled and must be installed using VMFINS. VMFINS is an installation aid supplied as part of VMSES/E to make installation of VM and LPs consistent.

### Important Installation Note

The 'HLASM Installation and Customization Guide' Release 6 indicates that the name of the HLASM PPF file is 'P696234J'. This is incorrect, the PPF file name is '5696234J'.

The installation and tailoring of IBM High Level Assembler V1R6.0 is documented in the *IBM HLASM Installation and Customization Guide*. You **must** have a copy of this manual to properly install and customize the High Level Assembler.

The *IBM HLASM Installation and Customization Guide* can be found on the following web page:

<http://www.ibm.com/software/awdtools/hlasm/>

**Click on Product Library**

**Installation and Customization Guide (SC26-3494)**

**Click on either View in PDF or BookServer format.**

Additional information on the installation, customization and servicing of High Level Assembler may be found in the following chapters of the *IBM HLASM Installation and Customization Guide*:

- Installation: Chapter 8, "Installing High Level Assembler on VM"
- Customization: Chapter 9, "Customizing High Level Assembler on VM"
- Service: Chapter 10, "Maintaining High Level Assembler on VM"

#### **Important Installation Note**

PTF UK15391 made a Publication Change (DEVCHG) to *High Level Assembler for MVS & VM & VSE Installation and Customization Guide Release 5 (SC26-3494)* Chapter 8, Installing High Level Assembler on VM. However, the DEVCHNG was never incorporated and it is not reflected in the new *High Level Assembler for MVS & VM & VSE Installation and Customization Guide Release 6 (SC26-3494-04)*.

As a result, the following information is missing:

If you are to run the HLASM toolkit with the assembler in a saved segment, then use VMFCOPY to copy ASMADOP MODULE to the Y disk.

PTF UK59302 modified High Level Assembler (HLASM) to support D/T2917. The addition of this support resulted in changes (DEVCHNG) to the HLASM publications. Please refer to the ':UMEMO.' section of the 'UK59302 \$PTFPART' file for information on the DEVCHNG. The 'UK59302 \$PTFPART' file may be found on the maintenance ID 'P696234J' 2D2 disk.

For more information on servicing IBM High Level Assembler using VMSES/E refer to *VMSES/E Introduction and Reference*.

#### **5.1.16.8 DCSS Information**

Refer to Part 2, Chapter 8, Step 5 "Define and Build High Level Assembler Saved Segment" of the *Installation and Customization Guide* for HLASM V1R6. for complete instructions. Please note that the

segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" on page 211 for more information.

### **5.1.16.9 Verification**

See the IBM HLASM Installation and Customization Guide for verification instructions.

When the command is issued to update the VMSES/E Build Status Table for IBM High Level Assembler, VMSES/E also executes the verification EXEC, V5696234. The procedure for updating the build status table is outlined in Step 4: "Verify the Installation in a Test Environment" in Chapter 8. "Installing High Level Assembler on VM" of the *IBM HLASM Installation and Customization Guide*.

## **5.1.17 5696-234 HLASM TOOLKIT V1R6.0**

### **5.1.17.1 PUT/ESO Applied**

The product is at service level ESO1112.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **5.1.17.2 Service Excluded**

### **5.1.17.3 Pre-Requisite Service**

None.

### **5.1.17.4 Co-Requisite Service**

None.

### **5.1.17.5 If-Requisite Service**

None.

### 5.1.17.6 Product Manuals

Form Number	Publication Title
GC26-4944	High Level Assembler for z/OS & z/VM & z/VSE Licensed Program Specifications
GC26-8711	High Level Assembler for z/OS & z/VM & z/VSE Toolkit Feature Installation and Customization Guide Release 6
GC26-8709	High Level Assembler for z/OS & z/VM & z/VSE Toolkit Feature Interactive Debug Facility User's Guide Release 6
GC26-8710	High Level Assembler for z/OS & z/VM & z/VSE Toolkit Feature User's Guide Release 6
GC26-8712	High Level Assembler for z/OS & z/VM & z/VSE IDF Reference Summary Release 6

### 5.1.17.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

---

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed

### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.



The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### **Installation Guidelines**

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

### **Installing Licensed Products Utilizing Product Envelopes**

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

See the High Level Assembler Toolkit Feature Installation and Customization Guide for installation instructions.

IBM High Level Assembler Toolkit Feature is VMSES/E enabled and must be installed using VMFINS.

### Important Installation Note

The 'High Level Assembler for z/OS & z/VM & z/VSE Toolkit Feature Installation and Customization Guide' Release 6 (GC26-8711-08) indicates that the name of the HLASM Toolkit PPF file is 'P696234K'. This is incorrect, the PPF file name is '5696234K'.

The installation and tailoring of IBM High Level Assembler Toolkit Feature is documented in the *High Level Assembler Toolkit Feature Installation and Customization Guide*. You **must** have a copy of this manual to properly install and customize the High Level Assembler Toolkit Feature.

The *IBM High Level Assembler Toolkit Feature Installation and Customization Guide* can be found on the following web page:

<http://www.ibm.com/software/awdtools/hlasm/>

**Click on Product Library**

**Installation and Customization Guide (SC26-3494)**

**Click on either View in PDF or BookServer format.**

Additional information on the installation, customization and servicing of HLASM Toolkit may be found in the following chapters of the *IBM Toolkit Installation and Customization Guide*:

#### 5.1.17.8 DCSS Information

The HLASM ToolKit Feature does not have any segments.

#### 5.1.17.9 Verification

See the IBM High Level Assembler Toolkit Feature Installation and Customization Guide for verification instructions.

Chapter 5 step 4 describes the verification test. You need to run T5696234 exec and reproduce the output shown in the *IBM High Level Assembler Toolkit Installation and Customization Guide*.

NOTE: If HLASM has been loaded into a shared segment and with no links to the HLASM mini disks, the invoking of HLASM returns RC=20. The NOSEG option has been removed from the IVP exec T5696234 invocation of HLASM. If HLASM has been loaded into a shared segment, then HLASM will be found and assembly of IVP sample program will work.

### 5.1.18 5697-F42 DB2 SERVER FOR VM V7R5.0

#### 5.1.18.1 PUT/ESO Applied

The product is at service level ESO1201.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 5.1.18.2 Service Excluded

### 5.1.18.3 Pre-Requisite Service

### 5.1.18.4 Co-Requisite Service

None.

### 5.1.18.5 If-Requisite Service

None.

### 5.1.18.6 Product Manuals

Form Number	Publication Title
GC09-2659	DB2 Server for VSE & VM Licensed Program Specifications
GC09-2984	DB2 Server for VM Messages and Codes
GC09-2987	DB2 Server for VSE & VM Performance Tuning Handbook
GC09-2995	DB2 Server for VSE & VM Overview
LC09-2907	DB2 Server for VM Diagnosis Guide and Reference
SC09-2888	DB2 Server for VSE & VM Database Administration
SC09-2889	DB2 Server for VSE & VM Application Programming
SC09-2890	DB2 Server for VSE & VM Master Index and Glossary
SC09-2980	DB2 Server for VM System Administration
SC09-2983	DB2 Server for VSE & VM Database Services Utility
SC09-2986	DB2 Server for VSE & VM Operation
SC09-2988	DB2 Server for VSE & VM Quick Reference
SC09-2989	DB2 Server for VSE & VM SQL Reference
SC09-2990	DB2 Server for VSE & VM Interactive SQL Guide and Reference
GI10-4998	Program Directory for IBM DATABASE 2 SERVER FOR VM Version 7 Release 5 Modification Level 0

### 5.1.18.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” on page 219 contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (PLAN NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (NOMEMO NOLINK ENV envelope\_filename**

### IMPORTANT NOTE REGARDING THIS SERVICE

There is subsequent DB2 Server for VM service processing required due to the service that has been applied. DB2 Server for VM DBS Utility load module (object ARISLKUC.UTILITY) had service applied.

Link-edit all user programs that include the DBS Utility according to instructions in the *DB2 Server for VM Database Services Utility manual*.

### IMPORTANT NOTE

Please review the PSP Bucket for latest updates prior to installing this feature. The PSP Bucket in RETAIN Upgrade: DB2VSEVM750 Subset: DB2/750 will be updated with any documentation updates.

**Note:** Items 1 and 3 that are listed under the **SECTION 3. GENERAL INFORMATION** have already been incorporated in this delivery, so **DO NOT** execute these steps or you may backlevel the code if any of mentioned files have been serviced.

For installation instructions and details, please refer to the Installing DB2 for VM section in the *Program Directory for IBM DATABASE 2 Server for VM Version 7 Release 5 Modification Level 0*.

The DB2<sup>®</sup> management system you will install, following the install instructions, does not support the distributed relational database architecture (DRDA<sup>®</sup>), nor VMDSS. However, you can install the additional code required for these facilities after installation. For DRDA, please reference the instructions in the *The DB2 Server for VM System Administration* manual.

If you plan to use VM DB2 Data Spaces Support (VMDSS) please review “Chapter 6” in the *DB2 Server for VSE & VM Performance Tuning Handbook* manual.

### 5.1.18.8 DCSS Information

Refer to the Saved Segment section of the *DB2 Server for VM System Administration* manual for details

on Saving Segments. Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" for more information.

### **5.1.18.9 Verification**

For instructions on verifying DB2, please refer to the "Section for Installation Verification" in the *Program Directory for IBM DATABASE 2 Server for VM Version 7 Release 5 Modification Level 0*.

---

## **5.1.19 5697-F42 DB2 DATA PROPAGATOR V7R4.0**

### **5.1.19.1 PUT/ESO Applied**

The product is at service level ESO0712.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **5.1.19.2 Service Excluded**

None.

### **5.1.19.3 Pre-Requisite Service**

None.

### **5.1.19.4 Co-Requisite Service**

None.

### **5.1.19.5 If-Requisite Service**

None.

### **5.1.19.6 Product Manuals**

<b>Form Number</b>	<b>Publication Title</b>
SC18-7568	IBM DB2 Information Integrator Replication and Event Publishing Guide and Reference
GI10-5000	Program Directory for IBM DB2 DataPropagator Q Capture for VM Version 7 Release 4.0

### **5.1.19.7 Installation**

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in an Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### **DASD Storage Requirements And User ID Definitions**

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO V6 webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### Installation Guidelines

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

### Pre-Requisite Licensed Products

**DB2 UDB Universal Database**

**MQ Series Client for VM/ESA**

### Note on Publications

The publications for DB2 DProp Q Capture for VM V7.4 are included with the pre-requisite product, DB2 UDB Universal Database. No publications are included when you order the basic materials for DB2 DProp Q Capture for VM V7.4.

For Installation instructions and details, please refer to "The Installation Instructions section" in the *Program Directory for DataPropagator Q Capture for VM Version 7 Release 4.0*. Also check the PSP Bucket in RETAIN for the latest information regarding the the installation or servicing of DB2 DataPropagator Q Capture V7R4.0

### Error Messages

During installation you may see the following error message, which the developer has determined can be ignored. Please reference the information contained in the PSP Bucket in RETAIN (Upgrade: DB2VSEVM740 Subset: DPRVM).

```
VMFSIP2500E Requisite error, missing requisite *@C0092YD* for PRODID
5697F74B%DPROPR
```

It also possible that you may see the following error messages, which result from DB2 DataPropagator Q Capture not recognizing DB2 Server for VM V7R5.0 (5697F75A) as the correct prerequisite. This can be corrected by issuing the commands that follow. Please reference the RETAIN PSP Bucket for more complete information.

```
SV:VMFSIP2500E Requisite error, missing requisite 5697F74A for PRODID
SV:          5697F74B%DPROPR
SV:VMFSIP2503E PRODID 5697F74B%DPROPR has a status of APPLIED but has
SV:          requisites that have not been APPLIED
WN:VMFREQ2806W The following requisites for product :PPF 5697F74B DPROPR
WN:          :PRODID 5697F74B%DPROPR are not satisfied:
WN:VMFREQ2806W Type          Product Component      PTF
WN:
WN:VMFREQ2806W Prerequisite 5697F74A
SV:VMFTNS2604E Product :PPF 5697F74B DPROPR :PRODID 5697F74B%DPROPR
SV:          cannot be processed because its requisites are not
SV:          satisfied
ST:VMFTNS2760I VMFTNS processing completed unsuccessfully
```

1. vmfsim modify vm sysrecs d tdata :prodid 5697F74A :PPF 5697F74A lib :stat received
2. vmfsim modify vm sysapps d tdata :prodid 5697F74A :PPF 5697F74A lib :stat applied
3. vmfsim modify vm sysreqt d tdata :prodid 5697F74A

### 5.1.19.8 DCSS Information

### 5.1.19.9 Verification

For Installation instructions and details, please refer to “The Installation Instructions section” in the *Program Directory for DataPropagator Q Capture for VM Version 7 Release 4.0*. Also check the PSP Bucket in RETAIN for the latest information regarding the installation or servicing of DB2 DataPropagator Q Capture V7R4.0

For instructions on verifying DB2 DataPropagator Q Capture, please reference “The Installation Verification section” in the *Program Directory for DataPropagator Q Capture for VM Version 7 Release 4.0*.

## 5.1.20 5697-F42 DB2 QMF V7R2.0

### 5.1.20.1 PUT/ESO Applied



The product is at service level ESO0709.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **5.1.20.2 Service Excluded**

None.

### **5.1.20.3 Pre-Requisite Service**

None.

### **5.1.20.4 Co-Requisite Service**

### **5.1.20.5 If-Requisite Service**

None.

### **5.1.20.6 Product Manuals**

<b>Form Number</b>	<b>Publication Title</b>
GC27-0720	Query Management Facility Installing and Managing QMF Version 7 Release 2
GC27-0717	Query Management Facility QMF Messages and Codes Version 7 Release 2
GC27-0714	Query Management Facility Introducing QMF Version 7 Release 2
SC27-0715	Query Management Facility QMF Reference Version 7 Release 2
SC27-0716	Query Management Facility Using QMF Version 7 Release 2
SC27-0718	Query Management Facility Developing QMF Applications Version 7
GI10-8329	Program Directory for Query Management Facility for VM/ESA Version 7 Release 2.0

### **5.1.20.7 Installation**

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in an Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

## **DASD Storage Requirements And User ID Definitions**

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### **Installation Guidelines**

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, “DASD Requirements” on page 201.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (PLAN NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (NOMEMO NOLINK ENV envelope\_filename**

For installation instructions and details, please refer to the "Installation Instructions" section of the *Program Directory for Query Management Facility Version 7 Release 2.0*.

NOTE: The P697F4BA 2D2 disk has increased to 1620 4K blocks. (9 cylinders of 3380 DASD or 8 cylinders of 3390 DASD.)

NOTE: Refer to the **Memo To Users** section of the UQ83930 \$PTFPART file on the P697F4BA 2D2 disk for important USER information regarding service that has been applied.

### Error Messages

During installation you may see the following error messages, which results from DB2 QMF not recognizing DB2 Server for VM V7R5.0 (5697F75A) as the correct prerequisite. This can be corrected by issuing the commands that follow. Please reference the RETAIN PSP Bucket for more complete information.

```
SV:VMFSIP2500E Requisite error, missing requisite 5697F74A for PRODID
SV:          5697F4BA%QMF
SV:VMFSIP2503E PRODID 5697F4BA%QMF has a status of APPLIED but has
SV:          requisites that have not been APPLIED
WN:VMFREQ2806W The following requisites for product :PPF 5697F74B DPROPR
WN:          :PRODID 5697F4BA%QMF are not satisfied:
WN:VMFREQ2806W Type          Product Component          PTF
WN:
WN:VMFREQ2806W Prerequisite 5697F74A
SV:VMFINS2604E Product :PPF 5697F4BA QMF :PRODID 5697F4BA%QMF
SV:          cannot be processed because its requisites are not
SV:          satisfied
ST:VMFINS2760I VMFINS processing completed unsuccessfully
```

1. vmfsim modify vm sysrecs d tdata :prodid 5697F74A :PPF 5697F74A lib :stat received
2. vmfsim modify vm sysapps d tdata :prodid 5697F74A :PPF 5697F74A lib :stat applied
3. vmfsim modify vm sysreqt d tdata :prodid 5697F74A

### 5.1.20.8 DCSS Information

For segment build instructions and details, please refer to the “Place QMF Into Production” section of the *Program Directory for Query Management Facility Version 7 Release 2.0*. Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, “Saved Segments” on page 211 for more information.

#### Important Note for Saving QMF Segment

Step 6.5.1.8 **Prepare to build segments.** of the *Program Directory for Query Management Facility Version 7 Release 2.0*. needs to be updated with the following:

Virtual Storage Needs to be set to **999M**.

Change the GDM Link statement in substep D. to read: **link p68416b 29e 194 rr**

### 5.1.20.9 Verification

For instructions on verifying QMF, please refer to the *Installing and Managing QMF on VM/ESA* manual.

## 5.1.21 5697-F42 DB2 CLIENT FOR VM

### V7R5.05.1.21.1 PUT/ESO Applied

The product is at service level ESO1201.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

#### 5.1.21.2 Service Excluded

None.

#### 5.1.21.3 Pre-Requisite Service

None.

#### 5.1.21.4 Co-Requisite Service

None.

### 5.1.21.5 If-Requisite Service

None.

### 5.1.21.6 Product Manuals

Form Number	Publication Title
GC09-2659	DB2 Server for VSE & VM Licensed Program Specifications
GC09-2984	DB2 Server for VM Messages and Codes
GC09-2987	DB2 Server for VSE & VM Performance Tuning Handbook
GC09-2995	DB2 Server for VSE & VM Overview

Form Number	Publication Title
LC09-2907	DB2 Server for VM Diagnosis Guide and Reference
SC09-2888	DB2 Server for VSE & VM Database Administration
SC09-2889	DB2 Server for VSE & VM Application Programming
SC09-2890	DB2 Server for VSE & VM Master Index and Glossary
SC09-2980	DB2 Server for VM System Administration
SC09-2983	DB2 Server for VSE & VM Database Services Utility
SC09-2986	DB2 Server for VSE & VM Operation
SC09-2988	DB2 Server for VSE & VM Quick Reference
SC09-2989	DB2 Server for VSE & VM SQL Reference
SC09-2990	DB2 Server for VSE & VM Interactive SQL Guide and Reference
GI11-8336	Program Directory for IBM DB2 SERVER FOR VM CLIENT EDITION Version 7 Release 5 Modification Level 0

### 5.1.21.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in an Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (PLAN NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (NOMEMO NOLINK ENV envelope\_filename**

### IMPORTANT NOTE REGARDING THIS SERVICE

There is subsequent DB2 Server for VM service processing required due to the service that has been applied. DB2 Server for VM DBS Utility load module (object ARISLKUC.UTILITY) had service applied.

Link-edit all user programs that include the DBS Utility according to instructions in the *DB2 Server for VM Database Services Utility manual*.

### IMPORTANT NOTE

Please review the PSP Bucket for latest updates prior to installing this feature. The PSP Bucket in RETAIN Upgrade: DB2VSEVM750 Subset: DB2750C will be updated with any documentation updates.

**Note:** Item 2 (APAR PK68794) that is listed under the **SECTION 3. GENERAL INFORMATION** has already been incorporated in this delivery, so **DO NOT** execute this step or you may backlevel the code if any of mentioned files have been serviced.

For installation instructions and details, please refer to the Installing DB2 for VM Client Edition section in the *Program Directory for IBM DATABASE 2 Server for VM Client Edition Version 7 Release 5 Modification Level 0*.

The DB2 management system you will install, following the install instructions, does not support the distributed relational database architecture (DRDA). You can install the additional DRDA code required for these facilities after installation, by following the instructions in the *The DB2 Server for VM System Administration* manual.

### Documentation Updates for The DB2 Server for VM System Administration manual.

Refer to APAR PK79201 for important Document updates to the *DB2 Server for VM System Administration* manual. regarding DRDA code.

### 5.1.21.8 DCSS Information

Refer to the Saved Segment section of the *DB2 Server for VM System Administration* manual for details on Saving Segments. Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" on for more information.

### 5.1.21.9 Verification

For instructions on verifying DB2, please refer to the “Section for Installation Verification” in the *Program Directory for IBM DATABASE 2 Server for VM Client Edition Version 7 Release 5 Modification Level 0*.

### **5.1.22 5697-J05 ARCHIVE MANAGER FOR Z/VM**

For installation, service and product requirements please refer to the *Archive Manager for z/VM Program Directory* (GI10-8661).

### **5.1.23 5697-J06 BACKUP AND RESTORE MANAGER FOR Z/VM**

For installation, service and product requirements please refer to the *Backup and Restore Manager for z/VM Program Directory* (GI10-8662).

### **5.1.24 5697-J08 TAPE MANAGER FOR Z/VM**

For installation, service and product requirements, please refer to the *Tape Manager for z/VM Program Directory* (GI10-8660).

### **5.1.25 5697-J10 OPERATIONS MANAGER FOR Z/VM**

For installation, service and product requirements please refer to the *Operations Manager for z/VM Program Directory* (GI10-8664).

### **5.1.26 5698-A36 IBM TIVOLI OMEGAMON XE ON Z/VM V4R3.0**

#### **5.1.26.1 PUT/ESO Applied**

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

#### **5.1.26.2 Service Excluded**

None.

#### **5.1.26.3 Pre-Requisite Service**

None.

#### 5.1.26.4 Co-Requisite Service

None.

#### 5.1.26.5 If-Requisite Service

None.

#### 5.1.26.6 Product Manuals

Form Number	Publication Title
GC27-2838	IBM Tivoli OMEGAMON XE on z/VM and Linux Troubleshooting Guide Version 4.3.0
GI11-9441	IBM Tivoli OMEGAMON XE on z/VM and Linux Quick Start Guide Version 4.3.0
SC27-2836	IBM Tivoli OMEGAMON XE on z/VM and Linux User's Guide Version 4.3.0
SC27-2837	IBM Tivoli OMEGAMON XE on z/VM and Linux Planning and Configuration Guide Version 4.3.0
GI11-4135	Program Directory for IBM Tivoli OMEGAMON XE on z/VM and Linux version 4 release 3.0

#### 5.1.26.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in an Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

##### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO NOLINK ENV *envelope\_filename***

#### 5.1.26.8 Packaging of IBM Tivoli OMEGAMON XE on z/VM and Linux

IBM Tivoli OMEGAMON XE on z/VM and Linux consists of three (3) components as follows which execute both under z/VM and Linux:



## 1. z/VM Performance Toolkit Component

- This part consists of a new level of the z/VM Performance Toolkit containing extensions that allow it to gather data and place it in a DCSS where it can be retrieved by the Tivoli OMEGAMON XE on z/VM and Linux, Linux Agent. It also contains a tool to help you analyze your installation and decide how large of a DCSS you will need for your performance data. This piece is delivered as part of the z/VM operating system. Depending on your version of z/VM it may be necessary to install service to receive this support.

### – NOTE:

z/VM Performance Toolkit is an optional z/VM feature which is delivered on the z/VM DDR in a 'DISABLED' state. In order to utilize IBM Tivoli OMEGAMON XE on z/VM and Linux, the following z/VM Performance Toolkit requirements must be met:

- License obtained.
  - 'ENABLED' on the z/VM System that IBM Tivoli OMEGAMON XE on z/VM and Linux will be utilized on.
  - Upgraded to include the service that contains the modifications that allows Toolkit to gather data required by OMEGAMON<sup>®</sup> and place the data where it can be retrieved by the OMEGAMON Linux Agent.
- For additional information on the z/VM Performance Toolkit and the service that is required to support OMEGAMON, please refer to the following website:

<http://www.vm.ibm.com/related/perfkit/>

## 2. Linux Agent

- This is the z/VM agent that runs on a Linux guest. It will take the data gathered by the Tivoli OMEGAMON XE on z/VM and Linux, Performance Toolkit Extensions and deliver it to the Tivoli Enterprise Management Server (TEMS). It is delivered on a CD which also contains seeding files for the TEMS, the Tivoli Enterprise Portal Server (TEPS) and the Tivoli Enterprise Portal (TEP). For instructions on installing and servicing this piece, see the *IBM Tivoli OMEGAMON XE on z/VM and Linux: Planning and Configuration Guide*. Note: If you have not previously installed IBM Tivoli Monitoring Services at your installation, there are CDs containing the product and documentation included in this package.

## 3. Command Processor

- This is the Command Processor portion of the product. It is installed and runs on your z/VM system.

The Command Processor Component is designed to allow action to be taken on the commands sent from the Linux Agent. The Command Process executes under z/VM.

This Service Delivery Offering (SDO) Program Directory and the *Program Directory for IBM Tivoli OMEGAMON XE on z/VM and Linux Version 4 Release 3.0*. are designed to provide the information required to install the **Command Processor Component** of the IBM Tivoli OMEGAMON XE on z/VM and Linux Product on your z/VM System.

### 5.1.26.9 Installation Instructions for OMEGAMON Command Processor Component

For installation instructions for IBM Tivoli OMEGAMON XE on z/VM and Linux please refer to the '6.0 Installation Instructions' Section in the *Program Directory for IBM Tivoli OMEGAMON XE on z/VM and*

*Linux Version 4 Release 3.0.*

**Note:** Other Program Product Requirements

The following program products are required to run Tivoli OMEGAMON XE on z/VM and Linux:

1. IBM Tivoli OMEGAMON XE on z/VM and Linux Tivoli Enterprise Portal Agent (includes seeding) LCD7-0982-06.
2. One of the following:
  - SUSE Linux Enterprise Server 9 for zSeries, 31-bit or 64-bit mode. Must be SP3 or above.
  - SUSE Linux Enterprise Server 10 for zSeries.
  - RedHat Enterprise Linux version 4 Update 5 or above

### **5.1.26.10 DCSS Information**

None.

### **5.1.26.11 Verification**

There is no verification program for IBM Tivoli OMEGAMON XE on z/VM and Linux.

---

## **5.1.27 5741-A07 DFSMS/VM V2R2.1**

---

### **5.1.27.1 PUT/ESO Applied**

The product is at service level ESO1006.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **5.1.27.2 Service Excluded**

None.

### **5.1.27.3 Pre-Requisite Service**

None.

### **5.1.27.4 Co-Requisite Service**

None.

### 5.1.27.5 If-Requisite Service

None.

### 5.1.27.6 Product Manuals

Form Number	Publication Title
SC24-6049	z/VM: DFSMS/VM Function Level 221 Planning Guide
SC24-6047	z/VM: DFSMS/VM Function Level 221 Customization
SC24-6051	z/VM: DFSMS/VM Function Level 221 Storage Administration Guide and Reference
GC24-6048	z/VM: DFSMS/VM Function Level 221 Messages and Codes
SC24-6050	z/VM: DFSMS/VM Function Level 221 Removable Media Services
GC24-6046	z/VM: DFSMS/VM Function Level 221 Diagnosis Guide

### 5.1.27.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in an Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional*

Licensed Products VM Directory section on the z/VM SDO webpage.

This webpage may be found off the VM System Delivery Offering (SDO) website at url: <http://www.vm.ibm.com/sdo/>

### Installation Guidelines

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (PLAN NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (NOMEMO NOLINK ENV envelope\_filename**

For installation instructions, please refer to chapter 6 of the *Program Directory for DFSMS/VM*.

When you get to the part where you build the DFSMSSEG segment, you will need to do the following commands first:

When you get to the part where you build the DFSMSSEG segment, you will need to update the FSMSEGDF EXEC file on the DFSMS 1B5 mdisk. The segment location should be changed because it conflicts with the INSTSEG segment. You will want to change the line that reads:

```
seg_address = '1400-14FF'          /* address of DFSMS segment */
```

to something like this:

```
seg_address = '2200-22FF'          /* address of DFSMS segment */
```

You will get an error when running FSMSEGDF if you do not make this change to the FSMSEGDF EXEC

first.

Refer to chapter 6 of the *Program Directory for DFSMS/VM* in section 6.6.2 step number 13 "Update the ISMF EXEC". It explains how to update the ISMF EXEC. You want to change this file to show that the PDF code is installed on the ISPVM 192 disk. You want to change the line from:

```
separate_pdf_disk = 'YES';           /* PDF available    ~/
```

to:

```
separate_pdf_disk = 'NO';           /* PDF available    ~/
```

Refer to the *Program Directory for DFSMS/VM* in the chapter entitled "Installation Requirements and Considerations" in the section titled "Migrating from Previous Releases of DFSMS/VM to Function Level 221" for information on migration considerations.

### 5.1.27.8 DCSS Information

The steps to create the DFSMS segment are described in: *z/VM DFSMS/VM Function Level 221 Customization*

Refer to Define the DFSMS/VM Saved Segment for Space Management step in the DFSMS/VM Tailoring section of the *Program Directory for DFSMS/VM*, in the chapter entitled "Installation Instructions". Please note that the segment range should be based on the segment layout as defined in the SDO Program Directory. See Appendix D, "Saved Segments" for more information.

### 5.1.27.9 Verification

Refer to the *z/VM DFSMS/VM Function Level 221 Customization* in the chapter entitled "Verifying the Installation Process" for information on verifying DFSMS.

## 5.1.28 5741-A07 DFSMS/VM KANJI V2R2.1

### 5.1.28.1 PUT/ESO Applied

The product is at service level ESO1003.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 5.1.28.2 Service Excluded

None.

---

### 5.1.28.3 Pre-Requisite Service

None.

### 5.1.28.4 Co-Requisite Service

None.

### 5.1.28.5 If-Requisite Service

None.

### 5.1.28.6 Product Manuals

Form Number	Publication Title
SC24-6049	z/VM: DFSMS/VM Function Level 221 Planning Guide
GC24-6047	z/VM: DFSMS/VM Function Level 221 Customization
SC24-6051	z/VM: DFSMS/VM Function Level 221 Storage Administration Guide and Reference
SC24-6048	z/VM: DFSMS/VM Function Level 221 Messages and Codes
SC24-6050	z/VM: DFSMS/VM Function Level 221 Removable Media Services
GC24-6046	z/VM: DFSMS/VM Function Level 221 Diagnosis Guide

### 5.1.28.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in an Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

## **DASD Storage Requirements And User ID Definitions**

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

## **Installation Guidelines**

A standard Maintenance ID has been defined for this Licensed Program Product. However, the Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

It is recommended that the Product be installed utilizing the standard Maintenance ID defined for this Licensed Program Product.

For information on the DASD storage requirements for the installation of this Licensed Program Product, refer to Appendix C, "DASD Requirements".

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV** *envelope\_filename*

**VMFINS INSTALL PPF** *ppfname compid* **(PLAN NOMEMO ENV** *envelope\_filename*

**VMFINS INSTALL PPF** *ppfname compid* **(NOMEMO NOLINK ENV** *envelope\_filename*

The mdisks listed in the Appendix labeled DASD Requirements of this document show the size of the mdisks for DSFMS. These mdisks must be increased by the amount shown for Kanji feature mdisks.

For installation instructions, please refer to Install Japanese Language Feature section of chapter 6 of the *Program Directory for DFSMS/VM*.

#### 5.1.28.8 DCSS Information

#### 5.1.28.9 Verification

## 6.0 Semi-VMSES/E Licensed Product Technical Notes

This chapter provides technical considerations for the Semi-VMSES/E Licensed Products. After you have followed the general instructions for Semi-VMSES/E products, from 4.0, "Semi-VMSES/E Licensed Product Installation Instructions", locate the specific Licensed Product in this chapter to complete the installation. Products are ordered in this section by product number.

### NOTE

In the case of a conflict, the information provided in this SDO Program Directory and in the *z/VM SDO Enabling Aid* overrides the information provided in the Licensed Program Product's Program Directory, all *z/VM* and Licensed Program Product documents and the Licensed Program Product's *PLANINFO* file.

The SDO Program Directory and the *z/VM SDO Enabling Aid* should be utilized as the basis for the installation of the Program Product. The SDO Program Directory will refer to the Licensed Program Product Program Director and/or other *z/VM* or Licensed Program Product documents when appropriate.

### 6.1 Semi-VMSES/E Licensed Product Specific Considerations



---

## 6.1.1 5654-260 EREP V3R5.0

### 6.1.1.1 PUT/ESO Applied

The product is at service level PUT9405.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 6.1.1.2 Service Excluded

None.

---

### 6.1.1.3 Pre-Requirement Service

None.

### 6.1.1.4 Co-Requirement Service

None.

### 6.1.1.5 If-Requirement Service

None.

### 6.1.1.6 Product Manuals

Form Number	Publication Title
GI10-8140	Program Directory for use with EREP Version 3 for VM
GC35-0151	EREP User's Guide
GC35-0152	EREP Reference

### 6.1.1.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in an Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

## DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

## Installation Guidelines

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, "DASD Requirements".
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this Licensed Program Product are **not linked R/W** by any ID including the ID where this Licensed Program Product is being installed from.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO ENV *envelope\_filename***

To install this product onto a test disk issue:

**vmfins install ppf \$5654260 erep (nomemo**

To install this product onto the production disk issue:

**vmfins install ppf \$5654260 ereprd (nomemo**

To install this product into the SFS test directory issue:

**vmfins install ppf \$5654260 erepsfs (nomemo**

To install this product into the SFS production directory issue:

**vmfins install ppf \$5654260 erepsfsprd (nomemo**

If you have installed the product onto a test disk, use **VMFCOPY** to copy the files to your production disks once you have completed your testing.

#### 6.1.1.8 EREP Service Application

Corrective service for EREP will be supplied using normal service procedures, either on tape or delivered electronically.

Corrective service must be applied manually for EREP because it is not in the standard VMSES/E format. ERPTFLIB TLBXXXXX is shipped with the PTF, where XXXXX is the number of the PTF being applied. This file will replace ERPTFLIB TXTLIB on your system.

Electronic service for non-VMSES format products is delivered in one of the following formats:

NLSTxxxx.bin and NPTFxxxx.bin

- or -

order\_number.SHIPDOCN and order\_number.SHIPTFSN

The files need to be transferred to VM as BINARY FIXED 1024. DETERSE needs to be run against the electronically delivered files once they are on VM. DETERSE is on the MAINT 5E5 or 5E6 minidisk. The file type on VM must be SERVLINK.

The following steps will be performed using the tape or the service envelope file, SERVLINK, for the NPTFxxxx or SHIPTFSN file in order to apply the corrective service.

1. By default, EREP is installed on the MAINT 201 minidisk. Back up the critical EREP files before beginning any maintenance activity.

2. Scan the PTF media to identify the highest level textlib. Locate the ERPTFLIB TLBXXXXX file on the tape using the VMFPLC2 command or in the service envelope file, using the VMFPLCD command.

```
VMFPLC2 SCAN (181 DISK DATE EOT
```

```
- output will be TAPE MAP A
```

```
- or from envelope where envelope is on A-disk -
```

```
VMFPLCD SCAN ENV= envname SERVLINK A (DISK DATE EOD
```

```
- output will be DISK MAP A
```

3. XEDIT the TAPE MAP or DISK MAP file created by the SCAN and issue ALL/ERPTFLIB at the command line. Locate the file with the highest numeric suffix string in the filetype following the TLB prefix (TLBnnnnn).

4. Load the highest level ERPTFLIB TLBXXXXX file.

```
-- from tape -- VMFPLC2 REW 181
```

```
VMFPLC2 LOAD ERPTFLIB TLBnnnnn a (EOT
```

```
-- or from envelope --
```

```
VMFPLCD RST
```

```
VMFPLCD LOAD ERPTFLIB TLBnnnnn a (EOD
```

```
-- output will be the ERPTFLIB TLBXXXXX file on A disk
```

5. Copy ERPTFLIB TLBXXXXX to ERPTFLIB TXTLIB with the REPLACE option, where xxxxx is the highest level PTF number. Make sure the previous version is backed up.

```
ACCESS 201 Z
```

```
RENAME ERPTFLIB TXTLIB Z ERPTFLIB TLBOLD Z (REPLACE
```

```
COPYFILE ERPTFLIB TLBxxxxx A ERPTFLIB TXTLIB Z (REPLACE
```

This completes the application of a 'typical' VM EREP PTF. A 'typical' VM EREP PTF replaces the EREP text lib (TXTLIB). Any other files received with the ERPTFLIB should be ignored. They are included due to packaging rules within the product and operating system. They are NOT needed in order to install EREP maintenance. They are NOT needed for any other component of your system. They should be ignored and should NOT be used by you for any reason. You should manually keep track of the service applied to your system.

### 6.1.1.9 DCSS Information

None.

### 6.1.1.10 Verification

Verification can be started by entering:

```
v5654260
```

## 6.1.2 5684-043 ISPF V3R2.0

### 6.1.2.1 PUT/ESO Applied

The product is at service level PUT9404.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **6.1.2.2 Service Excluded**

None.

### **6.1.2.3 Pre-Requisite Service**

None.

### **6.1.2.4 Co-Requisite Service**

None.

### **6.1.2.5 If-Requisite Service**

None.

### **6.1.2.6 Product Manuals**

<b>Form Number</b>	<b>Publication Title</b>
GC34-4268	ISPF LICENSED PROGRAM SPECIFICATION
SC34-4273	ISPF DIALOG MANAGEMENT GUIDE AND REFERENCE
SC34-4265	ISPF DIALOG MANAGEMENT EXAMPLES
SC34-4267	ISPF DIALOG TAG LANGUAGE GUIDE AND REFERENCE
SC34-4297	ISPF AND ISPF/PDF REFERENCE SUMMARY
GC34-4261	ISPF AND ISPF/PDF GENERAL INFORMATION
SC34-4271	ISPF AND ISPF/PDF PLANNING AND CUSTOMIZING

<b>Form Number</b>	<b>Publication Title</b>
SC34-4270	ISPF AND ISPF/PDF PRIMER
SC34-4282	ISPF AND MASTER INDEX
GI11-1448	ISPF V3R2 PROGRAM DIRECTORY
GI10-8150	ISPF/PDF V3R2 PROGRAM DIRECTORY

### 6.1.2.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in an Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### Installation Guidelines

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, "DASD Requirements".
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this Licensed Program Product are **not linked R/W** by any ID including the ID where this Licensed Program Product is being installed from.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO ENV *envelope\_filename***

To install this product onto a test disk issue:

**vmfins install ppf \$5684043 ispdm (nomemo**

To install this product onto the production disk issue:

**vmfins install ppf \$5684043 ispdmprd (nomemo**

To install this product into the SFS test directory issue:

**vmfins install ppf \$5684043 ispdmsfs (nomemo**

To install this product into the SFS production directory issue:

**vmfins install ppf \$5684043 ispdmsfsprd (nomemo**

---

If you have installed the product onto a test disk, use **VMFCOPY** to copy the files to your production disks once you have completed your testing.



The ISPF/DM segment is required for the execution of ISPF/PDF. Be careful, not to delete the Production version of the ISPF/DM segment during the production segment during testing.

### Warning

The *Program Directory for ISPF/DM V3* provides sample VM Directory entries for the ISPVM virtual service machine. These entries are for VM/SP 6 and VM/XA and should not be utilized for z/VM Systems. A sample VM Directory entry for the ISPVM virtual service machine for z/VM is provided in the SDO Enabling Aid feature. Information on the SDO Enabling Aid may be found in the Section: 2.5, "Install the SDO Optional Products Enabling Aid (Optional)".

The ISPFVM virtual service machine must execute using the System/370 Architecture to support the ISPF/DM application. The System/370 Architecture is not supported under z/VM. To allow for the execution of applications that require the System/370 Architecture the 370 Accommodation Facility has been included as an integrated part of z/VM. The 370 Accommodation Facility is enabled by issuing the command 'CP SET 370ACCOM ON' prior to invoking the application.

The command 'CP SET 370ACCOM ON' has already been added to the PROFILE EXEC that is delivered on the ISPVM 191 disk. If you utilize this exec, no additional action is required. However, if you utilize another exec to start the ISPF/DM application on the ISPVM virtual service machine, the exec must be modified to include the 'CP SET 370ACCOM ON' command prior to invoking the ISPF/DM application.

### 6.1.2.8 DCSS Information

The following commands may be utilized to create the ISPF/DM segment. The commands may be issued from any ID that with the following:

1. Maximum virtual storage size of 1024M (1G)
2. CP Privilege Class 'E' (Required to create the segment)
3. Write access to the ISPF/DM Code disk (Required to load the segment)
  - For the ISPF/DM Product disks, this is the ISPVM 192.
  - For the ISPF/DM Test disks, this is the PRETEST 459.

The segment range utilized for the ISPF/DM segment should be based on the segment layout as defined in the SDO Program Directory.

- Define the virtual storage at 1024M (1G) and ensure that storage is cleared.

**def stor 1024M**

**system clear**

---

- Link and access the ISPF/DM code disk. The disk should be linked in write mode.
  - For the ISPF/DM Production disk:

**link ISPVM 192 002 MW**

**acc 002 b**

– For the ISPF/DM Test disk:

**link PRETEST 459 002 MW**

**acc 002 b**

- Define the ISPF/DM segment space

**defseg** *segmentname startaddr - endaddr SR*

**Where:**

segment name - The name of the ISPF/DM segment.

startaddr - The starting address of the segment range

endaddr - The ending address of the segment range

**Note:**

1. ISPDCSS is the default name for the ISPF/DM segment.
2. The segment range specified in the SDO Program Directory is based on only English NLS been loaded. If other Language NLS is to be included in the segment, the segment range (size) must be adjusted accordingly.

For the space required to load additional National Languages into the ISPF/DM segment, please refer to the table *ISPF DCSS Storage Requirements for National Language Files* in Section 2.4 *Step 2 - Define the ISPF DCSS Area* in the *Program Directory for ISPF/DM V3*.

- Execute the ISPSAVE exec to save the ISPF/DM segment.

**ISPSAVE** *segmentname*

**Where:**

segment name - The name of the ISPF/DM segment.

**Note:**

The ISPSAVE exec will output a series of questions regarding the size of the ISPF/DM segment and the National Languages that are to be included in the segment.

For additional information regarding the creation of the ISPF/DM segment, please see Appendix D, "Saved Segments".

### 6.1.2.9 Verification

1. Make sure the ISPVM Virtual Machine is running disconnected:

**query ispvm**

This should return:

ISPVM - DSC

2. Link and access the ISPVM 192 disk containing the ISPF/DM application code:

**link ispvm 192 192 rr**

**access 192 b**

3. Execute the ISPSTART EXEC
4. The ISPF exec has executed successfully if the master application panel is displayed.

**6.1.3 5684-123 ISPF/PDF V3R2.0****6.1.3.1 PUT/ESO Applied**

The product is at service level PUT9405.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

**6.1.3.2 Service Excluded**

None.

**6.1.3.3 Pre-Requisite Service**

Product Number	PTF	APAR	Product Description
5684-043	UM18982	VM45458	ISPF APAR
5684-043	UM16038	VM43115	ISPF APAR
5684-043	UM17561	VM44707	ISPF APAR
5748-XX9	UN04159	PL77128	SCRIPT APAR: execute SCRIPT/BOOKMASTER in ISPF/PDF

**6.1.3.4 Co-Requisite Service**

Product Number	PTF	APAR	Product Description
5684-123	UM18168	VM46996	ISPF/PDF NLS - Swiss German
5684-123	UM18424	VM47921	ISPF/PDF NLS - Swiss German
5684-123	UM19493	VM47561	ISPF/PDF NLS - Swiss German
5684-123	UM19509	VM46996	ISPF/PDF NLS - Swiss German
5684-123	UM19509	VM47574	ISPF/PDF NLS - Swiss German
5684-123	UM19510	VM47675	ISPF/PDF NLS - Swiss German
5684-123	UM19515	VM47676	ISPF/PDF NLS - Swiss German

5684-123	UM21878	VM47921	ISPF/PDF NLS - Swiss German
5684-123	UM21878	VM51918	ISPF/PDF NLS - Swiss German
5684-123	UM22584	VM53357	ISPF/PDF NLS - Swiss German
5684-123	UM22769	VM53002	ISPF/PDF NLS - Swiss German
5684-123	UM23024	VM53030	ISPF/PDF NLS - Swiss German
5684-123	UM23197	VM53876	ISPF/PDF NLS - Swiss German
5684-123	UM23669	VM53876	ISPF/PDF NLS - Swiss German
5684-123	UM23669	VM54245	ISPF/PDF NLS - Swiss German
5684-123	UM24823	VM56318	ISPF/PDF NLS - Swiss German
5684-123	UM25230	VM54518	ISPF/PDF NLS - Swiss German
5684-123	UM25939	VM57709	ISPF/PDF NLS - Swiss German
5684-123	UM26370	VM58322	ISPF/PDF NLS - Swiss German
5684-123	UM27019	VM59075	ISPF/PDF NLS - Swiss German
5684-123	UM27102	VM59240	ISPF/PDF NLS - Swiss German
5684-123	UM27655	VM60128	ISPF/PDF NLS - Swiss German
5684-123	UM28251	VM60513	ISPF/PDF NLS - Swiss German
5684-123	UM28303	VM60791	ISPF/PDF NLS - Swiss German
5684-123	UM29205	VM62060	ISPF/PDF NLS - Swiss German
5684-123	UM31095	VM63433	ISPF/PDF NLS - Swiss German
5684-123	UM18169	VM46996	ISPF/PDF NLS - Japanese
5684-123	UM18425	VM47921	ISPF/PDF NLS - Japanese
5684-123	UM19494	VM47561	ISPF/PDF NLS - Japanese
5684-123	UM19508	VM46996	ISPF/PDF NLS - Japanese
5684-123	UM19508	VM47574	ISPF/PDF NLS - Japanese

<b>Product Number</b>	<b>PTF</b>	<b>APAR</b>	<b>Product Description</b>
5684-123	UM19511	VM47675	ISPF/PDF NLS - Japanese
5684-123	UM19516	VM47676	ISPF/PDF NLS - Japanese
5684-123	UM21879	VM47921	ISPF/PDF NLS - Japanese
5684-123	UM21879	VM51918	ISPF/PDF NLS - Japanese
5684-123	UM22585	VM53357	ISPF/PDF NLS - Japanese
5684-123	UM22770	VM53002	ISPF/PDF NLS - Japanese
5684-123	UM23025	VM53030	ISPF/PDF NLS - Japanese
5684-123	UM23198	VM53876	ISPF/PDF NLS - Japanese
5684-123	UM23670	VM53876	ISPF/PDF NLS - Japanese
5684-123	UM23670	VM54245	ISPF/PDF NLS - Japanese

5684-123	UM24824	VM56318	ISPF/PDF NLS - Japanese
5684-123	UM25231	VM54518	ISPF/PDF NLS - Japanese
5684-123	UM25940	VM57709	ISPF/PDF NLS - Japanese
5684-123	UM26371	VM58322	ISPF/PDF NLS - Japanese
5684-123	UM27020	VM59075	ISPF/PDF NLS - Japanese
5684-123	UM27103	VM59240	ISPF/PDF NLS - Japanese
5684-123	UM27656	VM60128	ISPF/PDF NLS - Japanese
5684-123	UM28252	VM60513	ISPF/PDF NLS - Japanese
5684-123	UM28304	VM60791	ISPF/PDF NLS - Japanese
5684-123	UM29206	VM62060	ISPF/PDF NLS - Japanese
5684-123	UM31096	VM63433	ISPF/PDF NLS - Japanese
5684-123	UM18170	VM46996	ISPF/PDF NLS - German
5684-123	UM18426	VM47921	ISPF/PDF NLS - German
5684-123	UM19495	VM47561	ISPF/PDF NLS - German
5684-123	UM19503	VM46996	ISPF/PDF NLS - German
5684-123	UM19503	VM47574	ISPF/PDF NLS - German
5684-123	UM19512	VM47675	ISPF/PDF NLS - German
5684-123	UM19517	VM47676	ISPF/PDF NLS - German
5684-123	UM21880	VM47921	ISPF/PDF NLS - German
5684-123	UM21880	VM51918	ISPF/PDF NLS - German
5684-123	UM22586	VM53357	ISPF/PDF NLS - German
5684-123	UM22771	VM53002	ISPF/PDF NLS - German

<b>Product Number</b>	<b>PTF</b>	<b>APAR</b>	<b>Product Description</b>
5684-123	UM23026	VM53030	ISPF/PDF NLS - German
5684-123	UM23199	VM53876	ISPF/PDF NLS - German
5684-123	UM23671	VM53876	ISPF/PDF NLS - German
5684-123	UM23671	VM54245	ISPF/PDF NLS - German
5684-123	UM24825	VM56318	ISPF/PDF NLS - German
5684-123	UM25232	VM54518	ISPF/PDF NLS - German
5684-123	UM25941	VM57709	ISPF/PDF NLS - German
5684-123	UM26372	VM58322	ISPF/PDF NLS - German
5684-123	UM27021	VM59075	ISPF/PDF NLS - German
5684-123	UM27104	VM59240	ISPF/PDF NLS - German
5684-123	UM27657	VM60128	ISPF/PDF NLS - German

5684-123	UM28253	VM60513	ISPF/PDF NLS - German
5684-123	UM28305	VM60791	ISPF/PDF NLS - German
5684-123	UM29207	VM62060	ISPF/PDF NLS - German
5684-123	UM31097	VM63433	ISPF/PDF NLS - German
5684-123	UM18216	VM46996	ISPF/PDF NLS - Traditional Chinese
5684-123	UM18427	VM47921	ISPF/PDF NLS - Traditional Chinese
5684-123	UM19496	VM47561	ISPF/PDF NLS - Traditional Chinese
5684-123	UM19504	VM46996	ISPF/PDF NLS - Traditional Chinese
5684-123	UM19504	VM47574	ISPF/PDF NLS - Traditional Chinese
5684-123	UM19513	VM47675	ISPF/PDF NLS - Traditional Chinese
5684-123	UM19518	VM47676	ISPF/PDF NLS - Traditional Chinese
5684-123	UM21881	VM47921	ISPF/PDF NLS - Traditional Chinese
5684-123	UM21881	VM51918	ISPF/PDF NLS - Traditional Chinese
5684-123	UM22587	VM53357	ISPF/PDF NLS - Traditional Chinese
5684-123	UM22772	VM53002	ISPF/PDF NLS - Traditional Chinese
5684-123	UM23027	VM53030	ISPF/PDF NLS - Traditional Chinese
5684-123	UM23200	VM53876	ISPF/PDF NLS - Traditional Chinese
5684-123	UM23672	VM53876	ISPF/PDF NLS - Traditional Chinese
5684-123	UM23672	VM54245	ISPF/PDF NLS - Traditional Chinese
5684-123	UM24826	VM56318	ISPF/PDF NLS - Traditional Chinese
5684-123	UM25235	VM54518	ISPF/PDF NLS - Traditional Chinese

<b>Product Number</b>	<b>PTF</b>	<b>APAR</b>	<b>Product Description</b>
5684-123	UM25942	VM57709	ISPF/PDF NLS - Traditional Chinese
5684-123	UM26373	VM58322	ISPF/PDF NLS - Traditional Chinese
5684-123	UM27022	VM59075	ISPF/PDF NLS - Traditional Chinese
5684-123	UM27105	VM59240	ISPF/PDF NLS - Traditional Chinese
5684-123	UM27658	VM60128	ISPF/PDF NLS - Traditional Chinese
5684-123	UM28254	VM60513	ISPF/PDF NLS - Traditional Chinese
5684-123	UM28306	VM60791	ISPF/PDF NLS - Traditional Chinese
5684-123	UM29208	VM62060	ISPF/PDF NLS - Traditional Chinese
5684-123	UM31098	VM63433	ISPF/PDF NLS - Traditional Chinese

### 6.1.3.5 If-Requisite Service

None.

### 6.1.3.6 Product Manuals

Form Number	Publication Title
GC34-4261	ISPF AND ISPF/PDF GENERAL INFORMATION
SC34-4270	ISPF AND ISPF/PDF PRIMER
SC34-4295	ISPF AND ISPF/PDF MASTER INDEX
GC34-4303	LICENSED PROGRAM SPECIFICATION
SC34-4305	ISPF AND ISPF/PDF PLANNING AND CUSTOMIZING
GC34-4306	ISPF/PDF GUIDE
GC34-4307	ISPF/PDF SERVICES
GC34-4308	ISPF/PDF LIBRARY MANAGEMENT FACILITY
SC34-4309	ISPF AND ISPF/PDF REFERENCE SUMMARY
SC34-4296	Software Configuration and Library Manager (SCLM) Guide and Reference
GI11-1448	ISPF V3R2 PROGRAM DIRECTORY
GI10-8150	ISPF/PDF V3R2 PROGRAM DIRECTORY

### 6.1.3.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### **Installation Guidelines**

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, "DASD Requirements".
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this Licensed Program Product are **not linked R/W** by any ID including the ID where this Licensed Program Product is being installed from.

### **Installing Licensed Products Utilizing Product Envelopes**

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO ENV *envelope\_filename***

### **Other Requisite Licensed Products**



## PRODUCT INSTALLATION REQUIREMENTS

### 1. Mount the Product Tape as 181

### 2. Load Product Files from Tape

- To install this product onto a test disk issue:

**vmfins install ppf \$5684123 ispdf (nomemo**

- To install this product onto the production disk issue:
- 

**vmfins install ppf \$5684123 ispdfprd (nomemo**

- To install this product into the SFS test directory issue:

**vmfins install ppf \$5684123 ispdfsfs (nomemo**

- To install this product into the SFS production directory issue:

**vmfins install ppf \$5684123 ispdfsfsprd (nomemo**

### 3. Detach Product Tape

### 4. Load NLS Other Than English

#### Notes:

- a. The English ISPF/PDF - NLS feature in MACLIB format is included with this version of ISPF/PDF.
- b. The ISPF/PDF - NLS feature should be installed only if a language other than English is required.
- c. The SDO ISPF/PDF NLS feature has all the service listed as co-req service already applied. (i.e. If the SDO ISPF/PDF NLS feature is utilized to install a language, no additional service has to be applied to the language.)

If the SDO ISPF/PDF NLS feature **IS NOT** utilized to install a language, all the service listed as co-req service for the NLS must be applied. Failure to do so may result in incorrect results and/or the abend of ISPF/PDF.

### 5. Customize ISPF/PDF

Please refer to the *ISPF/PDF Program Directory* for tailoring and customization.

#### Notes:

- a. If the Remote Spooling Communications (RSCS) Subsystem and the PDF Spool Utility (Option 3.6) are to be utilized the ISRXPARM ASSEMBLE file must be created. Failure to do so will result in the ISPF/PDF modules being built incorrectly by the ISRINSXR exec. Please refer to the section *Preprocessing for Transmit/Receive* in the *ISPF/PDF Program Directory* for information on the ISRXPARM ASSEMBLE file.
- b. The ISPF/PDF modules are built utilizing the following command:

**ISRINSXR fm**

where:

fm - The file mode of the disk containing the ISPF/PDF code. The disk must be accessed as R/W.

---

**Notes:**

- 1) The disk containing the Product 5684-043 ISPF/DM must be accessed.
- 2) The modules created by the ISRINSXR EXEC are not included on the SDO tape. As a result, when the ISRINSXR EXEC attempts to erase the modules prior to creating them it is unable to do so and the following message is output:

**DMSERS002E FILE module\_name MODULE B1 NOT FOUND**

This messages may be ignored.

- 3) Please refer to the section 'ISRINSXR EXEC' in the *ISPF/PDF Program Directory* for information on the use of the 'ISRINSXR EXEC'.

**6. Build the ISPF/PDF Segment**

Please refer to the section *DCSS Information* for information on building the ISPF/PDF segments.

**7. Move ISPF/PDF Into Production**

If you have installed the product onto a test disk, use **VMFCOPY** to copy the files to your production disks once you have completed your testing.

**PRODUCT SERVICE REQUIREMENTS**

- After the service has been loaded from the corrective service tape and the 'RENAME EXEC' has been executed, renamed files must be moved to the disk that contains your PDF Product maintenance.
- If your corrective service contains any of the following files the 'ISRINSXR EXEC' will have to be run to rebuild the appropriate modules. Please refer to the section 'ISRINSXR EXEC' in the the *ISPF/PDF Program Directory* for information on the use of the 'ISRINSXR EXEC'.

FLMCMD TEXT	ISRFXDAT TEXT	ISRLE* TEXT
ISRLMFI TEXT	ISRLMFZ TEXT	ISRS* TEXT
ISR* TEXT	ISR* TEXT	ISR* TEXT

- IF your corrective service contains any 'ISR\* TEXT' files other than those mentioned above, the 'ISRSAVE EXEC' will have to be run to rebuild your ISPF/PDF shared segment. Please refer to the section *SAVE THE ISPF/PDF AND SCLM DCSS* in the *ISPF/PDF Program Directory* for information on resaving the ISPF/PDF shared segments.
  - If your corrective service contains any 'FLM\* TEXT' files other than those listed above, the 'FLMSAVE EXEC' will have to be run to rebuild your SCLM shared segment. Please refer to the section *SAVE THE ISPF/PDF AND SCLM DCSS* in the the *ISPF/PDF Program Directory* for information on resaving the ISPF/PDF shared segments.
  - Any panels, messages, skeletons of tables should be put into the appropriate MACLIB using the CMS 'MACLIB REP' command.
- 

**6.1.3.8 DCSS Information**

The following commands may be utilized to create the ISPF/PDF segment. The commands may be issued from any ID that with the following:

1. Maximum virtual storage size of 1024M (1G)
2. CP Privilege Class 'E' (Required to create the segment)
3. Write access to the ISPF/DM and ISPF/PDF Code disks (Required to load the segment)
  - For the ISPF/DM and ISPF/PDF Product disk, this is the ISPVM 192.
  - For the ISPF/DM and ISPF/PDF Test disks, this is the PRETEST 459 and PRETEST 457 respectively.

The segment range utilized for the ISPF/PDF segment should be based on the segment layout as defined in the SDO Program Directory.

- Define the virtual storage at 1024M (1G) and ensure that storage is cleared.

**def stor 1024M**

**system clear**

- Link and access the ISPF/DM ISPF/PDF code disk(s). The disk(s) should be linked in write mode.
  - For the ISPF/DM and ISPF/PDF Production disk:

**link ISPVM 192 002 MW**

**acc 002 b**

- For the ISPF/DM and ISPF/PDF Test disk:

**link PRETEST 459 002 MW**

**link PRETEST 457 003 MW**

**acc 003 b**

**acc 002 c**

- Define the ISPF/PDF segment space

**defseg *segmentname startaddr - endaddr SR***

**Where:**

segment name - The name of the ISPF/PDF segment.

startaddr - The starting address of the segment range

endaddr - The ending address of the segment range

**Note:**

1. ISRDCSS is the default name for the ISPF/PDF segment.
2. The segment range specified in the SDO Program Directory is large enough to contain ISPF/PDF, LMF and two National Languages. If more than two languages are to be included in the ISPF/PDF segment, seven (7) must be added to the segment range for each additional segment.

For example, if the segment range for the ISPF/PDF segment range specified in the SDO Program Directory is 30000-300FF and one (1) additional National Language is included in the segment, then a segment range of 30000-30106 must be specified.

If three additional languages are to be included in the segment (i.e. All five National Languages provided with ISPF/PDF are to be included in the segment), a segment range of 30000-30115 must be specified.

- Execute the ISRSAVE exec to save the ISPF/PDF segment.

**ISRSAVE** *segmentname*

**Where:**

segment name - The name of the ISPF/PDF segment.

**Note:**

The ISRSAVE exec will output a series of questions regarding the size of the ISPF/PDF segment and the National Languages that are to be included in the segment.

For additional information regarding the creation of the ISPF/PDF segment, please see Appendix D, "Saved Segments".

The SCLM feature of ISPF/PDF is not required for the execution of ISPF/PDF, is not Y2K Ready and is no longer supported by IBM.

The SCLM feature however has been included with this version of ISPF/PDF for consistency with previous versions of ISPF/PDF on a 'as is' basis.

For more information on the SCLM feature of ISPF/PDF refer to the *ISPF/PDF Software Configuration and Library Manager(SCLM) Guide and Reference*.

For information on the creation of the segment for the SCLM feature, please refer to the section *DCSS Information* and to the *ISPF/PDF Program Directory*.

For the recommended segment range for the SCLM segment, please see Appendix D, "Saved Segments".

### 6.1.3.9 Verification

1. Make sure the ISPVMM Virtual Machine is running disconnected **query ispvmm**

This should return:

```
ISPVMM    - DSC
```

2. Use the **PDF EXEC**

3. The exec ran successfully if the primary option panel is displayed.
- 

## 6.1.4 5684-123 ISPF/PDF NLS V3R2.0

### 6.1.4.1 PUT/ESO Applied

The product is at service level PUT9405.

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

#### **6.1.4.2 Service Excluded**

None.

#### **6.1.4.3 Pre-Requisite Service**

None.

#### **6.1.4.4 Co-Requisite Service**

<b>Product Number</b>	<b>PTF</b>	<b>APAR</b>	<b>Product Description</b>
5684-123	UM28301	VM60791	ISPF/PDF BASE
5684-123	UM28249	VM60513	ISPF/PDF BASE
5684-123	UM27100	VM59240	ISPF/PDF BASE
5684-123	UM27017	VM59075	ISPF/PDF BASE
5684-123	UM26368	VM58322	ISPF/PDF BASE
5684-123	UM25937	VM57709	ISPF/PDF BASE
5684-123	UM25228	VM54518	ISPF/PDF BASE
5684-123	UM23667	VM54245	ISPF/PDF BASE
5684-123	UM23195	VM53876	ISPF/PDF BASE
5684-123	UM23022	VM53030	ISPF/PDF BASE

<b>Product Number</b>	<b>PTF</b>	<b>APAR</b>	<b>Product Description</b>
5684-123	UM22767	VM53002	ISPF/PDF BASE
5684-123	UM31093	VM63433	ISPF/PDF BASE

#### **6.1.4.5 If-Requisite Service**

None.

#### **6.1.4.6 Product Manuals**

None.

#### **6.1.4.7 Installation**

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

---

## DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

## Installation Guidelines

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, "DASD Requirements".
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this Licensed Program Product are **not linked R/W** by any ID including the ID where this Licensed Program Product is being installed from.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO ENV *envelope\_filename***

### SDO ISPF/PDF NLS Tape Content

The SDO ISPF/PDF NLS Tape contains the following languages in MACLIB format:

- German
- Swiss German
- Traditional Chinese
- Japanese
- English (American English)

All service specified as required in the ISPF/PDF Base feature section of the SDO Program Directory has been included. (i.e. If this feature is utilized to install a language no additional service has to be applied to the language.)

### SDO ISPF/PDF NLS Disk Requirements

The disk size specified in the 'DASD Requirements' Appendix of the SDO Program Directory for ISPF/PDF NLS feature is the amount of DASD required to install one (1) NLS language. To estimate the total DASD required for the ISPF/PDF NLS feature multiple the disk size specified in the Appendix by the number of NLS languages to be installed.

For example, if you are going to install German and Swiss German and the 'DASD Requirements' Appendix states that 1000 4K blocks are required, then the DASD required for German and Swiss German is 2000 4k blocks (i.e. 2 x 1000).

### NLS INSTALLATION REQUIREMENTS

#### 1. Mount the SDO ISPF/PDF NLS Tape as 181

#### 2. Load Language Files from Tape

- To install a language onto a test disk issue:

**vmfins install ppf \$568412n inLLL (nomemo**

- To install a language onto the production disk issue:



---

---

**vmfins install ppf \$568412n inLLLprd (nomemo)**

- To install a language into the SFS test directory issue:

**vmfins install ppf \$568412n inLLLSfs (nomemo)**

- To install a language into the SFS production directory issue:

**vmfins install ppf \$568412n inLLLSfsprd (nomemo)**

**Notes:**

- a. 'LLL' in the above command must be replaced with the three character language code for the language that is to be loaded:

DEU - German  
DES - Swiss German  
CHT - Traditional Chinese  
JPN - Japanese  
ENG - English

- b. The above command must be repeated for each language to be loaded.
- c. English NLS in MACLIB format is included with the SDO ISPF/PDF Base feature. If the Base feature of ISPF/PDF was installed from the SDO, the English NLS does not have to be installed from the ISPF/PDF NLS tape.
- d. All service listed in the SDO Program Directory under the ISPF/PDF Base Feature as co-req service for the NLS feature has already been applied. (i.e. If this feature is utilized to install a language, no additional service has to be applied to the language.)
- e. The SDO ISPF/PDF Base feature has all the service listed as co-req service already applied. (i.e. If the SDO ISPF/PDF Base feature was utilized to install the Base feature of ISPF/PDF no additional service has to be applied to the Base feature of ISPF/PDF.)

If the SDO ISPF/PDF Base feature **WAS NOT** utilized to install the Base feature of ISPF/PDF, all the service listed as co-req service for ISPF/PDF Base Feature must be applied. Failure to do so may result in incorrect results or the abend of ISPF/PDF.

**Warning:** Ensure that all minidisks required by this Licensed Product are not linked R/W by any user ID including the user ID where this Licensed Product is being installed from. For production minidisk information refer to Appendix C, "DASD Requirements" or for test minidisk information refer to Figure 2.

### 3. Detach ISPF/PDF NLS Tape

#### PRODUCT SERVICE REQUIREMENTS

The ISPF/PDF NLS feature is serviced as part of ISPF/PDF. Please refer to the ISPF/PDF Base feature section of the SDO Program Directory for information on servicing ISPF/PDF.

#### 6.1.4.8 DCSS Information

Please refer to the ISPF/PDF Base feature section of the SDO Program Directory for information on the

generation of the ISPF/PDF segment and the inclusion of a language within the segment.

#### 6.1.4.9 Verification

Please refer to the ISPF/PDF Base feature section of the SDO Program Directory for information on ISPF/PDF verification.

---

### 6.1.5 5697-F42 DB2 RXXSQL V7R1.0

#### 6.1.5.1 PUT/ESO Applied

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

#### 6.1.5.2 Service Excluded

None.

#### 6.1.5.3 Pre-Requisite Service

None.

#### 6.1.5.4 Co-Requisite Service

None.

#### 6.1.5.5 If-Requisite Service

None.

#### 6.1.5.6 Product Manuals

Form Number	Publication Title
SC09-2891	DB2 REXX SQL for VM/ESA Installation and Reference

Form Number	Publication Title
GI10-5006	Program Directory for REXX SQL for VM/ESA Version 7 Release 1, Modification Level 0

#### 6.1.5.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### **DASD Storage Requirements And User ID Definitions**

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

### Installation Guidelines

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, "DASD Requirements".
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this Licensed Program Product are **not linked R/W** by any ID including the ID where this Licensed Program Product is being installed from.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO ENV *envelope\_filename***

To install this product onto a test disk issue:

- **vmfins install ppf B5697F42 db2 (nomemo**

---

To install this product onto the production disk issue:

- **vmfins install ppf B5697F42 db2prd (nomemo)**

To install this product into the SFS test directory issue:

- **vmfins install ppf B5697F42 db2sfs (nomemo)**

To install this product into the SFS production directory issue:

- **vmfins install ppf B5697F42 db2sfsprd (nomemo)**

If you have installed the product onto a test disk, use **VMFCOPY** to copy the files to your production disks once you have completed your testing.

### ***Installation of RXSQL into a Database***

The RXSQL Package and Help tables must be manually installed into each DB2 DataBase that REXX SQL is to be utilized with.

The following steps may be used to install the RXSQL feature in the DataBase:

- Logon to an ID with DBA Authority **Note:** The DB2 Application Server that contains the DataBase must have already been started.
- Link the DB2 RXSQL Production Disk, SQLMACH 198, type:  
LINK SQLMACH 198 198 RR  
ACCESS 198 P
- Link the DB2 RXSQL Service Disk, SQLMACH 199, type:  
LINK SQLMACH 199 199 RR  
ACCESS 199 V
- Link the DB2 Application Server Production Disk, SQLMACH 195, type:  
LINK SQLMACH 195 195 RR

---

ACCESS 195 Q

- Enter the command:  
SET LANG AMENG (ADD ARI USER
- Connect to the database  
SQLINIT DB(dbname)

**Note:** The dbspace RXSQHELP will be dropped and recreated with the new RXSQL help tables if you are upgrading. The installation exec will acquire the necessary dbspace for the help tables if you are installing for the first time.

- Install DB2 RXSQL into a DB2 application server  
ELOAMOD
- Install DB2 RXSQL HELP tables  
ELOHLPLD
- To update the DB2 RXSQL HELP tables  
ELOSHLP LANG(S001)

Please refer to the ***Installing DB2 RXSQL*** chapter of the 'DB2 REXX SQL for VM/ESA Installation' manual for complete installation instructions for RXSQL 7.1.0.

### 6.1.5.8 DCSS Information

None.

### 6.1.5.9 Verification

To verify the RXSQL installation, refer to the chapter entitled "Installing DB2 RXSQL", in the section entitled "Installation Verification", in the *DB2 REXX SQL for VM/ESA Installation and Reference* manual.

Prior to running step three of the verification (issuing the EMPCRE command), a private DB space for SQLUSER must be obtained. To do this, enter the following command from ISQL:

**acquire private dbspace named sqluser.example**

**Note:** This step can only be done by a userid that already has DBA authority.

---

## **6.1.6 5697-F42 DB2 DATA RESTORE V7R3.0**

### **6.1.6.1 PUT/ESO Applied**

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **6.1.6.2 Service Excluded**

None.

### **6.1.6.3 Pre-Requisite Service**

None.

### **6.1.6.4 Co-Requisite Service**

None.

### **6.1.6.5 If-Requisite Service**

None.

---

### 6.1.6.6 Product Manuals

Form Number	Publication Title
SC09-2991	DB2 Data Restore Guide
GC09-2982	DB2 Server for VM & VSE LPS for VM/ESA & VSE/ESA
GI10-5004	Program Directory for Data Restore for VM/ESA Version 7 Release 3, Modification Level 0

### 6.1.6.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.



## DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

## Installation Guidelines

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, "DASD Requirements".
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this Licensed Program Product are **not linked R/W** by any ID including the ID where this Licensed Program Product is being installed from.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO ENV *envelope\_filename***

To install this product onto a test disk issue:

- **vmfins install ppf F5697F42 db2 (nomemo**

To install this product onto the production disk issue:

- **vmfins install ppf F5697F42 db2prd (nomemo**

To install this product into the SFS test directory issue:

- **vmfins install ppf F5697F42 db2sfs (nomemo To**

install this product into the SFS production directory issue:

- **vmfins install ppf F5697F42 db2sfsprd (nomemo**

If you have installed the product onto a test disk, use **VMFCOPY** to copy the files to your production disks once you have completed your testing.

In order for the Data Restore facility to be utilized on a DB2 DataBase, Data Restore must be installed (loaded) into the DataBase.

Please refer to the ***Installing Under VM*** section in the ***Installing Data Restore*** chapter of the 'DB2 Data Restore Guide' manual for Data Restore installation instructions.

---

- **Note:**

1. The disk containing the Data Restore code (e.g. SQLDRR 191) must be linked in write mode and accessed as the 'A' disk.
2. If you are migrating from an earlier level of Data Restore, only **Step 3.3 Load the Data Restore Packages** is required to be performed.
  - **Note:** The following error may occur during the execution of the exec XTS9PREP. This error does not relate to the reload of Data Restore and may be ignored.

```
ARI0503E An SQL error has occurred.  
An attempt to revoke a privilege from DATARFTR  
was denied. Either DATARFTR does not have  
this privilege, or SQLDEA does not have  
the authority to revoke this privilege.  
ARI0505I SQLCODE = -556 SQLSTATE = 42504 ROWCOUNT = 0  
ARI0504I SQLERRP: ARIXA09 SQLERRD1: -300 SQLERRD2: 0
```

3. If Data Restore is to be installed on more than one application server, repeat the installation steps for each application server.

### 6.1.6.8 DCSS Information

None.

### 6.1.6.9 Verification

To verify that the Restore Feature was installed successfully, follow the steps outlined in the chapter entitled "Installing Data Restore", Refer to section "Installing under VM", of the *DB2 Data Restore Guide* manual.

---

## 6.1.7 5697-F42 DB2 CONTROL CENTER V7R3.0

### **6.1.7.1 PUT/ESO Applied**

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **6.1.7.2 Service Excluded**

None.

### **6.1.7.3 Pre-Requisite Service**

None.

### **6.1.7.4 Co-Requisite Service**

None.

---

### **6.1.7.5 If-Requisite Service**

None.

### **6.1.7.6 Product Manuals**

Form Number	Publication Title
-------------	-------------------

GC09-2993	DB2 Server for VSE & VM Control Center Operations Guide for VM
GI10-5002	Program Directory for Control Center for VM Version 7 Release 3.0

### 6.1.7.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

#### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (PLAN NOMEMO ENV *envelope\_filename***

**VMFINS INSTALL PPF *ppfname compid* (NOMEMO ENV *envelope\_filename***

#### Installation Guidelines

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, “DASD Requirements”.
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this

### Important Note about Document Changes

Please review the PSP Bucket for the latest Document changes for *IBM DB2 for VM Control Center Operations Guide V7.3* GC09-2993-01 Use RETAIN Upgrade DB2VSEVM730, subset CCVM

To install this product onto a test disk issue:

- **vmfins install ppf G5697F42 db2 (nomemo)**

To install this product onto the production disk issue:

- **vmfins install ppf G5697F42 db2prd (nomemo)**

To install this product into the SFS test directory issue:

- **vmfins install ppf G5697F42 db2sfs (nomemo)** To

install this product into the SFS production directory issue:

- **vmfins install ppf G5697F42 db2sfsprd (nomemo)**

If you have installed the product onto a test disk, use **VMFCOPY** to copy the files to your production disks once you have completed your testing.

For detailed instructions on installing the Control Center, reference the *Program Directory for Control Center for VM V7R3.0*.

---

NOTE. You must configure the Control Center for your specific site. Please refer to section "Configure Control Center Files" in the *Program Directory for Control Center for VM V7R3.0*.

NOTE. For Migration information refer to Chapter 6 in the *Program Directory for Control Center for VMV7R3.0*.

### 6.1.7.8 DCSS Information

None.

### **6.1.7.9 Verification**

For instructions on verifying the Control Center, refer to section 7 "Installation Verification" in the *Program Directory for Control Center for VM V7R3.0*.

## **6.1.8 5697-F42 DB2 NLS VM HELP FILES V7R5.0**

### **6.1.8.1 PUT/ESO Applied**

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### **6.1.8.2 Service Excluded**

None.

### **6.1.8.3 Pre-Requisite Service**

None.

### **6.1.8.4 Co-Requisite Service**

None.

### **6.1.8.5 If-Requisite Service**

None.

### **6.1.8.6 Product Manuals**

### **6.1.8.7 Installation**

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, "z/VM 6.2 Installation and Production Enablement Requirements" contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

### **DASD Storage Requirements And User ID Definition**

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.



The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url: <http://www.vm.ibm.com/sdo/>

#### **Installation Guidelines**

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, "DASD Requirements".
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this Licensed Program Product are **not linked R/W** by any ID including the ID where this Licensed Program Product is being installed from.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (PLAN NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (NOMEMO ENV envelope\_filename**

### 6.1.8.8 DB2 NLS Requirements

The requirements for the installation of an NLS Language are detailed in Section “10.0 NLS Installation Instructions” of the *Program Directory for IBM DATABASE 2 Server for VM Version 7 Release 5 Modification Level 0*

It is recommended that, with the exception of the Sub-Section “10.4.2 Install an NLS Language for DB2 for VM,” this section be reviewed prior to the installation of the DB2 NLS.

Please note that the 5697F75A 193 disk and the SQLMACH 193 DASD minidisks may require additional space to hold the NLS Languages.

For example, the 5697F75A 193 disk must have sufficient free space to hold all 5 NLS Languages provided for DB2. On a 3380 DASD, this amounts to approximately 9000 4k blocks (or 60 cylinders).

Please refer to Section 10.3 “DASD Storage and User ID Requirements” in the *Program Directory for IBM DATABASE 2 Server for VM Version 7 Release 5 Modification Level 0*

### 6.1.8.9 DB2 NLS Semi-VMSES/E Installation

DB2 NLS should be installed from the installation DB2 Installation ID 5697F75A.

All the NLS Languages will be installed to the DB2 Server Code test build 193 minidisk (or SFS Directory) under the ID 5697F75A. This is different from the standard installation defined in the Sub-Section “10.4.2 Install an NLS Language for DB2 for VM,” of the *Program Directory for IBM DATABASE 2 Server for VM Version 7 Release 5 Modification Level 0* which provides for the installation of a single NLS language on the 5697F75A 193 (DB2 Server Code test build disk).

After logging onto the installation ID and mounting the DB2 for VM NLS installation tape at virtual address 181, the following steps/commands replace the commands specified in Sub-Section “10.4.2 Install an NLS Language for DB2 for VM,” and must be utilized to install DB2 NLS:

1. Access the VMSES/E code:

**link MAINT 5E5 5E5 rr**

**access 5E5 b**

2. Access the System Software Inventory disk:

**link MAINT 51D 51D mr**

**access 51D d**

3. Install the DB2 NLS code:

- - a. Onto the Pretest DB2 Server Code minidisk issue:  
**vmfins install ppf I5697F42 db2 (nomemo)**
  - b. Onto the Pretest DB2 Server Code build SFS directory:  
**vmfins install ppf I5697F42 db2sfs (nomemo)**
  - c. Onto the DB2 Server production Code build minidisk:  
**vmfins install ppf I5697F42 db2prd (nomemo)**
  - d. Onto the production DB2 Server Code build SFS directory:  
**vmfins install ppf I5697F42 db2sfsprd (nomemo)**
- **Note:** If desired, the default installation disk addresses may be altered by creating a PPF override file for the DB2 NLS. Please refer to the *GC24-6243 z/VM VMSES/E Introduction and Reference* manual for information on creating a PPF override file.

After the NLS has been placed on the NLS disk, the desired NLS language must be integrated into the appropriate DB2 DataBase(s) and copied to DB2 and System Production minidisks (SFS Directories). This is accomplished by performing the steps defined in Sections “10.4.3 Installation Step 3. Install DB2 for VM Messages, ISQL Help Text and CMS Help” through “10.4.7 Installation Step 7. Post-Installation Customization Steps for DB2 for VM”

### 6.1.8.10 DCSS Information

It is recommended for performance reasons that each activated NLS Language be saved in a shared segment. Please refer to the section “Using Saved Segments for NLS Components and Choosing a National Language” in the *DB2 Server for VM System Administration* for the procedures on “defining Message Repositories as Saved Segments.”

### 6.1.8.11 Verification

None.

## 6.1.9 5697-F42 DB2 CLIENT NLS VM HELP FILES V7R5.0

### 6.1.9.1 PUT/ESO Applied

The PUT/ESO Service Level of the Licensed Program Product may be found in the *z/VM SDO Optional Licensed Product Service* section on the *z/VM SDO V6 webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

This section provides the PUT/ESO Service Level of the Licensed Program Products plus a list of PTFs in addition to the PTFs included in the PUT/ESO service that have been applied.

### 6.1.9.2 Service Excluded

None.

### 6.1.9.3 Pre-Requisite Service

None.

### 6.1.9.4 Co-Requisite Service

Product Number	PTF	APAR	Product Description
5741-A05	VM63968	UM32108	Z/VM CP V5R3M0

### 6.1.9.5 If-Requisite Service

None.

### 6.1.9.6 Product Manuals

### 6.1.9.7 Installation

With z/VM 6.2, a number of changes were introduced in the System Maintenance and Service environment. Prior to installing a Licensed Program Product in a Single System Image (SSI) environment (SSI-Ready or SSI-Enabled) Chapter 28. *Converting a z/VM System to a Single-Member z/VM SSI Cluster* and Chapter 25. *Setting Up z/VM Single System Image Clusters* in the *z/VM CP Planning and Administration* manual should be reviewed.

An overview of the changes introduced in z/VM 6.2 to support an SSI environment may be found in Chapter 2. *System Changes* in the *z/VM Migration Guide*.

Appendix F, “z/VM 6.2 Installation and Production Enablement Requirements” contains an overview of several of the major changes introduced with z/VM 6.2 and their effect on the installation and Production enablement of Licensed Program Products. This appendix should be reviewed prior to the installation of this Licensed Program Product.

## DASD Storage Requirements And User ID Definitions

The DASD storage requirements (e.g. minidisk definitions) and the User ID definitions (i.e. Virtual Machine VM System Directory entries) from the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the IDs and minidisks required for the installation and Production enablement of this Licensed Program Product.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO webpage*.

The information on DASD storage requirements and User ID definitions provided in the *z/VM SDO Enabling Aid* may also be found in the *z/VM SDO Product DASD Requirements* section and the *z/VM SDO Optional Licensed Products VM Directory* section on the *z/VM SDO webpage*.

This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

## Installation Guidelines

This Licensed Program Product may be installed from any ID that has:

- READ access to the MAINT 5E5 disk
- WRITE access to the MAINT 51D and 31D disks
- WRITE access to the minidisks or SFS Directory that is to be utilized for the Licensed Program Product's code.

This Licensed Program Product may be installed to the Product's Production disks or to the Product's Test disks.

- For Production minidisk information refer to Appendix C, "DASD Requirements".
- For Test minidisk information refer to Figure 2.

It is recommended that the Product be installed utilizing the z/VM 6.2 standard system maintenance ID, MAINT620, and the Test disks.

Prior to installation of this Licensed Program Product, ensure that all minidisks required by this Licensed Program Product are **not linked R/W** by any ID including the ID where this Licensed Program Product is being installed from.

### Installing Licensed Products Utilizing Product Envelopes

When installing using the Product Envelope, use the ENV option with the VMFINS commands. The Product Envelope should be on a minidisk or SFS directory accessed as the 'C' disk.

**VMFINS INSTALL INFO (NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (PLAN NOMEMO ENV envelope\_filename**

**VMFINS INSTALL PPF ppfname compid (NOMEMO ENV envelope\_filename**

## 6.1.9.8 DB2 NLS Requirements

### IMPORTANT NOTE

Please review the PSP Bucket for latest updates prior to installing this feature. The current Program Directory dated February 2007 is incomplete. The PSP Bucket in RETAIN Upgrade: DB2VSEVM750 Subset: DB2750C will be updated to reflect this information in the near future:

The requirements for the installation of an NLS Language are detailed in Section "8.0 NLS Installation Instructions" of the *Program Directory for IBM DB2 Server for VM Client Edition Version 7 Release 5 Modification Level 0*

It is recommended that, with the exception of the Sub-Section "8.4.2 Install an NLS Language for DB2 for VM Client Edition," this section be reviewed prior to the installation of the DB2 NLS.

Please note that the 5697F75C 193 disk and the SQLCLNT 193 DASD minidisks may require additional space to hold the NLS Languages.

For example, the 5697F75C 193 disk must have sufficient free space to hold all 5 NLS Languages provided for DB2. On a 3380 DASD, this amounts to approximately 9000 4k blocks (or 60 cylinders).

Please refer to Section 8.3 "DASD Storage and User ID Requirements" in the *Program Directory for IBM DB2 Server for VM Client Edition Version 7 Release 5 Modification Level 0*

## 6.1.9.9 DB2 Client Edition NLS Semi-VMSES/E Installation

DB2 Client Edition NLS should be installed from the installation DB2 Client Edition Installation ID 5697F75C.

All the NLS Languages will be installed to the DB2 Server Code test build 193 minidisk (or SFS Directory) under the ID 5697F75C. This is different from the standard installation defined in the Sub-Section "8.4.2 Install an NLS Language for DB2 for VM Client Edition," of the *Program Directory for IBM DB2 Server for Client Edition VM Version 7 Release 5 Modification Level 0* which provides for the installation of a single NLS language on the 5697F75C 193 (test service build disk).

After logging onto the installation ID and mounting the DB2 for VM Client Edition NLS installation tape at virtual address 181, the following steps/commands replace the commands specified in Sub-Section "8.4.2 Installation Step 2. Install an NLS Language for DB2 for VM Client Edition," and must be utilized to install DB2 Client NLS:

1. Access the VMSES/E code:

**link MAINT 5E5 5E5 rr**

**access 5E5 b**

2. Access the System Software Inventory disk:

**link MAINT 51D 51D mr**

**access 51D d**

3. Install the DB2 NLS code:

•

a. Onto the Pretest DB2 Client Code minidisk issue:

**vmfins install ppf J5697F42 db2 (nomemo**

b. Onto the Pretest DB2 Client Code build SFS directory:

**vmfins install ppf J5697F42 db2sfs (nomemo**

c. Onto the DB2 Client production Code build minidisk:

**vmfins install ppf J5697F42 db2prd (nomemo**

d. Onto the production DB2 Client Code build SFS directory:

**vmfins install ppf J5697F42 db2sfsprd (nomemo**

- **Note:** If desired, the default installation disk addresses may be altered by creating a PPF override file for the DB2 Client Edition NLS. Please refer to the *GC24-6243 z/VM VMSES/E Introduction and Reference* manual for information on creating a PPF override file.

After the NLS has been placed on the NLS disk, the desired NLS language must be integrated into the appropriate DB2 DataBase(s) and copied to DB2 and System Production minidisks (SFS Directories). This is accomplished by performing the steps defined in Sections “8.4.3 Installation Step 3. Install DB2 for VM Client Edition Messages, ISQL Help Text and CMS Help” through “8.4.6 Installation Step 7. Post-Installation Customization Steps for DB2 for VM Client Edition”

### **6.1.9.10 DCSS Information**

It is recommended for performance reasons that each activated NLS Language be saved in a shared segment. Please refer to the section “Using Saved Segments for NLS Components and Choosing a National Language” in the *DB2 Server for VM System Administration* for the procedures on “defining Message Repositories as Saved Segments.”

### **6.1.9.11 Verification**

None.

## Appendix A. z/VM SDO IBM Licensed Program Products

The figure below is a list of the z/VM SDO Licensed Products. The list is in alphabetical order by "Product Abbrev" and can be used as a cross reference between Licensed Product name and Licensed Product number.

### Note!

A **Semi-VMSES/E** product was previously called '**Pre-Install**' format.

These terms were misleading, so the names have been changed to better describe the install format of the Licensed Product. The term 'Pre-Install' may still appear on the Packing List or the Media Description report, the Configurator, or Marketing Literature, but should be interpreted to mean Semi-VMSES/E.

### A.1 z/VM SDO Licensed Products Table

Figure 3 (Page 1 of 2). Licensed Products Abbreviations

Product Abbrev.	Product Number	Description	Install Format
Archive Manager for z/VM	5697-J05	Archive Manager for z/VM	VMSES/E
ACF/VTAM ESA	5654-010	ACF/VTAM for Use with VM/ESA	VMSES/E
APPC APPL SUITE	5654-010	APPC Applications Suite	VMSES/E
Backup and Restore Manager for z/VM	5697-J06	Backup and Restore Manager for z/VM	VMSES/E
DB2 Client for VM	5697-F42	DB2 Client for VM	VMSES/E
DB2 Client NLS VM Help Files	5697-F42	DB2 Client NLS VM Help Files	Semi-VMSES/E
DB2 Control Center	5697-F42	DB2 Control Center	Semi-VMSES/E
DB2 Data Propagator	5697-F42	DB2 Data Propagator	VMSES/E
DB2 Data Restore	5697-F42	DB2 Data Restore	Semi-VMSES/E
DB2 NLS VM Help Files	5697-F42	DB2 NLS VM Help Files	Semi-VMSES/E
DB2 QMF	5697-F42	Query Management Facility English Base VM	VMSES/E
DB2 RXSQL	5697-F42	DB2 RXSQL	Semi-VMSES/E
DB2 Server for VM	5697-F42	DB2 Server for VM	VMSES/E
DFSMS/VM	5741-A07	DFSMS/VM - Data Facility Storage Management Subsystem	VMSES/E



Figure 3 (Page 2 of 2). Licensed Products Abbreviations

Product Abbrev.	Product Number	Description	Install Format
DFSMS/VM KANJI	5741-A07	DFSMS/VM - Data Facility Storage Management Subsystem (JAPANESE)	VMSES/E
DITTO	5654-029	Data Interfile Transfer, Testing, and Operations Utility for VM	VMSES/E
EREP	5654-260	Environmental Record Editing and Printing Program	Semi-VMSES/E
GDDM-IMD	5668-801	Graphical Data Display Manager/Interactive Map Definition	VMSES/E
GDDM-IVU	5668-723	Graphical Data Display Manager/Image Viewing Facility	VMSES/E
GDDM-PGF	5668-812	Graphical Data Display Manager/Presentation Graphics Facility	VMSES/E
GDDM/VM	5684-168	Graphical Data Display Manager/VM	VMSES/E
HLASM	5696-234	IBM High Level Assembler/VM	VMSES/E
HLASM Toolkit	5696-234	IBM High Level Assembler/VM	VMSES/E
IBM Debug Tool for z/VM	5654-A23	IBM Debug Tool for z/VM	VMSES/E
IBM Director	5648-DRZ	IBM Director for Linux on System z	DVD
IBM Tivoli zSecure Manager for RACF	5655-T13	IBM Tivoli zSecure Manager for RACF z/VM	VMSES/E
IBM Tivoli Omegamon XE on z/VM	5698-A36	IBM Tivoli Omegamon XE on z/VM and Linux	VMSES/E
ICKDSF	5684-042	Device Support Facilities	VMSES/E
ISPF/PDF	5684-123	ISPF/Program Development Facility	Semi-VMSES/E
ISPF/PDF NLS	5684-123	ISPF/Program Development Facility NLS	Semi-VMSES/E
ISPF	5684-043	Interactive System Productivity Facility/Dialog Manager	Semi-VMSES/E
Operations Manager for z/VM	5697-J10	Operations Manager for z/VM	VMSES/E
REXX/370 Compiler	5695-013	IBM Compiler for SAA REXX/370	VMSES/E
REXX/370 Compiler Kanji	5695-013	IBM Compiler for SAA REXX/370	VMSES/E
REXX/370 Library	5695-014	IBM Library for SAA REXX/370	VMSES/E
REXX/370 Library Kanji	5695-014	IBM Library for SAA REXX/370	VMSES/E
SDO z/VM Opt. Product Enabling Aid	5741-A08	SDO z/VM Optional Products Enabling Aid	Internet Download
Tape Manager for z/VM	5697-J08	Tape Manager for z/VM	VMSES/E
XL C/C++ 130 for z/VM	5654-A22	XL C/C++ for z/VM	VMSES/E

---

## Appendix B. IBM Licensed Program Products Interdependencies

---

### B.1 Requisite IBM Licensed Program Product Dependencies

Figure 4 lists the pre-, co-, and if-requisites for all the z/VM SDO Licensed Products that are part of the z/VM SDO package. A requisite Licensed Product is one that is required by another Licensed Product. The extent of the requirement determines which requisite category the Licensed Product belongs in.

When re-installing a Licensed Product Y, then any Licensed Product X that has Y as a pre- or co-requisite should also be re-installed. This is recommended for every re-install.

**Note:** z/VM SDO ensures that the Pre-requisites and Co-requisites of the Licensed Products are also included in the z/VM SDO package, unless otherwise noted.

#### B.1.1 Pre-Requisites (Install-Time Full Requisite)

The absence of a pre-requisite (Y) prevents the successful installation of Licensed Product X. A pre-requisite (Y) must be installed prior to the installation of Licensed Product X; otherwise, Licensed Product X will not be installed successfully.

#### B.1.2 Co-Requisite (Run-time Full Requisite)

The absence of a co-requisite (Y) results in the full loss of the function of any Licensed Product X. This loss of function occurs at the time that Licensed Product X is used. Although Licensed Product X installed successfully, Licensed Product X will not function. A co-requisite (Y) may be installed after Licensed Product X without affecting the installation or the operation of Licensed Product X.

#### B.1.3 If-Requisites (Install-time and Run-time Part Requisites)

**Note:** Only Licensed Products supported by z/VM SDO are listed as If-requisites.

- If-requisite Needed for Install-time

The absence of an if-requisite (Y) for install results in the partial loss of function for any Licensed Product X, during the installation of Licensed Product X. Usually this loss occurs in the interface between Licensed Product X and the requisite (Y). An if-requisite for install must be installed prior to the installation of Licensed Product X; otherwise, Licensed Product X will lose some of its function.

- If-requisite Needed for Run-time

The absence of an if-requisite (Y) for run-time results in the partial loss of function for any Licensed Product X. This loss of function occurs at the time that Licensed Product X is used. Although Licensed Product X was installed successfully, some of the functions of Licensed Product X will not be available when Licensed Product X is used. An if-requisite for run-time may be installed after Licensed Product X without affecting the installation or operation of Licensed Product X.

## B.2 z/VM SDO Licensed Product Requisites Table

Figure 4 (Page 1 of 2). Product Pre-, Co-, and If-Requisites List

Product Number	Product Abbrev.	Pre-Requisites	If-Requisite (for Install)	Co-Requisite	If-Requisite (for run-time)
feature of 5654-A22	XL C/C++	HLASM			
5654-A23	Debug Tool for z/VM				
5654-010	ACF/VTAM ESA				
feature of 5654-010	APPC APPL SUITE			ACF/VTAM ESA	
5654-029	DITTO				
5654-260	EREP				
5655-T13	zSecure Manager	ISPF/DM		ISPF/DM	ISPF/PDF
5668-723	GDDM-IVU	GDDM/VM			GDDM/VM
5668-801	GDDM-IMD	GDDM/VM			GDDM/VM
5668-812	GDDM-PGF	GDDM/VM			GDDM/VM
5684-042	ICKDSF				
5684-043	ISPF/DM				
5684-123	ISPF/PDF	ISPF/DM		ISPF/PDF NLS	
feature of 5684-123	ISPF/PDF NLS	ISPF/PDF			
5684-168	GDDM/VM				
feature of 5695-013	REXX/370 Comp. Kanji	REXX/370 Compiler			
5695-013	REXX/370 Compiler			REXX/370 Library	
feature of 5695-014	REXX/370 Lib. Kanji	REXX/370 Library			
5695-014	REXX/370 Library			REXX/370 Compiler	
5696-234	HLASM				
feature of 5696-234	HLASM Toolkit	HLASM			
5697-F42	DB2 Server for VM				
feature of 5697-F42	DB2 Data Propagator	DB2 Server for VM			
feature of 5697-F42	DB2 RXSQL	DB2 Server for VM			
feature of 5697-F42	DB2 Data Restore	DB2 Server for VM			
feature of 5697-F42	DB2 Control Center	DB2 Server for VM			
feature of 5697-F42	DB2 QMF	DB2 Server for VM	GDDM/VM	GDDM/VM	ISPF/PDF GDDM-PGF

Figure 4 (Page 2 of 2). Product Pre-, Co-, and If-Requisites List

Product Number	Product Abbrev.	Pre-Requisites	If-Requisite (for Install)	Co-Requisite	If-Requisite (for run-time)
feature of 5697-F42	DB2 NLS VM Help			DB2 Server for VM	

feature of 5697-F42	DB2 Client for VM		
feature of 5697-F42	DB2 Client NLS Help		DB2 Client for VM
5697-J05	Archive Manager		REXX/370 Library
5697-J06	Backup and Restore		REXX/370 Library
5697-J08	Tape Manager		REXX/370 Library
5697-J10	Operations Manager		
5698-A36	Omegamon XE		
feature of 5741-A07	DFSMS/VM		ISPF/DM ISPF/PDF REXX/370 Compiler REXX/370 Library
feature of 5741-A07	DFSMS/VM JAPANESE	DFSMS/VM	ISPF/DM ISPF/PDF REXX/370 Compiler REXX/370 Library

## Appendix C. DASD Requirements

This appendix provides the specific sizes for the minidisks associated with each of the Licensed Products in z/VM SDO.

To obtain an estimated total amount of DASD required to install the z/VM System Delivery and selected Licensed Products please see your IBM Marketing Representative.

To estimate the size a minidisk should be in order to install the Licensed Products you have selected, total the number of blocks for each minidisk across all Licensed Products.

For example, the following Licensed Products are going to be installed:

ISPF Service Machine Work Disk	ISPVM 191	150 4K blocks
ISPF Service Machine Code Disk	ISPVM 192	6700 4K blocks
ISPVM Document Disk	MAINT 319	150 4K blocks
	TOTAL	7000 4K blocks

VMFCNVT can be used to obtain the number of cylinders required for your DASD type. Refer to *z/VM VMSES/E Introduction and Reference* for more information on using VMFCNVT.

For updates, refer to 2.3.1, "Preventive Service Planning" for PSP information.

### C.1 z/VM SDO Licensed Product DASD Requirements

<i>Figure 5 (Page 1 of 9). Product DASD Requirements</i>			
Product Number	Product Abbrev.	Minidisks	Size -CMS 4K blocks unless otherwise stated
feature of 5654-A22	XL C/C++	29E 5654A22C 2A2 5654A22C 2D2 5654A22C 19E MAINT 51D MAINT 191 5654A22C 2A6 5654A22C 2B2 5654A22C 2C2 5654A22C	81000 900 81000 81000 2700 22500 900 45000 900
<b>Note 1:</b> The amount of DASD used by the feature has been included in the DASD allocation shown for a previous feature.			

<i>Figure 5 (Page 2 of 9). Product DASD Requirements</i>			
Product Number	Product Abbrev.	Minidisks	Size -CMS 4K blocks unless otherwise stated
5654-A23	Debug Tool for z/VM	19E MAINT 51D MAINT	3600 360

		191 5654A23A	900
		29E 5654A23A	3600
		2A2 5654A23A	360
		2A6 5654A23A	360
		2B2 5654A23A	5400
		2C2 5654A23A	360
		2D2 5654A23A	2700
5654-010	ACF/VTAM ESA	51D MAINT	35
		191 5654010A	3000
		29A 5654010A	6000
		2A2 5654010A	1500
		2A6 5654010A	1500
		2B2 5654010A	11250
		2C2 5654010A	1500
		2C4 5654010A	300
		2D2 5654010A	15000
		401 5654010A	1200
		402 5654010A	1200
		493 5654010A	900
		49A 5654010A	6000
feature of 5654-010	APPC APPL SUITE	191 ANAME	1500
		191 A3270	1500
		51D MAINT	150
		191 5654025	1500
		29A 5654025	4500
		2A2 5654025	300
		2A6 5654025	300
		2B2 5654025	4500
		2C2 5654025	1500
		2D2 5654025	1500
		49A 5654025	4500
5654-029	DITTO	51D MAINT	150
		191 5654029D	2250
		2A2 5654029D	300
		2A6 5654029D	300
		2B2 5654029D	3000
		2C2 5654029D	300
		2D2 5654029D	2250
		400 5654029D	2340
		401 5654029D	2250
5654-260	EREP	201 MAINT	2250
<b>Note 1:</b> The amount of DASD used by the feature has been included in the DASD allocation shown for a previous feature.			

<i>Figure 5 (Page 3 of 9). Product DASD Requirements</i>			
Product Number	Product Abbrev.	Minidisks	Size
			<b>-CMS 4K blocks unless Otherwise stated</b>
5655-T13	zSecure Manager	51D MAINT	180
		0191 5655T13B	5400
		02A2 5655T13B	1800
		02A6 5655T13B	1800
		02B2 5655T13B	19800
		02C2 5655T13B	360
		02D2 5655T13B	7200

		100 5655T13B	19800
		200 5655T13B	19800
5668-723	GDDM-IVU	19E MAINT	150
		51D MAINT	180
		191 P68416B	180
		29E P68416B	300
		2A2 P68416B	180
		2A6 P68416B	180
		2B2 P68416B	300
		2C2 P68416B	180
		2D2 P68416B	180
5668-801	GDDM-IMD	19E MAINT	750
		51D MAINT	180
		191 P68416B	180
		29E P68416B	750
		2A2 P68416B	180
		2A6 P68416B	180
		2B2 P68416B	750
		2C2 P68416B	180
		2D2 P68416B	180
5668-812	GDDM-PGF	19E MAINT	1800
		51D MAINT	180
		191 P68416B	180
		29E P68416B	1800
		2A2 P68416B	180
		2A6 P68416B	180
		2B2 P68416B	1980
		2C2 P68416B	180
		2D2 P68416B	1260
<b>Note 1:</b> The amount of DASD used by the feature has been included in the DASD allocation shown for a previous feature.			

*Figure 5 (Page 4 of 9). Product DASD Requirements*

Product Number	Product Abbrev.	Minidisks	Size -CMS 4K blocks unless otherwise stated
5684-042	ICKDSF	19D MAINT	55 1K
		19E MAINT	775
		51D MAINT	35
		191 5684042J	1620
		29D 5684042J	360
		29E 5684042J	2700
		2A2 5684042J	360
		2A6 5684042J	360
		2B2 5684042J	1440
		2C2 5684042J	360
		2D2 5684042J	3600
5684-043	ISPF/DM	191 ISPVM	150
		192 ISPVM	6700
		319 MAINT	150
5684-123	ISPF/PDF	192 ISPVM	6000
		319 MAINT	120
feature of 5684-123	ISPF/PDF NLS	192 ISPVM	2700
		192 ISPVM	2700
		192 ISPVM	2700
		192 ISPVM	2700

5684-168	GDDM/VM	192 ISPVM	2700		
		19E MAINT 51D MAINT 191 P68416B	15000 450 15000		
		29E P68416B 2A2 P68416B 2A6 P68416B 2B2 P68416B 2C2 P68416B 2D2 P68416B	15000 450 450 13600 450 9000		
		5695-013	REXX/370 Compiler	19E MAINT 51D MAINT 101 P695013H	450 150 1200
				191 P695013H 201 P695013H 2A2 P695013H 2A6 P695013H 2B2 P695013H 2C2 P695013H 2D2 P695013H	1800 1200 300 300 1050 300 1500

**Note 1:** The amount of DASD used by the feature has been included in the DASD allocation shown for a previous feature.

*Figure 5 (Page 5 of 9). Product DASD Requirements*

Product Number	Product Abbrev.	Minidisks	Size -CMS 4K blocks unless Otherwise stated
feature of 5695-013	REXX/370 Comp. Kanji	51D MAINT 191 P695013H 2A2 P695013H 2A6 P695013H 2D2 P695013H 501 P695013H	150 150 150 150 150 300
5695-014	REXX/370 Library	19E MAINT 51D MAINT 100 P695014H 191 P695014H 200 P695014H 2A2 P695014H 2A6 P695014H 2B2 P695014H 2C2 P695014H 2D2 P695014H	600 150 600 1500 600 150 150 300 150 4500
feature of 5695-014	REXX/370 Lib. Kanji	51D MAINT 191 P695014H 2A2 P695014H 2A6 P695014H 2D2 P695014H 501 P695014H	150 150 150 150 150
5696-234	HLASM	51D MAINT 0191 P696234J 29E P696234J 2A2 P696234J 2A6 P696234J 2B2 P696234J 2C2 P696234J	180 900 1080 180 180 1800 720



		2D2 P696234J	1800
feature of 5696-234	HLASM Toolkit	51D MAINT 0191 P696234K 29E P696234K 2A2 P696234K 2A6 P696234K 2B2 P696234K 2C2 P696234K 2D2 P696234K	180 900 9000 180 180 9000 720 9000
<b>Note 1:</b> The amount of DASD used by the feature has been included in the DASD allocation shown for a previous feature.			

<i>Figure 5 (Page 6 of 9). Product DASD Requirements</i>			
<b>Product Number</b>	<b>Product Abbrev.</b>	<b>Minidisks</b>	<b>Size</b> <b>-CMS 4K blocks unless</b> <b>Otherwise stated</b>
5697-F42	DB2 Server for VM	51D MAINT 191 SQLMACH 193 SQLMACH 195 SQLMACH 200 SQLMACH 201 SQLMACH 202 SQLMACH 191 SQLUSER 191 5697F75A 193 5697F75A 195 5697F75A 2A2 5697F75A 2A6 5697F75A 2B2 5697F75A 2C2 5697F75A 2D2 5697F75A	300 1980 12600 5940 5220 1K 1260 11700 900 5400 12600 5940 2340 2340 11160 1620 9900
feature of 5697-F42	DB2 Data Propagator	191 CAPTMACH 300 CAPTMACH 51D MAINT 191 5697F74B 200 5697F74B 2A2 5697F74B 2A6 5697F74B 2B2 5697F74B 2C2 5697F74B 2D2 5697F74B	180 2160 300 720 2160 180 180 2160 180 2700
feature of 5697-F42	DB2 RXSQL	198 SQLMACH 199 SQLMACH 191 SQLUSER	540 1080 900
feature of 5697-F42	DB2 Data Restore	191 SQLDRR	1620
feature of 5697-F42	DB2 Control Center	191 MSTRSRVO 195 MSTRSRVO	2700 3600
feature of 5697-F42	DB2 QMF	51D MAINT 191 P697F4BA 2A2 P697F4BA 2A6 P697F4BA 2B2 P697F4BA 2C2 P697F4BA 2D2 P697F4BA	450 1620 360 360 4500 360 1620

		400 P697F4BA	3240
		401 P697F4BA	3240
		500 P697F4BA	3060
		501 P697F4BA	3060
<b>Note 1:</b> The amount of DASD used by the feature has been included in the DASD allocation shown for a previous feature.			

*Figure 5 (Page 7 of 9). Product DASD Requirements*

Product Number	Product Abbrev.	Minidisks	Size -CMS 4K blocks unless Otherwise stated
feature of 5697-F42	DB2 NLS VM Help	401 MAINT 402 MAINT 404 MAINT 405 MAINT 193 SQLMACH 193 5697F75A	300 300 300 300 1800 9000
feature of 5697-F42	DB2 Client for VM	51D MAINT 191 SQLCLNT 193 SQLCLNT 195 SQLCLNT 191 SQLUSER 191 5697F75C 193 5697F75C 195 5697F75C 2A2 5697F75C 2A6 5697F75C 2B2 5697F75C 2C2 5697F75C 2D2 5697F75C	300 1980 12600 5940 900 5400 12600 5940 2340 2340 11160 1620 9900
feature of 5697-F42	DB2 Client NLS Help	401 MAINT 402 MAINT 404 MAINT 405 MAINT 193 SQLCLNT 193 5697F75C	300 300 300 300 1800 9000
5697-J05	Archive Manager	Refer to Program Directory	Publication GI10-8661

*Figure 5 (Page 8 of 9). Product DASD Requirements*

Product Number	Product Abbrev.	Minidisks	Size -CMS 4K blocks unless otherwise stated
5697-J06	Backup and Restore	Refer to Program Directory	Publication GI10-8662
5697-J08	Tape Manager	Refer to Program Directory	Publication GI10-8660
5697-J10	Operations Manager	Refer to Program Directory	Publication GI10-8664
5698-A36	Omegamon XE	51D MAINT 0191 OMEGACMD 0301 OMEGACMD 0191 5698A36C 02A2 5698A36C 02A6 5698A36C 02B2 5698A36C	180 360 360 180 180 180 360

		02C2 5698A36C 02D2 5698A36C 300 5698A36C	180 360 360
feature of 5741-A07	DFSMS/VM	191 DFSMS 1A2 DFSMS 1A4 DFSMS 1A6 DFSMS 1B1 DFSMS 1B5 DFSMS 1C2 DFSMS 1C4 DFSMS 1D6 DFSMS 19D MAINT 51D MAINT	5400 300 300 300 12300 12420 300 300 7200 5600 1K 900
<b>Note 1:</b> The amount of DASD used by the feature has been included in the DASD allocation shown for a previous feature.			

<i>Figure 5 (Page 9 of 9). Product DASD Requirements</i>			
<b>Product Number</b>	<b>Product Abbrev.</b>	<b>Minidisks</b>	<b>Size -CMS 4K blocks unless otherwise stated</b>
feature of 5741-A07	DFSMS/VM JAPANESE	191 DFSMS 1A2 DFSMS 1A4 DFSMS 1A6 DFSMS 1B1 DFSMS 1B2 DFSMS 1B5 DFSMS 1C2 DFSMS 1C4 DFSMS 1D6 DFSMS 401 MAINT 51D MAINT	300 150 150 150 150 5400 150 150 150 750 4950 1K 150
<b>Note 1:</b> The amount of DASD used by the feature has been included in the DASD allocation shown for a previous feature.			

---

## Appendix D. Saved Segments

This appendix provides the recommended size, location and name for the saved segments associated with the z/VM Licensed Program Products.

For information about planning, administering and generating saved segments see the *z/VM Saved Segments Planning and Administration* manual.

It is recommended that the Section *Planning Considerations* in Chapter 1. *Planning and Defining CP Saved Segments* in the *z/VM Saved Segments Planning and Administration* manual be reviewed.

---

### D.1 z/VM SDO Program Product Segment Layout

The following table provides the recommended size, location and name for the saved segments associated with the z/VM SDO Licensed Program Products.

The segment layout specified in the table is the same layout that is utilized by IBM internally. The layout is designed to both allow for expansion and to place as many saved segments associated with the Program Products above the 16MB memory line as possible.

#### Segment Overlap

Saved segments for Licensed Program Products and z/VM Components/Features may overlap provided that the Products and/or z/VM Component/Features are not normally utilized at the same time.

The **VMFSGMAP** or **q nss map** command may be utilized to see which saved segments overlap.

#### Shared Segment Size Requirements

The shared segment size specified in the *z/VM SDO Enabling Aid* and the SDO Program Directory should be utilized when creating the shared segment for the z/VM SDO Licensed Program Products.

The information provided in the *z/VM SDO Enabling Aid* and the SDO Program Directory overrides the information provided in the Licensed Program Product's Program Directory and *PLANINFO* file. The information provided in the Program Directory and the *PLANINFO* file may not have been updated to reflect changes resulting from the IBM Service that has been applied to the Licensed Program Product or changes in the z/VM Environment.

The *z/VM SDO Enabling Aid* may be downloaded from the *z/VM SDO VnRn.0* webpage, which may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

<i>Figure 6 (Page 1 of 2). Product Segments for z/VM SDO SDO Products</i>					
<b>Product Number</b>	<b>Product Abbrev.</b>	<b>Segment Name</b>	<b>Location</b>	<b>Type</b>	<b>Space Name</b>
5654-A22	C/C++ Compiler	CCNSEG	3D000-41BFF	SR	
5654-A23	Debug Tool	SEQBSEG SEQASEG	900-9FF 2800-2EFF	SR SR	
5654-010	ACF/VTAM ESA	VTAM	D00-DFF	SR	
5668-723	GDDM-IVU	ADMIV000	3C900-3C9FF	SR	
5668-801	GDDM-IMD	ADMIM000	3BF00-3BFFF	SR	
5668-812	GDDM-PGF	ADMPG000	3B700-3BDFF	SR	
5684-043	ISPF	ISPDCSS	30000-300FF	SR	
5684-123	ISPF/PDF	ISRDCSS FLMDCSS	30200-302FF 36000-36172	SR SR	
5684-168	GDDM/REXX GDDM/VM	ERXR000 ADMXSS00	36700-367FF 3C400-3C8FF	SR SR	
5695-014	REXX/370 Library	EAGRTSEG	40000-400FF	SR	
5696-234	HLASM	ASMAPSEG	3CF00-3CFFF	SR	

<i>Figure 6 (Page 2 of 2). Product Segments for z/VM SDO SDO Products</i>					
<b>Product Number</b>	<b>Product Abbrev.</b>	<b>Segment Name</b>	<b>Location</b>	<b>Type</b>	<b>Space Name</b>
5697-F42	DB2 for VM	SQLISQL SQLRMGR SQLSQLDS SQLXRDS LANGS001 LANGS002 LANGS003 LANGS004 LANGD001 SQLISQL SQLRMGR LANGS001 LANGS002 LANGS003 LANGS004 LANGD001	B00-B5F 3A000-3A23F 900-A7F 35000-353DF A00-A4F A00-A4F A00-A4F A00-A4F A00-A4F A00-A4F B00-B5F 3A000-3A23F A00-A4F A00-A4F A00-A4F A00-A4F A00-A4F	SR SR SR SR SR SR SR SR SR SR SR SR SR SR SR SR	
5697-F42	QMF	QMF720E	36400-366FF	SR	
5741-A07	DFSMS/VM FL 221	DFSMSSEG	2200-22FF	SW	

## D.2 Creating Saved Segments Utilizing the SDO Enabling Aid

VMSES/E can be utilized to manage and create saved segments for Licensed Program Products that are in VMSES/E format. To allow for the use of VMSES/E for VMSES/E Program Product, a SDOZVM62

PRODPART file is provided as part of the *z/VM SDO Enabling Aid*. This *PRODPART* may be utilized to update the VMSES/E *SEGDATA* file with the saved segment definitions for VMSES/E formatted z/VM SDO Licensed Program Products.

### Semi-VMSES/E Formatted Program Products

Saved segments for z/VM SDO Licensed Program Products that are in Semi-VMSES/E format must be defined and created following the instructions in the Licensed Product Technical Notes Section provided for each Product.

Semi-VMSES/E formatted Licensed Program Products cannot be created utilizing VMSES/E.

To utilize the SDOZVM62 PRODPART file, the *SDO Enabling Aid* must first be downloaded to the z/VM System.

The *SDO Enabling Aid* may be downloaded from the *z/VM SDO VnRn.0* webpage. This webpage may be found off the *VM System Delivery Offering (SDO)* website at url:

<http://www.vm.ibm.com/sdo/>

After the *z/VM SDO Enabling Aid* has been downloaded to the z/VM System, the instructions found in Chapter 3. *Using VMSES/E to Define, Build and Manage Saved Segments* of the *z/VM Saved Segments Planning and Administration* manual under the Sub-Section *Adding Saved Segment Definitions for VMSES/E-Format Product* may be utilized, with the following modifications, to update the *SEGDATA* file:

- In Step 4, use **sdozvm62** as the *prodid*  
A *compname*, which represents a product component, is not required.
- Skip Step 5
- In Step 7, type in the keyword **deleted** in the DEFPARMS field for any saved segments for an Licensed Program Product that you haven't installed and are not planning to install. For z/VM 6.3 or higher the HELPSEG segment was deleted please make sure to delete it.

After you have completed Step 11, the VMFBLD Command (z/VM 5.4 or z/VM 6.2) or the PUT2PROD Exec (z/VM 6.2) may be utilized to build or delete the saved segments.

### Segment Requirements

- Segment Overlap  
Saved segments for Licensed Program Products and z/VM Components/Features may overlap provided that the Products and/or z/VM Component/Features are not normally utilized at the same time.  
The **VMFSGMAP** or **q nss map** command may be utilized to see which saved segments overlap.
- Segments Above the 16MB Memory Line  
If any part of the segment range specified on the *DEFPARMS* line in the segment definition is above the 16MB Memory Line (i.e. Page 1000 or greater), then the *GT\_16MB* must be set to **YES**

If all of the segment range specified on the *DEFPARMS* line in the segment definition is below the 16MB Memory Line (i.e. Page 0FFF or less), then the *GT\_16MB* must be set to **NO**

---

## Appendix E. Licensed Products Tapemaps

This appendix provides tapemaps of stacked VMSES/E and Semi-VMSES/E.

### E.1 Stacked Tape for VMSES/E and Semi-VMSES/E Licensed Products

The first tape file of the Licensed Product tape is created by merging the first tape files of all the products on the tape. The second tape file of the Licensed Product tape is created by merging the second tape files of all the products on the tape. Together, the first and second files form the Table of Contents (TOC) of the Licensed Product tape.

The first file on Tape File 1 will be a file with a filename of 'INS' and filetype of the 'yymm' (where 'yy' is the year and 'mm' is the month in which the tape was manufactured). This file combines the 'INS' files for all the products on the tape. The next file will be the \$\$TAPE\$\$ VMSES file, which combines all the copyright files for all the products on the tape.

Tape File 3 marks the beginning of the first product on the tape and contains only information on the first product. It can be identified by the 'prodid1 0vrmmn1' and 'prodid \$INSyymm' file. The remainder of the tape files for this product will follow in sequence.

The next product will follow, beginning with its Tape File 3, the 'prodid 0vrmmn1' and 'prodid \$INSyymm' files.

*Figure 7 (Page 1 of 2). VMSES/E and Semi-VMSES/E IBM Licensed Program Product Tape Format*

```
Tape File 1 (Combines all Tape Files 1 for all Products on
Tape)
INS 0203
$$TAPE$$ VMSES
prodid1 $PPF
prodid1 PPF
prodid1 PRODPART
prodid1 MEMO
.
.
.
prodidn $PPF
prodidn PPF
prodidn PRODPART
prodidn MEMO
```

*Figure 7 (Page 2 of 2). VMSES/E and Semi-VMSES/E IBM Licensed Program Product Tape Format*

---

```
Tape File 2 (Combines all Tape Files 2 for all Products on
Tape)
prodid1 0vrmmn1
```

```

prodid1 $PPF
prodid1 PPF
prodid1 PRODPART
prodid1 MEMO
.
.
.
prodidn 0vrmmn1
prodidn $PPF
prodidn PPF
prodidn PRODPART
prodidn MEMO
-----
Tape File 3 (Tape File 3 of first product only)
prodid1 0vrmmn1
prodid1 $INSyynn
-----
Tape File 4 (Tape File 4 of first product only)
$prodid1 MEMO
-----
Tape File 5 (Begins remaining tape files of first product)
$prodid1 Files
-----
.
.
.
-----
Tape File n (Tape File 3 of next product)
prodidn 0vrmmn1
prodidn $INSyynn
-----
Tape File n + 1 (Tape File 4 of next product)
prodidn MEMO
-----
Tape File n + 2 (Begins remaining tape files for this product)
$prodidn Files
.
.
.

```

#### Files in Tape File1 to Tape File 4

- prodid1, prodidn - Indicates the PPF file name
  - INS 'yymm' - Content directory which lists tape files for all products on this tape. 'yymm' indicates the year and month this tape was manufactured.
  - \$\$TAPE\$\$ VMSES - Contains copyright statements for all products on the tape.
- 

- prodid MEMO - The z/VM SDO memo for prodid
- prodid \$PPF - Source Product Parameter File (installation customization file) for prodid
- prodid PPF - Compiled Product Parameter File prodidN
- prodid PRODPART - Contains control information for prodidN such as resource requirements
- prodid 0vrmmn1 - the Licensed Product identifier file for prodidN The characters in the file type are defined as follows

0            Constant denoting this as part of the Licensed Product tape.



<i>v</i>	The version number of the Licensed Product
<i>r</i>	The release number of the Licensed Product
<i>m</i>	The modification level number of the Licensed Product
<i>nn</i>	The number of product files + 2 product headers + 1 tape header
<i>1</i>	The "1" indicates it is in VMSES/E format.

---

## Appendix F. z/VM 6.2 and higher Installation and Production Enablement Requirements

This appendix provides an overview of the major changes introduced in z/VM 6.2 to support a z/VM Single System Image (SSI) and the effect of the changes on the installation and Production enablement of Licensed Program Products.

---

### F.1 SSI-Enabled (Multisystem SSI Cluster) User ID Definitions

z/VM 6.2 introduced a new VM Directory ID definition statement, *IDENTITY* and changed how a System utilizes the *USER* VM Directory ID definition statement:

*USER*: An ID defined by the USER statement can only be logged on (i.e. actively logged on or in a disconnected state) a single Member in the Cluster at any given time. That is the ID *CANNOT* be concurrently logged onto more than one (1) Member in the Cluster.

*IDENTITY*: An ID defined by the IDENTITY statement can be logged onto one (1) or more Members in the Cluster at any given point in time. That is the ID can be concurrently logged onto more than one (1) Member in the Cluster.

For those Licensed Program Products that have a unique installation User ID associated with them, it is recommended that the installation ID be defined utilizing the *USER* statement.

---

### F.2 SSI-Enabled Real Device and Minidisk Management

In an SSI-Enabled environment, real DASD storage devices may be either:

*Shared:*

The real DASD storage devices are accessible by more than one System (Member) in the SSI Cluster. With Shared DASD, the DASD may be accessed from an available authorized Member in the Cluster regardless of the availability of any other authorized Member of the Cluster.

For example, in a two system SSI Cluster, Member '1' and Member '2', for DASD authorized to be accessed by both Member '1' and Member '2', the DASD may be accessed by

- Member '1' when Member '1' is available and Member '2' is not available.
- Member '2' when Member '2' is available and Member '1' is not available.
- Both Member '1' and Member '2' when both Member '1' and Member '2' are available.

*Nonshared:*

The real DASD storage devices are only accessible from a single System (Member) in the SSI Cluster. With Nonshared DASD, the DASD cannot be accessed if the single authorized Member in the Cluster is not available.

For example in a two system SSI Cluster, Member '1' and Member '2', if a Nonshared DASD is only authorized to be accessed by Member '1', then the DASD cannot be accessed by Member '2', regardless of whether Member '1' is available or not available.

Minidisks may be defined on either Nonshared or Shared DASD. If the minidisk is defined on Nonshared DASD, then the minidisk is only accessible on the Member in the SSI Cluster that DASD is authorized for.

If the minidisk is defined on a Shared DASD, then the minidisk may be accessible from all Members in the Cluster. Whether a minidisk is accessible on a specific Member in the Cluster is dependent upon whether the DASD is authorized for the Member and how the minidisk is defined in the VM System Directory.

z/VM 6.2 introduced the VM Directory *SUBCONFIGURATION* statement. The *SUBCONFIGURATION* statement must be associated with an *IDENTITY* User ID definition statement and is utilized to specify those User ID statements which apply only to the specific Member in the Cluster associated with the *SUBCONFIGURATION* statement.

Each Member in a Cluster has its own unique *SUBCONFIGURATION* statement. When a User ID logs onto a Member in the Cluster, the User ID statements under the *SUBCONFIGURATION* statement for the Member are merged with the User ID statements under the ID's *IDENTITY* statement to create the instance of the ID on the Member.

The *Scope of a Minidisk* is utilized to indicate the effect the *USER*, *IDENTITY* and *SUBCONFIGURATION* statements associated with the minidisk's *MDISK* definition statement have on the accessibility of a minidisk from the Members in a Cluster:

Scope	Cluster Accessibility	Minidisk Definition
<i>Global</i>	All Members in the SSI Cluster	<i>MDISK</i> statement under <i>USER</i> or <i>IDENTITY</i> User ID definition statement
<i>Local</i>	Single Member in the SSI Cluster	<i>MDISK</i> statement under <i>SUBCONFIGURATION</i> statement

In addition to its *Scope*, a minidisk is defined as either *Shareable* or *Nonshareable (Private)*. A *Shareable* minidisk may be concurrently linked by multiple virtual machines. A *Nonshareable* minidisk may only be accessed by a single virtual machine at any given time.

All minidisks defined by a *MDISK* statement in the VM Directory are *Shareable* regardless of whether they are defined under a *USER*, *IDENTITY* or *SUBCONFIGURATION* statement.

For those Licensed Program Products that have a unique installation minidisks associated with them, it is recommended that the minidisks be defined with a *Global Scope* on *Shared DASD*.

### F.3 Installation of Licensed Program Product into SFS Directories

Licensed Program Products may be installed either on minidisks or into a Shared File System (SFS) Filepool. Unless specified in either the SDO PD or the Licensed Program Product's PD, the default SFS Filepool for Licensed Program Products delivered under SDO, is the z/VM System Filepool *VMSYSU*

In a SSI-Enabled Environment, a separate *VMSYSU* filepool exist on each Member in the SSI Cluster.

Directories established in this filepool are unique to the Member that the directory was created on and cannot be shared across Members in the Cluster.

The recommended SFS Filepool for Licensed Program Products is *VMPSFS*. On the IBM z/VM 6.2 and higher System as delivered by IBM, the minidisks utilized for this filepool are defined on *Shared DASD* and have a *Global* scope. As a result the minidisks that comprise the *VMSYSP* filepool may be accessed from any Member in the SSI Cluster.

However, the z/VM SFS component only allows a single filepool server for a given filepool to be active (e.g. logged on) at any point in time. In addition, under z/VM, SFS filepools whose name starts with *VMSYS* are accessible only from the System that the filepool server is active on.

The SFS directories in the *VMPSFS* Filepool can be accessed from all Members in the SSI Cluster at any point in time.

If the Licensed Program Product is to be installed on other than the default filepool for the Product, the Product's PPF file must be updated with the name of the filepool that is to be utilized for the installation. For information on modifying the Licensed Program Product's PPF file refer to Chapter 3 in the *z/VM VMSES/E Introduction and Reference* manual.

---

## F.4 z/VM 6.2 and higher System Maintenance ID and System Disk Ownership

The standard system maintenance ID for z/VM 6.2 and higher is *MAINT6rm* (where *rm* is the release modification level).

The *MAINT* ID, which was the standard system maintenance ID prior to z/VM 6.2, is still defined on the z/VM 6.2 and higher system as delivered by IBM.

---

The *MAINT6rm* ID is defined utilizing an *IDENTITY* VM Directory statement which allows the *MAINT6rm* to be concurrently logged on to multiple Members in the SSI Cluster. The *MAINT* ID is defined utilizing a *USER* VM Directory statement. As a result, the *MAINT* ID can only be logged onto a single Member in the Cluster at any point in time.

The *MAINT6rm* ID and the *MAINT* ID share the same 5E5 (SES/E code disk), 51D (System Inventory disk), 319 (System document disk) and System Disks (190, 193, 19D, 19E). Therefore either the *MAINT* ID or the *MAINT620* ID may be utilized for Licensed Program Product installation, customization and Production enablement.

For example, if the Licensed Program Product instructions state that the *MAINT 19E* should be linked in *WRITE* mode as the *29E* then either a *'LINK MAINT 19E 29E MW'* or a *'LINK MAINT620 19E 29E MW'* may be utilized.

When performing Licensed Program Product installation, maintenance or Production enablement consideration must be given to the Member of the Cluster that is being utilized for the installation, maintenance or enablement, and the disk access requirements.

On the IBM delivered z/VM 6.2 System, the *MAINT620* ID owns the 5E5, 51D and 319 minidisks. These minidisks are defined on *Shared DASD* volumes which are accessible from all Members of the SSI Cluster. Therefore, the same 5E5, 51D and 319 minidisks are utilized on all Members in the SSI Cluster.

The System Disks (190, 193, 19D, 19E) are owned by the MAINT ID and are defined on *Nonshared* DASD volumes which are only accessible to a single Member in the Cluster. As a result, the System Disks are unique to each Member in the Cluster.

The z/VM 6.2 and higher System as delivered by IBM is based on the same Member of the SSI Cluster being utilized for maintenance of the all z/VM System Components. It is recommended that Licensed Program Product installation and service be performed on the same Member that is utilized for z/VM System Component service.

In addition, when the Licensed Program Product installation, customization or Production enablement instructions indicate that the MAINT ID should be utilized to perform a task, it is recommended that the MAINT6rm ID be utilized instead.

## **F.5 SSI-Enabled Environment LP Production Enablement Considerations**

The following items should be taken into consideration when Production enabling a Licensed Program Product (LP) in a Single System Image (SSI) Cluster multisystem (SSI-Enabled) environment.

### **System Minidisks and SFS Filepools**

In an SSI-Enabled environment, each Member in the cluster has its own System minidisks (MAINT 190, 193, 19D and 19E disks) and System filepools (VMSYS and VMSYSU). As a result, for Licensed Program Products that are to be utilized on more than one (1) Member in the Cluster, consideration must be given

as to whether the Licensed Program Product code is to be shared across the Members in the SSI Cluster or whether each Member in the Cluster is to have its own unique version of the Product code.

For example, for a Licensed Program Product that is normally placed on the MAINT 19E, the decision may be to place the Product on a minidisk that is shared across all Members in the Cluster.

If the decision is to continue to utilize the MAINT 190, 193, 19D or 19E disks, or the filepools VMSYS or VMSYSU than the Product must be moved to the minidisks or filepools on *EACH* Member in the Cluster that the Product will be utilized on.

### **Licensed Program Product Shared Segments**

Shared Segments are unique to each Member in the SSI Cluster and cannot be shared across Members. Therefore, if a Licensed Program Product utilizes a Shared Segment, the Segment must be created (saved) on each Member in the Cluster that the Product will be utilized on.

For some Licensed Program Products, the creation of a shared segment for the Product is optional. If the optional shared segment for a Product is created on one Member of the Cluster, it is recommended that the shared segment be created on all Members in the Cluster.

### **z/VM 6.2 and higher Shared Segments and Systems**

Dependent upon the service applied to or the customization performed on a Licensed Program Product, it may be necessary to rebuild the CMS Saved System or the z/VM System Shared Segments. Information

on rebuilding the CMS Saved System and z/VM System Shared Segments may be found in the *z/VM Service Guide*.

It is recommended that the both CMS Saved System and the z/VM System Shared Segments be rebuilt from the MAINT6rm Maintenance ID.

The following are the general commands for rebuilding CMS Saved System and the z/VM Shared Segments:

CMS Saved System

PUT2PROD SAVECMS

z/VM Shared Segments

- All z/VM Shared Segments

PUT2PROD SEGMENTS ALL

- Specific z/VM Shared Segment

PUT2PROD SEGMENTS segment\_name

In an SSI-Enabled Environment, the CMS Saved System and the z/VM System Shared Segments must be rebuilt on each Member in the Cluster.

### **z/VM 6.2 and higher DASD Format and Directory Maintenance Utilities**

With z/VM 6.2 and higher the following utilities components have been moved from the *MAINT 190 (System CMS Disk)* to a new disk, *PMAINT 551*.

CPFMTXA EXEC

CPRMTXA MODULE

DIRECTXA MODULE

DIRMAP MODULE

DISKMAP EXEC

FORMSSI MODULE

The *PMAINT 551* is defined on a *Shared DASD* and is available on all Members in the SSI Cluster.



## Bibliography

*z/VM Program Directory* (GI13-4358)

*z/VM Installation Guide* (GC24-6292)

*z/VM General Information* (GC24-6286)

*z/VM VMSES/E Introduction and Reference*  
(GC24-6336)

*z/VM Service Guide* (GC24-6325)

*z/VM CMS Commands and Utilities Reference*  
(SC24-6260)

*z/VM CP Planning and Administration* (SC24-6271)

*z/VM System Operation* (SC24-6326)

*z/VM CMS File Pool Planning, Administration, and  
Operation* (SC24-6261)

*z/VM CMS and REXX/VM Messages and Codes*  
(GC24-6255)

*z/VM CP Messages and Codes* (GC24-6270)

*z/VM Other Components Messages and Codes*  
(GC24-6300)

*z/VM Saved Segments Planning and Administration*  
(SC24-6322)

---

## Reader's Comments

### Program Directory for System Delivery Offering Version 6.2 and higher (including Version 7)


You may use the VM Feedback page (Contact z/VM) on the z/VM Web site at:

[www.vm.ibm.com/forms/](http://www.vm.ibm.com/forms/)

to comment about this document, its organization, or subject matter.

Please understand that your feedback is of importance to IBM, but IBM makes no promise to always provide a response to your feedback. When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

**IBM**



6I13-4375-00