

z/VM
7.3

DFSMS/VM Messages and Codes



Note:

Before you use this information and the product it supports, read the information in [“Notices” on page 211.](#)

This edition applies to version 7, release 3 of IBM® z/VM® (product number 5741-A09) and to all subsequent releases and modifications until otherwise indicated in new editions.

Last updated: 2023-12-09

© **Copyright International Business Machines Corporation 1991, 2023.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Tables..... V

About This Book.....vii

How to provide feedback to IBM.....ix

Summary of Changes for z/VM: DFSMS/VM Messages and Codes.....xi

Chapter 1. Introduction to DFSMS/VM Messages and Codes.....1

Chapter 2. DFSMS/VM DGT Messages..... 9

Chapter 3. DFSMS/VM FSM Messages.....35

Chapter 4. DFSMS/VM IGD Messages..... 157

Chapter 5. DFSMS/VM Return and Reason Codes..... 179

Notices.....211

Bibliography..... 215

Tables

1. ACS Routine Return Codes.....	179
2. ISMF Standard Return Codes.....	179
3. DFSMS Command Processor Return Codes.....	208
4. CP Completion Status.....	209

About This Book

This book contains explanations and suggested actions for messages and codes issued by Data Facility Storage Management Subsystem/VM (DFSMS/VM), an IBM® z/VM® feature that improves productivity by providing storage management for Shared File System (SFS) and Removable Media Services (RMS), and by easing the task of moving minidisks from one physical device to another.

For a description of the message format for the master virtual machines, server virtual machines, and the DFSMS commands, see [“DFSMS/VM Message Format”](#) on page 2. For a description of the ISMF message format, see [“ISMF Message Format”](#) on page 1.

For error messages issued by the master virtual machines, server virtual machines, or the DFSMS commands, see:

- [Chapter 2, “DFSMS/VM DGT Messages,”](#) on page 9, for messages from issuing DFSMS/VM commands with explanations and suggested actions.
- [Chapter 3, “DFSMS/VM FSM Messages,”](#) on page 35, for messages from a DFSMS/VM server with explanations and suggested actions.
- [Chapter 4, “DFSMS/VM IGD Messages,”](#) on page 157, for messages from Automatic Class Selection (ACS) routine processing with explanations and suggested actions.
- [“ACS Routine Return Codes”](#) on page 179, for a table listing the standard ACS return codes.
- [“ISMF Return and Reason Codes”](#) on page 179, for Interactive Storage Management Facility (ISMF) return and reason codes.
- [“DFSMS/VM Return Codes”](#) on page 208, for DFSMS command return codes, IUCV return codes, and CP return codes, that appear in DFSMS/VM messages.

Intended Audience

This manual is intended for anyone who needs to understand the messages and codes issued by DFSMS/VM.

Where to Find More Information

See [“Bibliography”](#) on page 215 at the back of this book.

Links to Other Documents and Websites

The PDF version of this document contains links to other documents and websites. A link from this document to another document works only when both documents are in the same directory or database, and a link to a website works only if you have access to the Internet. A document link is to a specific edition. If a new edition of a linked document has been published since the publication of this document, the linked document might not be the latest edition.

How to provide feedback to IBM

We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information. See [How to send feedback to IBM](#) for additional information.

Summary of Changes for z/VM: DFSMS/VM Messages and Codes

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line (|) to the left of the change.

GC24-6276-73, z/VM 7.3 (December 2023)

This edition includes terminology, maintenance, and editorial changes.

GC24-6276-73, z/VM 7.3 (September 2022)

This edition supports the general availability of z/VM 7.3. Note that the publication number suffix (-73) indicates the z/VM release to which this edition applies.

GC24-6276-01, z/VM 7.2 (September 2020)

This edition supports the general availability of z/VM 7.2.

GC24-6276-00, z/VM 7.1 (September 2018)

This edition supports the general availability of z/VM 7.1.

Chapter 1. Introduction to DFSMS/VM Messages and Codes

This chapter contains information to help you understand the messages and codes issued by Data Facility Storage Management Subsystem/VM (DFSMS/VM). The information describes the message format and explains how you can display DFSMS/VM messages.

Messages and codes describe the results of processing and are issued by:

- DFSMS/VM commands
- DFSMS and RMS (removable media services) virtual machines
- Interactive Storage Management Facility (ISMF)
- Interactive Systems Productivity Facility (ISPF)

DFSMS/VM Virtual Machines

When you issue a DFSMS/VM command, or use ISMF, DFSMS/VM handles your request through virtual machines. The following are functions that these virtual machines provide:

- Minidisk management, which includes the MOVE and CHECK commands, and the building of minidisk lists for the ISMF Minidisk Application. This is handled by the DFSMS master and minidisk server machines.
- Space management, which implements DFSMS storage management on Shared File System (SFS) files; this includes migration or expiration as determined by their management class. This is handled by the DFSMS master and server machines.
- Removable media management, which provides services to the IBM 3495 Tape Library Dataserver. This is handled by the RMS master virtual machine.

Message Formats

Messages consist of a message identifier (for example, FSM0509E) and message text. The identifier distinguishes messages from each other. The text describes a condition that has occurred and may suggest an action to the user.

The following sections describe the message formats used by DFSMS/VM components.

ISMF Message Format

The format of ISMF messages is

DGTxxnnn

where:

DGT

is the prefix that indicates a DFSMS/VM message

xx

is a two-character ISMF function identifier

nnn

is the message number

ISMF message explanations can be found online. For ISMF return and reason codes associated with ISMF messages see, [“ISMF Return and Reason Codes” on page 179](#).

DFSMS/VM Message Format

The format of master virtual machine, server virtual machine, and DFSMS/VM command messages is

###xxxnnns

where:

###

is the prefix that indicates a DFSMS/VM message. DFSMS/VM message prefixes are:

- DGT
- FSM
- IGD

xxx

is a three-character control section (CSECT) identifier that is requested by the IBM service representative if assistance is required.

nnnn

is the message number.

s

is one of the following severity codes:

- I = Informational
- W = Warning
- E = Error
- S = Severe error

Message Variables

The following are some of the variables used in the message explanations:

Variable

Meaning

Blocknumber

Number of a conversational monitor system (CMS) block

Catname

1-to-32 character category name that identifies a logical grouping of removable media volumes

CSL routine

Assembler program that resides in a callable services library and that can be invoked from an application program to do a specific function

Devtype

IBM device type

Dirid

Identifier for a Shared File System directory

File pool

Collection of minidisks managed by a Shared File System

Fn

File name

Ft

File type

Fm

File mode

Fileid

Fn ft [fm] or [directory ID]

Hex value

Value displayed in hexadecimal format

Libname

1-to-32 character name that identifies the tape library data server

Line number

Record number in the DFSMS/VM control file for which the message has been issued

Operation

Event or specific action performed by a logic element

Option

Keyword that controls the processing of the command

Pathid

Virtual machine path identification

Rdev

Real device address

Reason code

A number generated by the application being executed which provides additional information about an error or condition

Return code

A number generated by the application being executed which describes the result of processing a DFSMS/VM request

Request identifier

Unique identifier assigned to a DFSMS/VM request

Routine number

Unique number assigned to DFSMS/VM external processing

Server

Virtual machine that receives requests from the master virtual machine, executes requested operations, and reports status back to the master virtual machine

Step number

Identifier for the current operation being processed for a MOVE or CHECK command

Userid

One- to eight-character name that identifies the user

Vdev

One- to four-digit hexadecimal number that represents a virtual device number

Vlabel

Six character external volume label

Displaying Messages

The following sections summarize how you display ISMF and DFSMS/VM messages. Online DFSMS/VM message help information is available from the CMS command line and is useful for obtaining immediate information on a message.

ISMF Messages

When an error occurs while you are using ISMF, a short message appears at the right corner of the current panel as in [Figure 1 on page 3](#):

```
COMMAND ==>>
MINIDISK SELECTION PANEL LIST DOES NOT EXIST
SELECT SOURCE OF MINIDISK LIST ==>> 1 (1 - saved list, 2 - new list)
```

Figure 1. Sample Short Message

Messages produced by ISMF have a message prefix of DGT and are eight characters long.

1. If you need more information about the error, press **PF1** or enter the **HELP** command. A long message, such as the one shown in [Figure 2 on page 4](#) appears.

```
COMMAND ==>
MINIDISK SELECTION PANEL          LIST DOES NOT EXIST
The specified list does not exist because it was not saved
SELECT SOURCE OF MINIDISK LIST ==> 1      (1 - saved list, 2 - new list)
```

Figure 2. Sample of a Long Message

2. To obtain additional information, press **PF1** again. A message panel appears, such as the one shown in [Figure 3 on page 4](#). Message panels contain the message number, the short message, the long message, and an explanation of the error, along with a suggested action.

```
HELP-----ISMF MESSAGE-----HELP
COMMAND ==>

MESSAGE NUMBER:  DGTJM006

SHORT MESSAGE:   LIST DOES NOT EXIST

LONG MESSAGE:    The specified list does not exist because it was not
                  saved

EXPLANATION:
  The saved list generation did not execute successfully because the
  list does not exist in the output table library.  It is possible that
  you did not use the SAVE command to save the list or due to an
  unexpected ISMF internal error, the list was not saved.

SUGGESTED ACTION:
  Use the SAVE command on the list panel to save the list.  Then you
  will be able to generate the saved list by using the list name.  If
  the error persists, contact your system programmer or IBM for
  assistance.

Use ENTER to continue with ISMF HELP, Use END to return to ISMF.
```

Figure 3. Sample of a Message Panel

Messages produced by ISPF have a message prefix of ISP or ISR. If ISPF issued the message and the help panel does not indicate how to correct the error, see the *ISPF Dialog Management Guide*.

3. Enter the ISMF **ERTB** command to display the ISMF Error Table Display panel. This panel retrieves message IDs, return codes, and reason codes associated with the problem.
4. Look up the return codes, and reason codes in [“ISMF Return and Reason Codes” on page 179](#).
5. Ensure that the ISPF log is active and examine it for additional information. The level of information contained in the ISPF log depends on the settings you have specified in your ISMF user profile.

DFSMS/VM Messages

DFSMS/VM issues messages from the DFSMS/VM virtual machines. DFSMS/VM can place messages in a log file, the virtual machine’s console, or both. You can select the logging of messages with one of two pairs of control statements:

- DFSMS_LOG_TO_FILE
- DFSMS_LOG_TO_CONSOLE

or

- RM_LOG_TO_FILE
- RM_LOG_TO_CONSOLE

The control statements prefixed with DFSMS apply to logging in the DFSMS master and server virtual machines. Statements prefixed with RM apply to logging in the RMS master.

When LOG_TO_FILE is selected, specify an SFS file space where the log file can be maintained.

DFSMS/VM logs a message to the log file or console according to its severity and the severity specified in the control statement.

DFSMS/VM presents messages in four categories: severe, error, warning, and informational. The message category is indicated by a severity code letter in each message: S, E, W, or I, respectively. The severity codes are defined as follows:

Category
Meaning

Severe

A component of DFSMS/VM abends or otherwise stops because of some condition.

Error

DFSMS/VM cannot perform a function because of an unexpected condition.

Warning

DFSMS/VM performs the function correctly, but the results may not be what the command issuer expects.

Informational

DFSMS/VM performs the function correctly, and the results are what the command issuer expects.

You must specify logging of at least severe messages with one of these keywords. The recommended setting of the DFSMS_LOG_TO_FILE keyword or RM_LOG_TO_FILE keyword is 3. By choosing a setting of 3, you retain a record of severe, error, and warning messages, while maintaining efficient response time on DFSMS/VM. The recommended setting of the DFSMS_LOG_TO_CONSOLE keyword or RM_LOG_TO_CONSOLE keyword is 4. By choosing a setting of 4, you retain a complete record of DFSMS/VM processing. See *z/VM: DFSMS/VM Customization* for additional information about control file keywords.

You can capture the messages displayed on the console by putting the following statement in the PROFILE EXEC of the virtual machine before starting DFSMS/VM, or you can enter the following on the command line:

```
CP SPOOL CON START *
```

Note: Be aware that when spooling the console to a file, the file size can increase rapidly, consuming large amounts of spool space.

Following is an example of an SMS and minidisk log file.

Note: The highlighted column headings are not part of the log file. They are included only to clarify the log file contents and format.

Date of Message YYYYMMDD	Time of Message HHMMSS	Request ID	Message
19930913	083043	0000003	FSMEIF1211I DFSMS DETERMINE MANAGEMENT CLASS received from
19930913	083043	0000003	user KEN, request identifier = 3
19930913	083048	0000021	FSMEIF1211I DFSMS DETERMINE MANAGEMENT CLASS received from
19930913	083048	0000021	user DON, request identifier = 21

Note: When reviewing the log file, be sure to access the current day's log file with the NOLOCK option because DFSMS/VM keeps a lock on the current day's file.

Reviewing Console Logs

To review a console log file, do the following:

1. Log on to the DFSMS/VM virtual machine in question.
2. Enter

```
Begin
```

to resume operation in the virtual machine.

3. Enter

```
#CP SP CONS CLOSE TO userid
```

to send the console file of the virtual machine to a specific user ID.

4. On the owner user ID's virtual machine, browse the console log file for error messages.

The message format is

DGTxxxnnns

or

FSMxxxnnns

or

IGDxxxnnns

where:

xxx represents a three-character control section (CSECT) identifier requested by the IBM service representative if assistance is required.

nnnn is the message number.

s indicates the severity of the error (I=Informational, W=Warning, E=Error, S=Severe).

CP and CMS messages also appear in the console file.

5. Locate the error message either with online help or this manual. You will find explanations and suggested actions accompanying the error message.
6. If a message found on a DFSMS/VM virtual machine console file indicates a problem on another DFSMS/VM virtual machine, then check the indicated DFSMS/VM virtual machine.

Online HELP for Messages

Online help for messages is available from the CMS command line. The z/VM HELP facility can assist you by letting you conveniently display information about DFSMS/VM messages. Help text for messages is displayed when you invoke:

```
HELP cccnnns
```

or

```
HELP cccmmnnns
```

Where:

ccc is the component ID of the message (DGT, FSM, IGD)

mmm is the optional module identifier

nnnn is the message number

s is the message severity

See [z/VM: CMS Commands and Utilities Reference](#) for additional information about the z/VM HELP facility.

DFSMS COPY and DFSMS CHECK Commands

When the full error message function is in effect and you issue a DFSMS COPY or DFSMS CHECK command under CMS, messages are displayed on your terminal. For full error message function, issue the CP command SET EMSG ON after you log on. You can request that messages be held in a file and sent to your reader by specifying options with DFSMS COPY and DFSMS CHECK commands. Refer to the *z/VM: DFSMS/VM Storage Administration* for the options and syntax to request a message file. The message file allows you to perform the following:

1. You can look through the file for any DFSMS COPY or DFSMS CHECK command messages.
2. Look up message explanations and suggested actions for DFSMS COPY or DFSMS CHECK command messages in Chapter 2, “DFSMS/VM DGT Messages,” on page 9.

Displaying Messages in Other Languages

All messages documented in this book are in American English; however, most messages are displayed at your terminal in the language set for your virtual machine. If your virtual machine is set to another language, you will receive most messages in that language.

Messages within the FSM9900 to FSM9999 range are only displayed in American English.

Contacting the IBM Support Center

DFSMS/VM message help explanations may suggest that you contact the IBM Support Center for additional help with processing errors. When the proper diagnostic procedures have been followed and user specifications have been checked for accuracy, you should then contact the IBM Support Center for further assistance and supply this information:

- Customer number
- Processor number such as type, model, and serial
- Component ID of DFSMS/VM
- Current DFSMS/VM function level
- Current DFSMS/VM service level (list of PTFs that have been applied and the associated APAR)
- A brief description of the problem which includes type of failure, abend codes, exception codes, message numbers and text, and routine names

If the IBM Support Center representatives cannot immediately resolve the problem, they may pass the problem call to the DFSMS/VM Level 2 support group. When the support group representatives contact you, they will request that you have certain documentation at hand to aid in the diagnosis of the problem. Therefore, keep the following for possible future reference:

- System console log from around the time the problem occurred
- Dump information
- Log files
- Report files
- Command text as entered
- Messages in question
- For a wait or loop failure, all the data that was gathered while determining a wait/loop
- For a documentation failure, the location of the error in the manual and a description of the problem it caused
- ISPF transaction logs with problem related information
- Copy of DFSMS/VM control file (DGTVCNTL DATA)

If you wish to supply IBM this information on tape, use the VMFPLC2 or TAPE command to transfer it to tape.

You will also be asked to supply various types of information that describe the DFSMS/VM functions used, environment, and activities. Applicable items of information from the following list may also be requested:

- Copy of master or server virtual machine directory definitions
- Copy of PROFILE EXEC of master or server virtual machines if it is not the one supplied by IBM
- Copy of directory definitions of SFS servers used by DFSMS/VM for secondary storage
- Copy of DMSPARMS file for SFS servers
- Copy of the source configuration file
- Copy of any installation-wide exits you are using that are not what was originally shipped with DFSMS/VM

Component Identification

The component identifier is a number that identifies DFSMS/VM within the IBM software support database. For DFSMS/VM, the component ID is 570611601.

Function Level

To determine the function level of DFSMS/VM, enter the following on the user's virtual machine:

```
DFSMS QUERY DFSMSLEVEL
```

A message is displayed indicating the function level of DFSMS/VM.

Chapter 2. DFSMS/VM DGT Messages

DGT0001E **Error, no file mode specified**

Explanation

No file mode has been specified in the DFSMS COPY command. This is a required parameter. DFSMS COPY issues return code = 24.

Suggested Action

Check the input to DFSMS COPY.

DGT0002E **Error, no virtual device address specified**

Explanation

No address has been specified in the DFSMS COPY command. This is a required parameter. DFSMS COPY issues return code = 24.

Suggested Action

Check the input to DFSMS COPY.

DGT0003E **Option *option* invalid**

Explanation

An invalid option, as specified by *option*, has been specified in the DFSMS COPY command. DFSMS COPY issues return code = 24.

Suggested Action

Check the input to DFSMS COPY.

DGT0004E **File mode *fm* is not CMS format**

Explanation

An attempt has been made to copy a minidisk with DFSMS COPY that is not CMS format. *Fm* is the file mode. DFSMS COPY issues return code = 36.

Suggested Action

DFSMS COPY cannot copy non-CMS format. Use a data mover appropriate to the type of data on the minidisk.

DGT0005E **Disk *vdev* not ACCESSed**

Explanation

The source minidisk must be accessed before DFSMS COPY processing can start. Since the source minidisk is not accessed, DFSMS COPY issues return code = 36.

Suggested Action

ACCESS the source minidisk prior to invoking the DFSMS COPY command.

DGT0006E **Input disk *vdev* = output disk**

Explanation

The source and target minidisk virtual addresses are the same. *Vdev* is the minidisk virtual address. DFSMS COPY issues return code = 24.

Suggested Action

Check the input given to DFSMS COPY.

DGT0007E **Insufficient free storage**

Explanation

There is not enough virtual storage available to process the DFSMS COPY command. Since processing cannot occur, DFSMS COPY issues return code = 104.

Suggested Action

Invoke DFSMS COPY with a smaller OPTimize (1 or 2) value. The default is OPTimize(3). OPTimize(1) and OPTimize(2) require less virtual storage, but the time to move the data increases. See the *z/VM: DFSMS/VM Storage Administration* for information regarding COPY and the OPTimize option.

DGT0008E **File mode *fm* invalid**

Explanation

The file mode of the source minidisk is not a valid value for a CMS file mode. Due to the invalid file mode, DFSMS COPY issues return code = 24.

Suggested Action

Check the input to DFSMS COPY.

DGT0009E ***Vdev* is an invalid minidisk address**

Explanation

The virtual address of the target minidisk is invalid. DFSMS COPY issues return code = 24.

Suggested Action

Check the input to DFSMS COPY.

DGT0010E *Vdev is read-only*

Explanation

The target minidisk supplied to DFSMS COPY is LINKed read-only. DFSMS COPY issues return code = 36.

Suggested Action

Check the input to DFSMS COPY. If a copy of the minidisk is needed, retry the request after linking to the minidisk as read/write and accessing it.

DGT0011E **Output minidisk will not hold
number of blocks blocks**

Explanation

The target minidisk does not hold as many CMS blocks as are contained on the source minidisk. DFSMS COPY issues return code = 256.

Suggested Action

Check the input to DFSMS COPY. Provide a target minidisk with sufficient CMS blocks.

DGT0012E **Input and output not same device
class**

Explanation

Both the source and target minidisks are not the same format. DFSMS COPY issues return code = 24.

Suggested Action

Use CMS FORMAT and CMS COPYFILE to copy this minidisk instead of DFSMS COPY.

DGT0013E **"NOERASE" option can be used
only with FBA**

Explanation

The NOERASE option is only valid for FBA format DASD. DFSMS COPY issues return code = 24.

Suggested Action

Check the input to DFSMS COPY.

DGT0014E **Device vdev not supported**

Explanation

Either the source minidisk or target minidisk is on a DASD not supported by DFSMS COPY. DFSMS COPY issues return code = 24.

Suggested Action

Use the combination of CMS FORMAT and CMS COPYFILE to copy this minidisk instead of DFSMS COPY.

DGT0015E **Device address vdev is invalid**

Explanation

An attempt to acquire information about the specified virtual device has failed. Information is acquired by CP Diagnose X'24'. Either there is a virtual device, but no associated real device, or the virtual device does not exist. This message may be received if an attempt to copy an accessed minidisk, when the underlying CP virtual address has been detached, is made. DFSMS COPY issues return code = 100.

Suggested Action

Check the input to DFSMS COPY.

DGT0016E **Device vdev not attached**

Explanation

The virtual address is detached or redefined while DFSMS COPY is in operation. DFSMS COPY issues return code = 100.

Suggested Action

Check to see if operation of DFSMS COPY has been interrupted. If it has been running in a minidisk server, check the console log of that server.

DGT0017E **Device vdev busy or an interrupt
pending**

Explanation

A Diagnose I/O request issued by DFSMS COPY has received condition code 1 while executing a channel program. DFSMS COPY issues return code = 100.

Suggested Action

Check to see if operation of DFSMS COPY has been interrupted. If it has been running in a minidisk server, check the console log of that server.

DGT0018E **Wrong-length record found on device *vdev* at *var1 var2***

Explanation

A record read from the source minidisk is not the same length as the source minidisk CMS block size. This means the source minidisk is not formatted for CMS use. DFSMS COPY issues return code = 100.

Suggested Action

Request DFSMS CHECK on the source minidisk to ensure the source minidisk is intact.

DGT0019E **Unit exception on device *vdev* at *var1 var2***

Explanation

A Diagnose I/O request, issued by DFSMS COPY, has received condition code 2 while executing a channel program. This may mean that the source minidisk is not correctly formatted for use by CMS. DFSMS COPY issues return code = 100.

Suggested Action

Run DFSMS CHECK on the source minidisk to ensure the source minidisk is intact.

DGT0020I **Copying block *var1* of *var2***

Explanation

This informational message is produced when the STATUS option is specified on DFSMS COPY.

Suggested Action

None.

DGT0021E **Permanent I/O error on device *vdev* at *var1 var2***

Explanation

A permanent I/O error has occurred while trying to read or write a minidisk. The device address is displayed. DFSMS COPY issues return code = 100.

Suggested Action

Check to see if a DASD I/O error message has been sent to the system operator. You may also want to run EREP to see if any permanent errors have been logged. Refer to *z/VM: System Operation* for more information. The volume containing the affected minidisk may need repair.

DGT0022E **CSW = *var1 var2*, CCW = *var3 var4***

Explanation

A permanent I/O error has occurred while trying to read or write a minidisk. The CSW and the last CCW are displayed. DFSMS COPY issues return code = 100.

Suggested Action

Check to see if a DASD I/O error message has been sent to the system operator. You may also want to run EREP to see if any permanent errors have been logged. Refer to *z/VM: System Operation* for more information. The volume containing the affected minidisk may need repair.

DGT0023E **Sense bytes 0-3 = *sense bytes***

Explanation

A permanent I/O error has occurred while trying to read or write a minidisk. The first four sense bytes are displayed. DFSMS COPY issues return code = 100.

Suggested Action

Check to see if a DASD I/O error message has been sent to the system operator. You may also want to run EREP to see if any permanent errors have been logged. Refer to *z/VM: System Operation* for more information. The volume containing the affected minidisk may need repair.

DGT0024E **Internal error. BUFENTRY overlay at *work area storage***

Explanation

An internal DFSMS error has occurred.

Suggested Action

Contact the IBM Support Center and provide the message header and the *work area storage*.

DGT0025E **Internal error**

Explanation

An internal DFSMS error has occurred.

Suggested Action

Contact the IBM Support Center and provide the message header.

DGT0026E **Work area storage overlay at *work area storage***

Explanation

An internal DFSMS error has occurred.

Suggested Action

Contact the IBM Support Center and provide the message header and *work area storage*.

DGT0027W **SKIP not available, var1 not RW or EDF**

Explanation

The SKIP option can only be honored by DFSMS COPY if the source minidisk is linked read/write and is not an 800-byte block. DFSMS COPY issues return code = 4.

Suggested Action

LINK the source minidisk as read/write. Access the source disk and invoke DFSMS COPY again.

DGT0028I **Command *command* gave return code = *return code***

Explanation

This message is produced when the DFSMS COPY command processing stops. DFSMS COPY issues the return code returned by the routine it has called.

Suggested Action

None.

DGT0029E **No value given for option *option***

Explanation

No value has been provided for a keyword to the data mover in the minidisk server. DFSMS COPY issues return code = 24.

Suggested Action

Check the input to DFSMS COPY.

DGT0030E **Error, return code = *return code* when writing *fileid***

Explanation

The CMS file system has encountered the return code shown when attempting to write the file called for by the FILE, FOR, and AS options. Processing of DFSMS COPY continues, but no additional messages are written to the CMS file. DFSMS COPY issues the return code returned by CMS FSWRITE.

Suggested Action

Check the input to the DFSMS COPY command. The user ID specified by FOR *userid* and the virtual address specified by AS *vdev* are used to generate a CMS file name and type. Also, see if the minidisk referenced by the file mode containing the file output is out of space.

DGT0032E **Internal error. CCWAREA overlay at *work area storage***

Explanation

An internal DFSMS error has occurred.

Suggested Action

Contact the IBM Support Center and provide the message header and *work area storage*.

DGT0033E **BLKSIZE *blocksize* not valid for device *vdev***

Explanation

The block size of the source minidisk is not valid for the target minidisk. For example, 800 is not a valid block size for the device. DFSMS COPY issues return code = 88.

Suggested Action

The source minidisk must be copied to the target minidisk with a target block size value that is valid. This is done automatically by ISMF when reblocking is requested in the ISMF Move Entry panel.

DGT0034E **Missing record**

Explanation

DFSMS COPY detects that one or more CMS blocks has not been read from the source minidisk during a read operation that produced no I/O error. This can be caused by missing records on a track that is part of a CMS minidisk, or by device malfunction. DFSMS COPY issues return code = 100.

Suggested Action

Request DFSMS CHECK on the source minidisk to ensure that the source minidisk is intact.

DGT0035I ***Var1 var2***

Explanation

This is an informational message issued by DFSMS COPY.

Suggested Action

None.

DGT0048E CP/CMS size mismatch for device *vdev*

Explanation

A size mismatch between CP and CMS for the device has occurred.

Suggested Action

Consult *z/VM: CP Commands and Utilities Reference* and *z/VM: CMS Commands and Utilities Reference* to resolve the problem.

DGT0051E Input minidisk is damaged, COPY cannot proceed

Explanation

DFSMS COPY is unable to collect critical information from the input minidisk to start the copy. DFSMS COPY issues return code = 104.

Suggested Action

Run DFSMS CHECK on the source minidisk to see if the minidisk is intact.

DGT0052E Insufficient work space on source minidisk

Explanation

When copying from FBA to ECKD™, DFSMS COPY detects that the input minidisk is 100% full. DFSMS COPY issues return code = 24.

Suggested Action

Erase unused files from the source minidisk and then reissue DFSMS COPY.

DGT0053E Critical error has occurred, DFSMS COPY cannot continue

Explanation

DFSMS COPY cannot continue due to a critical error, such as an error in writing the label. DFSMS COPY issues return code = 104.

Suggested Action

Run DFSMS CHECK on the source minidisk to see if the minidisk is intact.

DGT0100I File: *fileid* Block: *blocknumber* - block number out of range

Explanation

Fileid, which includes the file name and file type, in the block has an invalid record length or *blocknumber*; the block number is not valid because it is larger than the maximum number of blocks on the minidisk. DFSMS CHECK issues return code = 4.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk or an SFS file space. Then reformat the source disk and copy the files back.

DGT0101E *Vdev* is an invalid minidisk address

Explanation

Vdev is the input virtual address to be checked and is invalid. DFSMS CHECK issues return code = 24.

Suggested Action

Verify the input to DFSMS CHECK is correct. Reissue the command.

DGT0102E Error, return code = *return code* when writing *fileid*

Explanation

Return code is the error return code from FSWRITE. *Fileid* is the file name and file type of the file being written when the error occurred. The CMS file system returns *return code* when trying to write the file called for by the FILE option. Execution of DFSMS CHECK continues, but all messages are written to the console instead of the CMS file. DFSMS CHECK issues the return code returned by FSWRITE.

Suggested Action

The input user ID or virtual address may be invalid, or there may not be enough room to write out the file. Check the input to the DFSMS CHECK command and reissue the request.

DGT0103E Device address *vdev* is invalid

Explanation

The virtual address defined by *vdev* is detached or redefined while DFSMS CHECK is in operation. DFSMS CHECK issues return code = 100.

Suggested Action

Check to see if operation of DFSMS CHECK has been interrupted. If it has been running in a minidisk server, check the console log of that server.

DGT0104E **Address: *vdev* Device Type: *device type* Date Created: *creation date***

Explanation

This is an informational message issued by DFSMS CHECK indicating the address, device type, and creation date.

Suggested Action

None.

DGT0105I **Valid: *volume id* Block size: *block size* Last Changed: *date last changed***

Explanation

This is an informational message issued by DFSMS CHECK indicating the volume ID, block size, and date last changed.

Suggested Action

None.

DGT0106I **Cyls: *number of cylinders* Usable Cyls: *number of usable cylinders***

Explanation

This is an informational message issued by DFSMS CHECK indicating the number of cylinders and number of usable cylinders.

Suggested Action

None.

DGT0107I **Total number of CMS blocks: *number of CMS blocks***

Explanation

This is an informational message issued by DFSMS CHECK indicating the total number of CMS blocks.

Suggested Action

None.

DGT0108I **Number of CMS blocks used: *number of blocks (percent used%)***

Explanation

This is an informational message issued by DFSMS CHECK indicating the number of blocks used.

Suggested Action

None.

DGT0109I **CMS blocks counted: *number of blocks***

Explanation

This is an informational message issued by DFSMS CHECK indicating the number of CMS blocks counted.

Suggested Action

None.

DGT0110I **Blocks in allocation map: *number of blocks***

Explanation

This is an informational message issued by DFSMS CHECK indicating the number of blocks in allocation map.

Suggested Action

None.

DGT0111W **Number of CMS blocks used: *number of blocks (percent used%)***

Explanation

This a warning message issued by DFSMS CHECK indicating the number of CMS blocks used.

Suggested Action

None.

DGT0112I **CMS blocks counted: *number of blocks* <- These three numbers**

Explanation

This is an informational message issued by DFSMS CHECK indicating the number of CMS blocks counted.

Suggested Action

None.

DGT0113I **Blocks in allocation map: *number of blocks* <- should be identical**

Explanation

This is an informational message issued by DFSMS CHECK indicating the number of blocks in allocation map.

Suggested Action

None.

DGT0114I **Lost CMS blocks: *number of CMS blocks***

Explanation

This is an informational message indicating the number of lost CMS blocks.

Suggested Action

None.

DGT0115I **Invalid CMS blocks: *number of CMS blocks***

Explanation

This is an informational message indicating the number of invalid CMS blocks.

Suggested Action

None.

DGT0116I **Overlapping CMS blocks: *number of CMS blocks***

Explanation

This is an informational message indicating the number of overlapping CMS blocks.

Suggested Action

None.

DGT0117I **Disk origin pointer: *disk origin pointer***

Explanation

This is an informational message issued by DFSMS CHECK indicating the disk origin pointer.

Suggested Action

None.

DGT0118I **Files reported in directory: *number of files (Including DIRECTOR and ALLOCMAP)***

Explanation

This is an informational message issued by DFSMS CHECK indicating the files reported in the CMS directory.

Suggested Action

None.

DGT0119I **Number of files found: *number of files***

Explanation

This is an informational message issued by DFSMS CHECK indicating the number of files found.

Suggested Action

None.

DGT0120I

Explanation

This is a blank line issued by DFSMS CHECK.

Suggested Action

None.

DGT0121E **Insufficient free storage**

Explanation

There is not enough virtual storage available to execute the DFSMS CHECK command. DFSMS CHECK issues return code = 104.

Suggested Action

Define additional storage and reissue the request.

DGT0122E **Allocation map error. The expected level is *expected level*, the actual level is *actual level*, indicated in ALLOCMAP**

Explanation

Expected level is the expected level and *actual level* is the actual level found in the ALLOCMAP. DFSMS CHECK found the PTR level is not the same as the PTR level indicated in the allocation map FST. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files on to a disk. Then reformat the source disk and copy the files back.

DGT0123E **BLDLVL error found within ALLOCMAP routine**

Explanation

A permanent I/O error has occurred while trying to read the minidisk directory. DFSMS CHECK issues return code = 201.

Suggested Action

Check to see if a DASD I/O error message has been sent to the system operator. You may also want to run EREP to see if any permanent errors have been logged. Refer to *z/VM: System Operation* for more information. A repair action may be required on the HDA containing the affected minidisk.

DGT0124W **Block *blocknumber* is in use by the file: *fileid***

Explanation

Block number is the block number and *fileid* indicates the file that has a block in use more than once. DFSMS CHECK found that the block is used more than once. DFSMS CHECK issues return code = 4.

Suggested Action

You may be able to salvage files by copying all usable files on to a disk. Then reformat the source disk and copy the files back.

DGT0125E **Error *error code* from RDTK during BLDLVL**

Explanation

An internal DFSMS error has occurred.

Suggested Action

Contact the IBM Support Center and provide the message header and the *error code*.

DGT0126W **Block *blocknumber* is invalid; used by: *fileid***

Explanation

Block number is the block number and *fileid* indicates the file name and file type. DFSMS found that

blocknumber is invalid and used more than once. DFSMS CHECK issues return code = 4.

Suggested Action

Recreate the minidisk contents, using backup media, and contact the storage administrator.

DGT0127I **Block *blocknumber* is lost**

Explanation

The allocation map shows that block number *blocknumber* is allocated but no file is using this block. DFSMS CHECK issues return code = 4.

Suggested Action

Recreate the minidisk contents, using backup media, and contact the storage administrator.

DGT0128I **FBA blocks: Total: *number of blocks* Usable: *number of blocks***

Explanation

This is an informational message issued by DFSMS CHECK indicating the total number of FBA blocks, and the number of usable blocks.

Suggested Action

None.

DGT0129I ***var1***

Explanation

This is an informational message issued by DFSMS CHECK.

Suggested Action

None.

DGT0130I **Internal error. Block *blocknumber*, FST pointer *FST pointer table address*: invalid flag bits**

Explanation

An internal DFSMS error has occurred.

Suggested Action

Contact the IBM Support Center and provide the message header, the *blocknumber*, and the *FST pointer table address*.

DGT0131W **Directory FST failed validation**

Explanation

There has been directory damage.

Suggested Action

Contact the storage administrator.

DGT0132W Invalid directory file name. Hex value = *hex value of fn*

Explanation

Hex value of fn is the *fn* that DFSMS found in hexadecimal format. DFSMS CHECK issues return code = 4.

Storage Administrator Response

Recreate the damaged minidisk using backup media.

Suggested Action

Contact the storage administrator.

DGT0133W Invalid directory file type. Hex value = *hex value of ft*

Explanation

Hex value of ft is the *ft* that DFSMS found in hexadecimal format. The directory file has collapsed. This may be the result of multiple writes to the disk. DFSMS CHECK issues return code = 4.

Storage Administrator Response

Recreate the damaged minidisk using backup media.

Suggested Action

Contact the storage administrator.

DGT0135E This disk is formatted for the old (CDF) file system; CHECK cannot analyze it

Explanation

CHECK does not support a minidisk block size of 800. DFSMS CHECK issues return code = 200.

Suggested Action

DFSMS CHECK cannot be used for a minidisk with a block size of 800. Choose another method of validating this minidisk.

DGT0136E This disk is in OS format; CHECK cannot analyze it

Explanation

DFSMS CHECK only supports CMS format minidisks. DFSMS CHECK issues return code = 200.

Suggested Action

Either reformat the minidisk or verify that you have issued the CHECK to a CMS formatted minidisk.

DGT0137E This disk is in CP-owned format; CHECK cannot analyze it

Explanation

DFSMS CHECK only supports CMS format minidisks. DFSMS CHECK issues return code = 200.

Suggested Action

You must first FORMAT the minidisk to use DFSMS CHECK.

DGT0138E This disk has an invalid label *label*; CHECK cannot analyze it

Explanation

The minidisk has an invalid disk label as specified in the message. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0139E Error *error code* from DMSDIOLR when attempting to read the disk label

Explanation

An internal DFSMS error has occurred.

Suggested Action

Check to see if a DASD I/O error message has been sent to the system operator. You may also want to run EREP to see if any permanent errors have been logged. Refer to *z/VM: System Operation* for more information. Contact the IBM Support Center and provide the message header, *error code*, and any I/O error message that may have occurred.

DGT0140E Error *error code* from RDTK (DMSDIO) when attempting to read the first directory block, record *record*

Explanation

An internal DFSMS error has occurred.

Suggested Action

Check to see if a DASD I/O error message has been sent to the system operator. You may also want to run EREP to see if any permanent errors have been logged. Refer to *z/VM: System Operation* for more information. A repair action may be required on the HDA containing the affected minidisk. Contact the IBM Support Center and provide the message header, the *error code*, and any I/O error message that may have occurred.

DGT0141E	Label damage. The block number of the first directory block is <i>blocknumber</i>. It should be either 4 or 5
-----------------	--

Explanation

The disk origin pointer must be in block 4 or 5. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0142E	Label damage. The block size reported in the label is <i>blocksize</i>. It should be either 512, 1024, 2048, or 4096
-----------------	---

Explanation

The block size must be one listed in the message. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0143E	Label damage. The number of formatted cylinders reported is greater than the number of cylinders on the disk. ADTCYL (formatted): <i>number of formatted cylinders</i>; ADTMCYL (disk size): <i>number of cylinders</i>
-----------------	--

Explanation

Number of formatted cylinders is the number of formatted cylinders on the disk. *Number of cylinders*

is the number of cylinders for this disk. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0145E	Label damage. The number of CMS blocks reported is incorrect. ADTNUM: <i>reported number of blocks</i>; should be: <i>actual number of blocks</i>
-----------------	--

Explanation

Reported number of blocks is total number of blocks reported for this minidisk. *Actual number of blocks* is the total number of blocks. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0146E	Label damage. The number of CMS blocks reported in use is greater than the number of blocks on the disk. ADTUSED (used): <i>number of used blocks</i>; ADTNUM (max): <i>maximum number of blocks</i>
-----------------	---

Explanation

Number of used blocks is the total number of blocks reported as used blocks. *Maximum number of blocks* is the maximum number of blocks for this minidisk. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0147E	Label damage. The FST size reported is <i>size</i>; it should be 64
-----------------	--

Explanation

The disk label is not correct. This may be caused by multiple write access to the minidisk. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0148E **Internal error**

Explanation

An internal logic error has occurred. DFSMS CHECK issues return code = 200.

Storage Administrator Response

Contact the IBM Support Center and provide the message header.

Suggested Action

Contact the storage administrator.

DGT0149E **Label damage. The number of FSTs per CMS block is incorrect. ADTNFST: reported number of blocks; should be actual number of blocks**

Explanation

The disk label is not correct. This may be caused by multiple write access to the minidisk. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0150I **Var1 var2 *var3***

Explanation

This is an informational message issued by DFSMS CHECK.

Suggested Action

None.

DGT0151E **Directory file name should be: X'00000001 00000000X'**

Explanation

The directory file name is invalid. Its name should be X'00000001 00000000'. DFSMS CHECK issues return code = 200.

Suggested Action

You may be able to salvage files by copying all usable files onto another minidisk. Then reformat the source minidisk and copy the files back.

DGT0152I **Directory file type should be: X'C4C9D9C5 C3E3D6D9'**

Explanation

The directory file type is invalid. Its *ft* should be X'C4C9D9C5 C3E3D6D9'. DFSMS CHECK issues return code = 200.

Suggested Action

Contact the storage administrator.

DGT0153E **Device *devtype* is not a supported type**

Explanation

The device, *devtype* is not supported by DFSMS CHECK. DFSMS CHECK issues return code = 200.

Suggested Action

Ensure that the specified device type is supported by DFSMS CHECK.

DGT0154I **Userid: *userid* Date: *date* Time: *time***

Explanation

This is an informational message issued by DFSMS CHECK indicating the user ID, date, and time.

Suggested Action

None.

DGT0155I **CHECK *var1***

Explanation

This is an informational message issued by DFSMS CHECK.

Suggested Action

None.

DGT0156E **Invalid option: *option***

Explanation

The specified option *option* is invalid. DFSMS CHECK issues return code = 200.

Suggested Action

Reissue the request with valid options.

DGT0157E **File name missing after FILE option**

Explanation

The file name parameter is missing after the FILE option.

Suggested Action

Correct the syntax of the command and try the command again.

DGT0158E **Options are conflicting options**

Explanation

Options are conflicting options and cannot be specified for the same request. For example, both FILE and NOFILE cannot be specified at the same time. DFSMS CHECK issues return code = 200.

Suggested Action

Check DFSMS CHECK syntax and reissue the request.

DGT0160E **Duplicate option: *option***

Explanation

An option has been specified more than once.

Suggested Action

Correct the syntax of the command and try the command again.

DGT0500E **Error from CMS command *CMS command*, return code = *return code***

Explanation

An attempt has been made to run *CMS command*, but an error occurs. *Return code* is the return code from the CMS command.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Consult *z/VM: CMS Commands and Utilities Reference* for information associated with the command and attempt to resolve the condition that has caused the problem.

DGT0502E **Insufficient free storage available**

Explanation

An attempt has been made to obtain some storage, but there is not enough free storage available in the virtual machine to satisfy the request.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Free storage by releasing unneeded minidisks, exiting from inactive applications, or logging on with a larger virtual machine storage size.

DGT0505E **Internal error from routine *routine number*, return code = *return code***

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number* and the *return code*.

Suggested Action

Contact the storage administrator.

DGT0506E **Internal error from routine *routine number*, return code = *return code*, status = *status code***

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, and the *status code*.

Suggested Action

Contact the storage administrator.

DGT0507E	Internal error from routine <i>routine number</i>, return code = <i>return code</i>, reason code = <i>reason code</i>
-----------------	--

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, and the *reason code*.

Suggested Action

Contact the storage administrator.

DGT0508E	Internal error from routine <i>routine number</i>, return code = <i>return code</i>, reason code = <i>reason code</i>, status = <i>status code</i>
-----------------	---

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, the *reason code*, and the *status code*.

Suggested Action

Contact the storage administrator.

DGT0509E	Internal error, return code = <i>return code</i>
-----------------	---

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header and *return code*.

Suggested Action

Contact the storage administrator.

DGT0510E	Internal error, return code = <i>return code</i>, reason code = <i>reason code</i>
-----------------	---

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *return code* and the *reason code*.

Suggested Action

Contact the storage administrator.

DGT0511E	Internal error, return code = <i>return code</i>, reason code = <i>reason code</i>, status = <i>status code</i>
-----------------	--

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *return code*, the *reason code*, and the *status code*.

Suggested Action

Contact the storage administrator.

DGT0513E **Error from CSL routine *CSL routine*,
return code = *return code*, reason
code = *reason code***

Explanation

DFSMS has called CSL routine *CSL routine* to perform some processing, but an error has occurred. The return and reason codes from the CSL routine are given in *return code* and *reason code*.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Consult *z/VM: CMS Callable Services Reference* for the CSL routine and attempt to resolve the condition that caused the error.

DGT0514W **Warning from CSL routine *CSL
routine*, return code = *return code*,
reason code = *reason code***

Explanation

DFSMS has called CSL routine *CSL routine* to perform some processing, but a warning condition has been returned. The return and reason codes from the CSL routine are given in *return code* and *reason code*.

System action

Processing continues.

Storage Administrator Response

None.

Suggested Action

Consult *z/VM: CMS Callable Services Reference* for the CSL routine and attempt to resolve the condition that caused the warning.

DGT1995E **LEVELS option already specified**

Explanation

The user has specified the LEVELS option more than once on a DFSMS command.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax and try the command again.

DGT1996E **VDEV and NOATTACH are
conflicting options**

Explanation

The user has specified both the VDEV and NOATTACH options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT1997E **Missing DFSMSRM operands**

Explanation

The user has not specified any DFSMSRM operands.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which operands are wanted and specify them when invoking the DFSMSRM command.

DGT1998E **AUTOFILL and NOAUTOFILL are conflicting options**

Explanation

The user has specified both the AUTOFILL and NOAUTOFILL options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT1999E **RANDOM and SEQUENTIAL are conflicting options**

Explanation

The user has specified both the RANDOM and SEQUENTIAL options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT2000E **DETAILS and NODETAILS are conflicting options**

Explanation

The user has specified both the DETAILS and NODETAILS options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT2001E **AUDIT and NOAUDIT are conflicting options**

Explanation

The user has specified both the AUDIT and NOAUDIT options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT2002E **ATTACH and NOATTACH are conflicting options**

Explanation

The user has specified both the ATTACH and NOATTACH options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT2003E	ASSIGN and NOASSIGN are conflicting options
-----------------	--

Explanation

The user has specified both the ASSIGN and NOASSIGN options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT2004E	IDRC and NOIDRC are conflicting options
-----------------	--

Explanation

The user has specified both the IDRC and NOIDRC options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error

messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT2005E	READONLY and READWRITE are conflicting options
-----------------	---

Explanation

The user has specified both the READONLY and READWRITE options on the DFSMSRM command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMSRM command.

DGT2006E	Error occurred before DFSMS could start processing your request
-----------------	--

Explanation

The DFSMS master virtual machine received your request, but an error occurred before a report file could be created. Therefore, no report file (if expected) is returned.

System action

None.

Storage Administrator Response

Review the DFSMS master log file or its console file to locate the message and determine the cause of the error.

Suggested Action

Contact the storage administrator.

DGT2007E **Invalid management class:**
management class

Explanation

The user has specified a value for management class that is incorrect.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax of the input value for management class and reissue the command.

DGT2008E **FORCE and NOFORCE are**
conflicting options

Explanation

The user has specified both the FORCE and NOFORCE options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2009E **Invalid operand: *operand***

Explanation

The user has specified an invalid operand.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the input value of the operand and try the command again.

DGT2010E **Missing user ID for FOR option**

Explanation

The user has not specified a value for a CMS user ID.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Specify an input value for the user ID and try the command again.

DGT2011E **Unexpected operand: *operand***

Explanation

The user has specified an unexpected operand.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2012E **Invalid request identifier: *nnnn***

Explanation

The user has specified a request identifier that is not between 3 and 9999999, inclusive.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the request identifier and try the command again.

DGT2013E **Invalid date: *date***

Explanation

The user has specified an invalid date or one not in the form of 'YYYYMMDD', where 'YYYY' is the year, 'MM' is the month, and 'DD' is the day.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the input value of the date and try the command again.

DGT2014E **DFSMS master not running**

Explanation

The application attempts to establish communications with the DFSMS master machine, but the APPC/VM connect request has been unsuccessful.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Reinitialize the DFSMS master machine.

Suggested Action

Contact the storage administrator and verify that DFSMS is operational.

DGT2015E **Error occurred during DFSMS processing**

Explanation

An error has occurred during DFSMS processing. Error messages associated with command processing are written to the DFSMS log files or DFSMS machine consoles, or both, if error message logging is enabled. Some DFSMS commands create a report file and send that file to the issuer of the command. The report file can also be browsed for information pertaining to errors that have occurred.

System action

None.

Storage Administrator Response

Consult the DFSMS logs to see the error messages which have been issued. If you consult the DFSMS log files, the request ID of the DFSMS command can be used to reference the error messages for that command.

Suggested Action

If the issued DFSMS command returns a report file, consult the report file for details on the processing of the command. If you issued a DFSMS command that should have returned a report file to your reader but no file arrives or if you issued a DFSMS command that does not generate a report file, contact the storage administrator and supply the request ID of the DFSMS command submitted.

DGT2016E **User not authorized to issue this command**

Explanation

Some commands require special authorization. The user has attempted to issue a command for which the user is not authorized. The request is not processed.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

There are various ways in which a user may be authorized. If RACF/VM or an equivalent product is installed, authorize the user to access the appropriate RACF® entities. If the DFSMS authorization file is being used, ensure that the user's user ID is included in the authorization file. If the installation has replaced the FSMVAUTH installation-wide exit, ensure that the user is authorized according to the criteria required by the replacement CSL routine.

Suggested Action

If the user should be authorized to issue this command, contact the storage administrator.

DGT2017E **FOR option already specified**

Explanation

The user has specified the FOR option more than once on a DFSMS command.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax and try the command again.

DGT2018E **AS option already specified**

Explanation

The user has specified the AS option more than once on a DFSMS command.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax and try the command again.

DGT2019E **OPTIMIZE option already specified**

Explanation

The user has specified the OPTIMIZE option more than once on a DFSMS command.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax and try the command again.

DGT2020E **Directory *dirid* accessed as file mode *file mode* is under directory control**

Explanation

An attempt has been made to migrate a file that has the directory attribute set to DIRControl.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

If the user wants to migrate these files, the FILEControl attribute must be set for this directory.

DGT2021I **DFSMS is stopping**

Explanation

A DFSMS STOP is in process.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

DGT2022E **Communications could not be made with DFSMS, return code = *return code***

Explanation

The application has attempted to establish communications with DFSMS/VM, but cannot. This may be because the DFSMS master machine is not active, or it may be because the SFS file pool server is not authorized to connect to the DFSMS master machine.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Ensure that the DFSMS master machine is logged on and active by issuing the DFSMS QUERY STATUS command. Autolog the DFSMS master if it is not logged on. If the DFSMS master machine is operational, determine the file pool to which the failing command has been directed and verify that the file pool has authority to connect to the DFSMS master machine. This is dependent upon the type of authorization the installation has chosen. Specific details concerning DFSMS authorization and the description of the FSMVAUTH installation-wide exit can be found in [z/VM: DFSMS/VM Customization](#).

If return code 64900 is received and the DFSMS master machine is operational, check the following to resolve the error:

- If the installation is using the DFSMS authorization file for authorization, the user ID of each file pool to be managed by DFSMS must be in the authorization file (DGTVAUTH DATA VMSYS:DFSMS.CONTROL).
- If the installation is using RACF/VM, the user ID of each file pool to be managed by DFSMS must have read authority to the STGADMIN.APPC RACF/VM entity.
- If the installation has replaced the FSMVAUTH installation-wide exit with its own installation-wide exit, the exit must be implemented to issue return code zero:
 - When the user ID for a DFSMS-managed file pool is passed to the exit
 - When the command passed to the exit is APPC

Suggested Action

Contact the storage administrator and verify that the DFSMS master machine is available and that each file pool to be managed by DFSMS/VM is authorized to connect to the DFSMS master machine.

DGT2023E **CSL routine error, reason code =**
reason code

Explanation

The application has called a CSL routine, but an error has occurred. *Reason code* indicates the reason code that was returned by the CSL routine.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

If the reason code is not found in [z/VM: CMS Callable Services Reference](#) and the reason code is not 66100, contact the IBM Support Center and provide the message header and the *reason code*. Reason code 66100 indicates that the file pool server cannot access the DFSMS product code. Consult [z/VM: DFSMS/VM Customization](#) and [z/VM: DFSMS/VM Storage Administration](#) to verify that the file pool has been properly configured to access the DFSMS product code. For example, the file pool may not be linking to the DFSMS product code, or the file pool may not be authorized to access the DFSMS product code, or the DFSMS product code may not be accessed in the PROFILE EXEC file of the file pool server.

Suggested Action

Consult the "CSL Reason Codes" section of [z/VM: CMS Callable Services Reference](#) for details on resolving the problem. If the reason code is not documented, contact the storage administrator.

DGT2024E **Internal error**

Explanation

An error has occurred on the DFSMS master machine that has prevented the user's request from being accepted.

System action

Command processing for this request is terminated.

Storage Administrator Response

None.

Suggested Action

Resubmit the request.

DGT2025E **File mode *fm* not associated with a**
directory

Explanation

Either of two conditions may result in this message being issued:

1. The user has not specified a directory ID or a file mode for the command, and DFSMS has chosen the

A disk as the default; however, the A disk does not resolve to a valid SFS directory.

2. The user has specified a file mode for the command; however the file mode that the user has specified does not resolve to a valid SFS directory.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Specify a file mode that is an accessed SFS directory and try the command again. Or, access an SFS directory as the A disk and try the command again.

DGT2026I DFSMS request *request id* accepted for processing

Explanation

The user's request has been accepted by DFSMS for processing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

DGT2027I DFSMS request *request id* has completed. Report has been sent to your reader

Explanation

The user has made a request where WAIT has been specified. DFSMS has finished processing the request and has returned a file to the user's reader.

System action

Control will return to the invoker of the DFSMS command.

Storage Administrator Response

None.

Suggested Action

Examine the reader file.

DGT2028E File pool *file pool* is unavailable or unknown

Explanation

A DFSMS command has been issued that tried to perform an action on an SFS file pool that is not available.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Restart the file pool.

Suggested Action

Wait for the file pool to be restarted, or contact the storage administrator to have the file pool restarted.

DGT2029E File pool *file pool* is not managed by DFSMS

Explanation

A DFSMS command has been issued to a file pool that is not supported by DFSMS.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Refer to *z/VM: DFSMS/VM Customization* for instructions on how to set up the file pool to be DFSMS-managed.

Suggested Action

Contact the storage administrator.

DGT2030E Invalid filepoolid: *file pool*

Explanation

The user has specified a value for an SFS file pool that is incorrect.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax of the input value for file pool and try the command again.

DGT2031E Invalid userid: *userid*

Explanation

The user has specified a value for a CMS user ID that is incorrect.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax of the input value for the user ID and try the command again.

DGT2032E Invalid directory id: *dirid*

Explanation

The user has specified a value for a CMS directory ID that is incorrect.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax of the input value for directory identifier and try the command again.

DGT2033E Invalid operand: *operand*

Explanation

The user has specified an item that is longer than any possible item, or the user has specified something after the right parentheses [)] in the command.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the syntax of the command and try the command again.

DGT2034E Invalid delete file token: *token*

Explanation

The user has specified a delete file token that is incorrect.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Consult the output of the DFSMS REPORT SPACEMANAGEMENT FILESPACE command from where the delete token has been obtained, correct the token, and try the command again.

DGT2035E Invalid storage group number: *nnnn*

Explanation

The user has specified a storage group identifier that is not between 2 and 32767, inclusive.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Correct the storage group identifier and try the command again.

DGT2036E **No default file pool assigned**

Explanation

Certain DFSMS commands use the current virtual machine file pool name when no file is specified on the command. However, there is no default file pool defined for this virtual machine. Therefore, DFSMS cannot determine the file pool for which this command has been directed.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Define a default file pool with the SET FILEPOOL command and try the command again, or explicitly specify the file pool when entering the command.

DGT2040E **TYPE and NOTYPE are conflicting options**

Explanation

The user has specified both the TYPE and NOTYPE options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2041E **INFO and NOINFO are conflicting options**

Explanation

The user has specified both the INFO and NOINFO options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2042E **FILE and NOFILE are conflicting options**

Explanation

The user has specified both the FILE and NOFILE options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2043E **NEWDATE and OLDDATE are conflicting options**

Explanation

The user has specified both the NEWDATE and OLDDATE options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error

messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2044E **WAIT and NOWAIT are conflicting options**

Explanation

The user has specified both the WAIT and NOWAIT options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2045E **QUIESCE and IMMEDIATE are conflicting options**

Explanation

The user has specified both the QUIESCE and IMMEDIATE options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2046E **THRESHOLD and NOTHRESHOLD are conflicting options**

Explanation

The user has specified both the THRESHOLD and NOTHRESHOLD options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others) the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT2047E **NOREDETERMINE and REDETERMINE are conflicting options**

Explanation

The user has specified both the NOREDETERMINE and REDETERMINE options on the DFSMS command.

System action

The system continues checking for other mutually exclusive words. After all have been checked and error messages generated (if an error is found on others), the system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Determine which value is actually wanted and specify that value when invoking the DFSMS command.

DGT9988E **ISMF command rejected, all file modes or virtual addresses are in use**

Explanation

ISMF requires access to a product minidisk or SFS directory, and a file mode is not available to allow access to the product minidisk or SFS directory. Or, ISMF is unable to find a free virtual address to link to a product minidisk.

Suggested Action

Make a file mode or virtual address available by using the CMS RELEASE command. See *z/VM: CMS Commands and Utilities Reference* for additional information on the use of the RELEASE command.

DGT9989E **ISMF command rejected; ISMF already processing**

Explanation

The ISMF command is rejected due to a previous invocation of ISMF that is still outstanding.

Suggested Action

Wait until current ISMF processing has completed and then reissue the command or IPL CMS again and reissue the command.

DGT9990E **You may need to re-IPL CMS**

Explanation

An attempt has been made to invoke ISMF while a previous invocation of ISMF is still outstanding.

Suggested Action

Wait until current ISMF processing has completed and then reissue the command or IPL CMS again and reissue the command.

DGT9991E **Unrecognized ISMF keyword: *keyword***

Explanation

The keyword issued, *keyword*, is not supported by ISMF.

Suggested Action

Reissue the correct keyword. For additional information on test mode keywords see the *ISPF Dialog Management Guide*.

DGT9992E **ISMF syntax is: ISMF TESTMODE**

Explanation

Incorrect syntax has been used; the correct syntax is: ISMF TESTMODE.

Suggested Action

Reissue the command or keyword using the correct ISMF syntax.

DGT9993E **TESTMODE keywords are: TEST, TESTX, TRACE, or TRACEX**

Explanation

TESTMODE has been incorrectly entered.

Suggested Action

Reissue ISMF TESTMODE using one of the following values for TESTMODE: TEST, TESTX, TRACE, or TRACEX.

DGT9994E **You entered: ISMF *keyword1* *keyword2***

Explanation

This is a display of the original entry.

Suggested Action

Check the original entry for incorrect syntax, and then reissue using the correct syntax: ISMF TESTMODE.

DGT9995E **Invalid syntax; *keyword* not allowed**

Explanation

The entry contained invalid syntax. The TESTMODE parameter, *keyword*, cannot be used if ISMF is invoked under the control of ISPF.

Suggested Action

Issue the ISMF command without a TESTMODE parameter.

DGT9996E ***Keyword* accepted only when invoking ISMF under the control of CMS**

Explanation

Keyword is allowed only when invoking ISMF from CMS.

Suggested Action

If you must invoke ISMF using *keyword*, you then need to invoke ISMF under the control of CMS.

DGT9997E ***Var1 var2 var3 failed; return code = return code***

Explanation

ISMF invoked a CMS command that returned a nonzero return code. *Var1 var2 var3* is the CMS command issued and *return code* is the return code.

Suggested Action

For ESTATE and COPYFILE failures, ensure that the DFSMS/VM product disk is accessed, and the disk label matches the one specified in the USER_INIT procedure in the ISMF EXEC. Release any currently accessed disks with the same label and reissue the ISMF command. For other errors, contact the IBM Support Center and provide the message header and *return code*.

DGT9998E ***ISMF error; return code = return code***

Explanation

The ISPF ISPSTART command has terminated with a nonzero return code: *return code*.

Suggested Action

Using ISPSTART to invoke ISPF at any point other than the CMS ready command line causes unpredictable results. For additional information regarding the ISPSTART, see the *ISPF Dialog Management Guide*. If the problem persists, contact the IBM Support Center.

DGT9999E ***ISMF failed; unknown operating environment***

Explanation

An error has occurred due to the inability to determine if the operating environment is a CMS or ISPF operating environment.

Suggested Action

Contact the IBM Support Center and provide the message header.

Chapter 3. DFSMS/VM FSM Messages

FSM0500E **Error from CMS command *CMS command*, return code = *return code***

Explanation

An attempt has been made to process *CMS command*, but an error has occurred. *Return code* is the return code from the CMS command.

System action

The system action taken depends on the actual condition that caused the error, but DFSMS attempts to recover from the condition and continues processing. If processing cannot continue, DFSMS stops.

Storage Administrator Response

Consult *z/VM: CMS Commands and Utilities Reference* for information associated with the command and attempt to resolve the condition that has caused the problem.

Suggested Action

None.

FSM0502E **Insufficient free storage available**

Explanation

An attempt has been made to obtain storage, but there is not enough free storage available in the virtual machine to satisfy the request.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Increase the virtual machine storage size for the DFSMS machine that is experiencing insufficient storage problems.

Suggested Action

None.

FSM0503E **Insufficient free storage available, status = *storage status***

Explanation

An attempt has been made to obtain storage, but there is not enough free storage available in the virtual machine to satisfy the request. *Storage status* is a value used by IBM for problem determination.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Increase the virtual machine storage size for the DFSMS machine that is experiencing insufficient storage problems. If insufficient storage problems continue, contact the IBM Support Center and provide the *storage status*.

Suggested Action

None.

FSM0505E **Internal error from routine *routine number*, return code = *return code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, and the *return code*.

Suggested Action

None.

FSM0506E **Internal error from routine *routine number*, return code = *return code*, status = *status code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, and the *status code*.

Suggested Action

None.

FSM0507E **Internal error from routine *routine number*, return code = *return code*, reason code = *reason code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, and the *reason code*.

Suggested Action

None.

FSM0508E **Internal error from routine *routine number*, return code = *return code*, reason code = *reason code*, status = *status code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, the *reason code*, and the *status code*.

Suggested Action

None.

FSM0509E **Internal error, return code = *return code***

Explanation

An internal DFSMS/VM error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header and the *return code*.

Suggested Action

None.

FSM0510E **Internal error, return code = *return code*, reason code = *reason code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a

critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header and the *return code*.

Suggested Action

None.

FSM0510W	Internal warning return code = <i>return code</i>, reason code = <i>reason code</i>
-----------------	--

Explanation

An internal DFSMS warning condition has occurred. This message should be of concern only if it appears frequently.

Storage Administrator Response

Contact the IBM Support Center and provide the message header and the *return code*.

Suggested Action

None.

FSM0511E	Internal error, return code = <i>return code</i>, reason code = <i>reason code</i>, status = <i>status code</i>
-----------------	--

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *return code*, the *reason code*, and the *status code*.

Suggested Action

None.

FSM0513E Variation 1	Error from CSL routine <i>CSL routine</i>, return code = <i>return code</i>, reason code = <i>reason code</i>
-----------------------------	--

FSM0513E Variation 2	Error from CSL routine <i>CSL routine</i>, return code = <i>return code</i>, reason code = <i>reason code</i>, file pool = <i>file pool</i>
-----------------------------	--

FSM0513E Variation 3	Error from a CSL call, return code = <i>return code</i>, reason code = <i>reason code</i>
-----------------------------	--

FSM0513E Variation 4	Error from a CSL call, return code = <i>return code</i>, reason code = <i>reason code</i>, file pool = <i>file pool</i>
-----------------------------	--

Explanation

DFSMS/VM has called a CSL routine to perform some processing, but an error has occurred. The return and reason codes from the CSL routine are given in *return code* and *reason code*. The file pool to which the error applies may also appear in the message. The following lists reason codes that you may see and what these errors mean to DFSMS/VM. Also check *z/VM: CMS Callable Services Reference* for an explanation of the CSL reason code listed.

Reason Code Description

44000

If the error occurred due to a FILEPOOL BACKUP or FILEPOOL RESTORE command, ensure that you have storage administrator authority to the migration level 1 file pool. If the error occurred due to a DFSMS MANAGE or a DFSMS CONVERT command, the storage group number that was contained in the command does not exist. Reissue the command with a valid storage group number. The storage group numbers can be obtained for any file pool by issuing the QUERY FILEPOOL STORGRP command.

50500

This error indicates that a file space does not have enough enrolled blocks to handle the file.

If the error occurred when migrating the file, check your secondary storage file space by issuing QUERY LIMITS. To correct this problem, either add more blocks to this file space by issuing the MODIFY USER command, or expire migrated files by issuing the MANAGE command.

If the error occurred when writing to the log file (log files will start writing to the consoles), then check the file space that stores the log files by issuing QUERY LIMITS. To correct the problem, either add more blocks to this file space by issuing the MODIFY USER command, expire log files by

issuing the MANAGE command if the files are DFSMS-managed, or erase old log files manually if the files reside in a DFSMS directory.

Otherwise, check the file space where the error occurred by issuing QUERY LIMITS. Increase the number of blocks to this file space using the MODIFY USER command.

51000

This error indicates that your storage group space has been exceeded. This may occur in secondary storage, primary storage, or where your log files and work directories are located. To correct the problem (if the files are not in a DFSMS file space), expire some files by issuing the MANAGE command, or add minidisk space to the affected storage group by issuing the FILESERV MINIDISK command.

If this error occurred on a MIGRATE, check your storage group space in secondary storage by issuing the QUERY FILEPOOL STATUS command.

If this error occurred on a RECALL, check your storage group space in primary storage.

Otherwise, check the storage group space where the error occurred.

81053

This reason code indicates a file pool error has occurred. However, other errors could also cause this error. If you locate this message in the log file, it should be followed by message FSM0518E that lists additional WUERROR information regarding the error. If the 81053 is issued because of a system deadlock, you will see reason code 2102 in message FSM0518E. If another reason code appears in that message, look for that reason code in the [z/VM: CMS Callable Services Reference](#).

For system deadlocks, the file or directory encountering the error is not processed. You may resubmit your command.

97250

The MAXCONN value of the virtual machine where this error has been detected may be too low. Increase or specify a larger MAXCONN value in the OPTIONS statement of the directory entry that defines the virtual machine. Refer to [z/VM: DFSMS/VM Customization](#) for directions on setting the MAXCONN value.

If this message is followed by another message indicating that a MIGRATE has failed, check the MAXCONN of the machine running that migrate (DFSMS master or DFSMS server). To determine if the error was detected in the DFSMS master machine or in one of the DFSMS server machines,

review the log files of each virtual machine and look for this message and reason code.

97280

This error indicates that the MAXCONN value specified in the directory entry for the virtual machine being connected to may be too low.

If this message is followed by message FSM1112E, then check that the MAXCONN in the CP directory of the file pool indicated in the FSM1112E message is set correctly.

If this message is followed by message FSM3131E or FSM3133E, then check that the MAXCONN in the directory of the file pool containing secondary storage is set correctly.

97400

This error indicates that either a file pool server is unavailable, or the USERS startup parameter in the DMSPARMS file on the file pool server is too low. If this error occurred on a MIGRATE or RECALL, check the USERS startup parameter in your secondary storage file pool. Otherwise, check the USERS startup parameter on the file pool where the error occurred. Increase the value in the USERS startup parameter. Refer to [z/VM: DFSMS/VM Customization](#) for directions on setting the USERS parameter.

97500

This error indicates that the file pool is unavailable or unknown. Either the file pool stopped due to errors, or it is not logged on. Investigate why the file pool stopped by checking the file pool server's console messages and correct the error. If the file pool is not logged on, autolog the virtual machine that runs the file pool.

98600

This error indicates that there is a problem with CRR. If you have secondary storage in a file pool separate from primary storage or your work directory is in a file pool separate from your DFSMS-managed file pools, CRR is required to complete commands successfully. Ensure the CRR server is available. Refer to [z/VM: CMS Callable Services Reference](#) for CRR commands.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Consult *z/VM: CMS Callable Services Reference* for the CSL routine and attempt to resolve the condition that has caused the error.

Suggested Action

None.

FSM0514W	Warning from CSL routine <i>CSL routine</i>, return code = <i>return code</i>, reason code = <i>reason code</i>
-----------------	--

Explanation

DFSMS has called CSL routine *CSL routine* to perform some processing, but a warning condition has been returned. The return and reason codes from the CSL routine are given in *return code* and *reason code*.

System action

Processing continues.

Storage Administrator Response

Consult *z/VM: CMS Callable Services Reference* for the CSL routine and attempt to resolve the condition that caused the warning.

Suggested Action

None.

FSM0515E	Installation-wide exit <i>exit name</i> exited with unexpected return code <i>return code</i>
-----------------	--

Explanation

An installation-wide exit has returned with an unexpected return code. The *exit name* can be one of the following:

- DGTQAUTO
- FSMACCNT
- FSMVAUTH
- FSMMECHK
- FSMRMATE
- FSMRMDEV
- FSMRMDTE
- FSMRMSHR
- FSMRMPRE
- FSMRMPRO

System action

The system action varies depending upon the exit that has been invoked:

Exit

System Action

DGTQAUTO

DFSMS continues initialization with the next server. If the server is not logged on, DFSMS attempts to autolog the server.

FSMACCNT

Any data placed in the buffer in this routine to modify the accounting record is ignored. DFSMS/VM continues processing as though return code 4 has been returned from the exit and the accounting record is not generated.

FSMVAUTH

The function for which authority is being checked is not performed and authorization fails. DFSMS/VM continues processing as though return code 8 has been returned from the exit.

FSMMECHK

If the file that has been passed to the exit was being processed by the MIGRATE command, and an unexpected return code is returned, the file is not be MIGRATED. If the file was being processed by the MANAGE command, and an unexpected return code is returned, the file is not MIGRATED or EXPIRED.

FSMRMATE

If the unexpected return code is returned when DFSMS/VM attempts to select and attach a device (because a device was not specified on the command), device selection continues with the next device. If the unexpected return code is returned when DFSMS/VM attempts to attach a device specified in a command, the function for which the device is being attached is not performed. DFSMS/VM continues processing as though return code 8 has been returned from the exit. If the unexpected return code is returned when DFSMS/VM attempts to attach the device to the user after primary processing of the request has completed, DFSMS/VM continues processing as though return code 8 has been returned from the exit.

FSMRMDEV

The function for which a device is being selected is not performed. DFSMS/VM continues as though return code 8 has been returned from the exit.

FSMRMDTE

If the unexpected return code is returned when DFSMS/VM is attempting to detach a device specified in a command from the command requestor, the function for which the device is

being detached is not performed. DFSMS/VM continues processing as though return code 8 has been returned from the exit. If the unexpected return code is returned when DFSMS/VM is attempting to detach the device after primary processing of the request has completed, DFSMS/VM continues processing as though return code 8 has been returned from the exit.

FSMRMSHR

The function for which library partitioning restrictions are being checked is not performed. DFSMS/VM continues processing as though returned code 8 has been returned from the exit.

FSMRMPRE

The function for which installation-defined preprocessing has been called is not performed. DFSMS/VM continues processing as though returned code 8 has been returned from the exit.

FSMRMPRO

This exit is called after primary processing of the request has been completed. DFSMS/VM continues processing as though return code 8 has been returned from the exit.

Storage Administrator Response

Examine the return code and verify that the exit is returning only those return codes which DFSMS/VM expects (as documented in the z/VM: DFSMS/VM Storage Administration).

Suggested Action

Contact the storage administrator.

FSM0516E	Installation-wide exit <i>exit name</i> abended
-----------------	--

Explanation

An installation-wide exit has abended. The *exit name* can be one of the following:

- DGTQAUTO
- FSMVAUTH
- FSMMECHK
- FSMACCNT

System action

The system action varies depending upon the exit that has been invoked:

Exit

System Action

DGTQAUTO

DFSMS continues initialization with the next server.

FSMVAUTH

The function for which authority was being checked is not performed. DFSMS continues processing as though return code 8 has been returned from the exit.

FSMMECHK

If the file that was passed to the exit was being processed by the MIGRATE command, MIGRATE processing terminates. If the file that was passed to the exit was being processed by the MANAGE command, MANAGE processing terminates.

FSMACCNT

Any data placed in the buffer in this routine to modify the accounting record is ignored. DFSMS/VM continues processing as though return code 4 has been returned from the exit and the accounting record is not generated.

Storage Administrator Response

Look for messages that indicate the reason for the CSL exit abend. If the CSL exit is provided by IBM, then contact the IBM Support Center for assistance. If the IBM-supplied version of the CSL exit has been replaced, then correct the problem.

Suggested Action

Contact the storage administrator.

FSM0518E	Error in file pool <i>file pool</i>, return code = <i>return code</i>, reason <i>reason code 1</i>, warning reason <i>reason code 2</i>, reason augmentation <i>reason code 3</i>
-----------------	--

Explanation

A DFSMS error has occurred. If the return code is 8 or greater, the reason code field should be reviewed. If the return code is a 4, the warning reason code field should be reviewed. An FSM0513 message is issued before the FSM0518 message. The FSM0513 message specifically indicates what CSL routine has been performed and the reason code for the error. The FSM0518 message provides additional information to help you resolve the problem. Generally, the information in the FSM0513 message is enough to determine the problem. However, in some instances, you also need the associated information in the FSM0518 to assist you in your problem determination. For example, if you get an FSM0513 error message with a reason code of 81053, this simply indicates that an error has occurred, but you cannot tell what error has occurred. The FSM0518 message provides the information that you need to determine the problem and the corrective action. If a file pool has ****, then

the file pool name was not available at the time this message was issued.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Check the log for the FSM0513 message that should be paired with the FSM0518 message. Use the return codes and reason codes to determine and resolve the problem. If the reason codes indicate a problem that you are unable to resolve, contact the IBM Support Center and provide the message header, the *file pool*, *return code*, and *reason codes*.

Suggested Action

None.

FSM0520S	Internal error, return code = <i>return code</i>, reason code = <i>reason code</i>
-----------------	---

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *return code*, and the *reason code*.

Suggested Action

None.

FSM0521S	Internal error, return code = <i>return code</i>, reason code = <i>reason code</i>, status = <i>status code</i>
-----------------	--

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *return code*, the *reason code*, and the *status code*.

Suggested Action

None.

FSM1001E	Authorization file not found
-----------------	-------------------------------------

Explanation

An authorization file is required when both of the following are true:

- The installation has not replaced the authorization exit.
- RACF/VM 1.9 or a subsequent release is not installed or running.

System action

Commands requiring authorization fail.

Storage Administrator Response

Create the authorization file (DGTVAUTH DATA VMSYS:DFSMS.CONTROL) and ensure that all master and server virtual machines have administrator authority to the file pool VMSYS.

Suggested Action

None.

FSM1002S	Abend occurred in the CSL routine FSMVAUTH
-----------------	---

Explanation

DFSMS has invoked the CSL routine FSMVAUTH to perform authority checking, and the CSL routine has abended.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Look for messages that indicate the reason for the CSL routine abend. If the CSL routine is provided by IBM, then contact the IBM Support Center for assistance. If the IBM-supplied version of the CSL routine has been replaced, correct the problem.

Suggested Action

None.

FSM1004E Session authentication failed

Explanation

The DFSMS master machine or one of the servers attempted to open a session with the ML2 server, but the authentication process has failed.

System action

The session with the ML2 server is terminated. A command that exclusively needs the ML2 server (for example, recalling a file from ML2) will fail; however, a command that does not have an exclusive dependency on the ML2 server will continue.

Storage Administrator Response

Check to see that there is not a password mismatch between the ML2 server and DFSMS. If authentication is enabled on the ML2 server, the password parameter on the MIGRATION_LEVEL_2 keyword in the DFSMS control file must match the password for the DFSMS node on the ML2 server. If the password has been changed in the DFSMS control file, the DFSMS master and server machines must be stopped and restarted in order for DFSMS to use the new password.

Note that the password parameter on the MIGRATION_LEVEL_2 keyword is not a required parameter. This allows an installation to run with authentication set off on the ML2 server.

Suggested Action

None.

FSM1100E Error from communication function *communication function*, return code = *return code*

Explanation

A communications error has occurred. *Communication function* indicates which APPC/VM, IUCV, or TSM™ Sign On function has failed. *Return code* indicates the return code that has been returned from the APPC/VM, IUCV, or TSM Sign On function. Following is a table that relates the return code in the FSM1100 message to the particular IUCV or APPC function that has been invoked:

- 24—CONNECT function of APPC/VM
- 30—SENDDATA function of APPC/VM
- 48—RECEIVE function of APPC/VM

- 68—ACCEPT function of IUCV
- 72—HNDIUCV SET function of CMSTIUCV
- 73—SIGNON function of TSM. The return code is set to the reject code returned from TSM
- 80—CONNECT function of IUCV
- 84—RECEIVE function of IUCV
- 88—SEND function of IUCV
- 92—SEVER function of IUCV

System action

If this error occurs on the user's machine, processing of the user's request stops. If it occurs on the DFSMS master machine or one of its servers, the particular request that is being processed stops, but processing continues on the machine.

Storage Administrator Response

Consult *z/VM: CP Programming Services* for information on the particular function that has failed. Consult the TSM documentation for information on the reject codes from the Sign On Response verb for communications function 73.

Suggested Action

Contact the storage administrator.

FSM1101E Communication error, *IDENT SEVER reason code = *reason code*

Explanation

A communications error has occurred on an IUCV path to *IDENT, resulting in an IUCV SEVER.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

The *IDENT SEVER reason code can assist in determining the problem. Consult *IDENT SEVER reason codes in *z/VM: CP Programming Services*.

Suggested Action

Contact the storage administrator.

FSM1102E No file mode available for DFSMS

Explanation

DFSMS requires one free file mode in the virtual machine; however, a file mode is not available.

System action

DFSMS processing stops until a file mode is available.

Storage Administrator Response

Free at least one file mode in the virtual machine.

Suggested Action

None.

FSM1103E	MAXCONN limit exceeded for this machine
-----------------	--

Explanation

A communications error has occurred while attempting to connect to a DFSMS APPC/VM resource or to the ML2 server virtual machine.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Increase the number of allowable connections for your virtual machine by increasing the MAXCONN parameter of the OPTION control statement in the virtual machine's directory entry.

Suggested Action

Contact the storage administrator.

FSM1104E	This machine not authorized to connect to *IDENT
-----------------	---

Explanation

A communications error has occurred on an IUCV path to *IDENT.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Add the IUCV control statement to the directory entry which allows your virtual machine to connect to *IDENT.

Suggested Action

Contact the storage administrator.

FSM1105E	MAXCONN limit exceeded for the
Variation 1	DFSMS or RMS master machine

Explanation

A communications error has occurred while attempting to connect to a DFSMS resource.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Increase the MAXCONN limit in the directory entry for the DFSMS or RMS master machine. Refer to [z/VM: DFSMS/VM Customization](#).

Suggested Action

Contact the storage administrator.

FSM1105E	MAXCONN limit exceeded for the
Variation 2	ML2 server

Explanation

A communications error has occurred while attempting to connect to the ML2 server.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Increase the MAXCONN limit in the directory entry for the ML2 server.

Suggested Action

Contact the storage administrator.

FSM1106E	Machine not authorized to identify
	global resources

Explanation

A communications error has occurred while attempting to identify an APPC/VM global resource to *IDENT.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Add the GLOBAL keyword to the IUCV *IDENT statement in the DFSMS or RMS master machine's directory entry.

Suggested Action

Contact the storage administrator.

FSM1107E **Machine not authorized to identify resource *communications resource***

Explanation

A communications error has occurred while attempting to identify a resource with *IDENT.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Add an IUCV control statement to the DFSMS or RMS master machine's directory entry that contains the correct resource (resid) or use the keyword RESANY. Refer to *z/VM: DFSMS/VM Customization* for recommendations.

Suggested Action

Contact the storage administrator.

FSM1108I **APPC/VM path connection limit (or MAXCONN) for this machine is *number of connections***

Explanation

This message provides the current MAXCONN setting for the virtual machine.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

None.

FSM1109I **Userid *target userid* severed attempted connection**

Explanation

A source communicator has severed a connection before the DFSMS or RMS master was able to accept the connection.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

None.

FSM1110E **ML2 server severed connection**

Explanation

The ML2 server detected an error and severed a connection to this virtual machine.

System action

The request being processed fails, but DFSMS/VM continues.

Storage Administrator Response

Consult the virtual machine console for the ML2 server to determine why the ML2 server severed the connection and resolve the problem.

Suggested Action

None.

FSM1111E **ML2 server refused connection from DFSMS**

Explanation

A DFSMS virtual machine has attempted to connect to the ML2 server machine, but the connection is refused.

This may occur when the ML2 server is logged on, but not active.

System action

The request that is being processed fails, but DFSMS continues.

Storage Administrator Response

Verify that the ML2 server is active. If the ML2 server is active, verify that the directory entries for the TSM and DFSMS virtual machines are correct.

Suggested Action

None.

FSM1112E Error processing file *fn ft dirid*

Explanation

There has been an error processing this file. See the accompanying FSM0513 message for details on the actual CSL routine that has failed and the accompanying return and reason code.

System action

The system action taken depends on the actual condition that caused the error, but DFSMS attempts to recover from the condition and continue processing, if possible. If processing cannot continue, the request that is being processed is cancelled.

Storage Administrator Response

Consult *z/VM: CMS Callable Services Reference* to resolve the problem.

Suggested Action

None.

FSM1120E ML2 server returned roll-back code = *roll-back code*

Explanation

DFSMS/VM was communicating with the ML2 server when the server encountered an error. *Roll-back code* indicates the vote field server roll-back code that has been returned from the ML2 server.

System action

The particular request that is being processed ends, but DFSMS continues processing with the next request.

Storage Administrator Response

Consult *WDSF/VM Programmer's Guide and Reference* for information on the vote field server roll-back code and resolve the problem.

Suggested Action

None.

FSM1200I The following files were assigned the new management class *name*:

Explanation

This message appears in the ALTER report when the new management class *name* has been assigned to one or more files.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM1201I FILENAME FILETYPE OLD MANAGEMENT CLASS

Explanation

This message appears in the ALTER report when a new management class has been assigned to one or more files.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM1202W Management class *name* is not in the active configuration

Explanation

The new management class specified with the DFSMS ALTER request is not in the active configuration. The system rejects the request when the FORCE

option is not specified and does not assign the new management class.

When the FORCE option is specified, the system assigns the new management class even though it is not in the active configuration. Therefore, it is recommended that the FORCE option be used with care since an invalid management class can result in files not being managed by DFSMS/VM. For more information on the FORCE option enter HELP DFSMS ALTER.

System action

The system will either assign the new management class or reject the request.

Storage Administrator Response

None.

Suggested Action

Verify that the new management class has been specified correctly.

FSM1203I	<i>nnnn</i> files assigned the new management class
-----------------	--

Explanation

This message appears in the ALTER report to indicate the number of files that have been assigned a new management class.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM1204E	Files in directory <i>dirid</i> cannot have their management class altered
-----------------	---

Explanation

An attempt is made to change the management class of files in the directory, but the files in the specified directory cannot have their management class altered because the top directory begins with DFSMS.

System action

Processing of the request ends.

Storage Administrator Response

Rename the top directory or move the files to another file space whose top directory does not begin with DFSMS.

Suggested Action

None.

FSM1205E	Directory <i>dirid</i> cannot have its management class altered
-----------------	--

Explanation

An attempt is made to change the management class of the directory, but the specified directory cannot have its management class altered because the top directory name begins with DFSMS.

System action

Processing of the request ends.

Storage Administrator Response

Verify that the top directory name is specified correctly. Note that the top directory name cannot begin with DFSMS.

Suggested Action

None.

FSM1206E	File <i>fn ft dirid</i> is not a base file
-----------------	---

Explanation

The DFSMS ALTER command can only be used to alter the management class of base files. This message appears in the ALTER report when an attempt is made to change the management class of a file that is not a base file.

System action

Processing of the request ends.

Storage Administrator Response

The CMS QUERY ALIAS command can be issued to determine the base file name of an alias.

Suggested Action

None.

FSM1207I *Number of files files migrated to migration level 2*

Explanation

This message appears in the MIGRATE report to indicate the total number of files successfully migrated to migration level 2.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM1208I *Number of files files recalled from migration level 2*

Explanation

This message appears in the RECALL report to indicate the total number of files successfully recalled from migration level 2.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM1211I *DFSMS command received from user userid, request identifier = request id*

Explanation

The DFSMS master received a command from *userid*. The request has been assigned the specified request identifier. The request identifier is displayed when a QUERY command is issued and can be used to DISCARD the request.

System action

The system continues processing the request.

Storage Administrator Response

None.

Suggested Action

None.

FSM1212I *DFSMS command restarted for userid userid, request identifier = request id*

Explanation

During restart of DFSMS, the command submitted by *userid* has been restarted. DFSMS continues to use the request identifier assigned at the time the request was first submitted for processing. The request identifier is displayed when a QUERY command is issued and can be used to DISCARD the request.

System action

The system continues processing the request.

Storage Administrator Response

None.

Suggested Action

None.

FSM1213W *DFSMS is unable to restart the command with request identifier request identifier*

Explanation

During restart of DFSMS, a command submitted for processing prior to restart of DFSMS cannot be restarted due to an internal error. Check preceding messages for error indication.

System action

The system bypasses the command.

Storage Administrator Response

None.

Suggested Action

None.

FSM1214E **File cannot be migrated because the associated base file is in a file space whose top directory name begins with DFSMS**

Explanation

A request has been received to migrate an alias file and the base file resides in a file space whose first five characters of the top directory name begins with DFSMS. DFSMS/VM will not migrate a file from such a file space.

System action

The MIGRATE command ends.

Storage Administrator Response

None.

Suggested Action

Avoid creating alias files whose base file resides in a file space having a top directory name that begins with DFSMS. Note that files stored in a top level directory whose name starts with DFSMS cannot be migrated.

FSM1215E **User ID *userid* is not enrolled in file pool *file pool***

Explanation

An attempt by DFSMS/VM to acquire storage group information for *userid* in *file pool* results in an error indicating that the user ID is not enrolled in the file pool. This can be either the migration level 1 file space specified in the DFSMS/VM control file or a user's file space.

System action

The report file is sent to the user, and processing of the request ends.

Storage Administrator Response

Verify that the user ID is enrolled in the file pool. Do not enroll the user ID in a file pool and storage group where migration level 1 is defined.

Suggested Action

Issue the QUERY ENROLL command to verify that the user ID is enrolled in the file pool, contact the storage administrator.

FSM1216E **Directory *dirid* not found or the DFSMS master is not authorized**

Explanation

This message appears in the MIGRATE and RECALL reports when either the named directory does not exist or the DFSMS master virtual machine has not been granted the proper authority to the file pool where the directory is defined.

System action

Processing of the request ends and the report is sent to the command issuer.

Storage Administrator Response

Verify that the DFSMS master virtual machine has been granted administrator authority to the file pool where the directory is defined.

Suggested Action

Verify that the directory does exist. If the directory exists, then contact your storage administrator.

FSM1217E **File *fn ft dirid* not found or the DFSMS master is not authorized**

Explanation

This message appears in the ALTER, MIGRATE, and RECALL reports when either the file does not exist or the DFSMS master virtual machine has not been granted the proper authority to the file pool where the file exists.

System action

Processing of the request ends and the report is sent to the command issuer.

Storage Administrator Response

Verify that the DFSMS master virtual machine has been granted administrator authority to the file pool where the directory is defined.

Suggested Action

Verify that the file does exist. If the file exists, then contact your storage administrator.

FSM1218E **Management class of directory *dirid* not altered because it is identical to the new management class *name***

FSM1218E **Management class of file *fileid* not altered because it is identical to the new management class *name***

Explanation

An ALTER request was submitted to change the management class of a directory or a file but has been rejected because the management class submitted with the request is identical to the management class currently assigned to the directory or file.

System action

None.

Storage Administrator Response

None.

Suggested Action

Check the specification of the new management class in the ALTER command. Verify that the new management class is spelled correctly, and the correct directory or file is specified.

FSM1300E **User ID *userid* not authorized to generate an accounting record**

Explanation

This message is issued when the user ID of the DFSMS virtual machine issuing the request is not authorized to use the account option.

System action

An accounting record is not generated.

Storage Administrator Response

Ensure that the ACCT operand has been specified on the OPTION control statement in the DFSMS master and server machine z/VM CP directories.

Suggested Action

None.

FSM1310W **Accounting data is lost or inaccurate**

Explanation

This message is issued when a DFSMS/VM error occurs that affects accumulation of accounting data.

System action

An accounting record may be generated, but accounting data is not accurate. Processing continues.

Storage Administrator Response

Check the log messages for further information regarding the error.

Suggested Action

None.

FSM1320E **Accounting record not generated**

Explanation

This message is issued when an error occurs that prevents the generation of an accounting record.

System action

An accounting record is not generated. Processing continues.

Storage Administrator Response

Check the log messages for further information regarding the error.

Suggested Action

None.

FSM2000E **Requested volume *vlabel* is a reserved volume; request identifier = *request id*, library name = *libname***

Explanation

The specified volume is reserved.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

None.

FSM2001E **Maximum number of library system tokens exceeded; request identifier = *request id*, library name = *libname***

Explanation

An attempt to reserve a new category for a SET VOLCAT or SET VOLCAT BULK command, or for a MOUNT or DEMOUNT command that specified a target category has failed because the number of systems requesting categories exceeds 256.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

None.

FSM2002E	All library categories are reserved; request identifier = <i>request id</i>, library name = <i>libname</i>
-----------------	---

Explanation

An attempt to reserve a new category for a SET VOLCAT or SET VOLCAT BULK command, or for a MOUNT or DEMOUNT command that specified a target category failed because there are no more categories available.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

Unused categories may be released by the RESET VOLCAT command.

Suggested Action

None.

FSM2003E	Request cancelled because the subsystem is functionally incompatible; request identifier = <i>request id</i>
-----------------	---

Explanation

A requested operation has been received by the subsystem, but cannot be performed due to the state

of the subsystem, its configuration, or the set of installed features.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

Contact the IBM Support Center and provide the message header.

Suggested Action

Contact the library administrator.

FSM2004E	Tape device subsystem is in degraded mode; device = <i>rdev</i>, sense data = <i>sense data</i>
-----------------	--

Explanation

A condition occurs on a device that causes the tape device subsystem to go into a degraded mode. This condition can cause degraded subsystem performance.

System action

The system continues operation.

Library Administrator Response

Contact the IBM Support Center and provide the message header.

Suggested Action

Contact the library administrator.

FSM2005E	Request <i>request id</i>, cancelled because the device is offline; device = <i>rdev</i>, library = <i>libname</i>
-----------------	---

Explanation

The specified drive is not online. The following conditions may cause this error:

- The device is switched offline
- The device power is switched off
- The device address is not set correctly

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

Check to see if the device is offline, powered off, or has an incorrect address.

Suggested Action

None.

FSM2006E **Library I/O error; reason code =
reason code, request identifier =
request id, device = rdev, library =
libname**

Explanation

A library hardware error has occurred that prevents a request from completion. See the specific reason code for further information.

Reason Code Significance

3332

Volume not in inventory — The requested volume has been deleted from the inventory

3348

Library volume misplaced — The specified volume has been misplaced

3500

Library attachment check

3504

Library manager offline

3508

Control unit and library manager error

3512

Library vision failure

3516

Library not capable

3600

Manual rewind/unload

3604

Degraded mode

3612

Bus-out parity check

3616

Channel interface permanent error

3620

Channel protocol error

3628

Channel protocol error

3636

Read data check

3640

Load display check

3644

Write data check

3652

Write ID mark check

3656

Unsolicited environment data

3660

Environmental data present

3664

Permanent equipment check

3668

Data security erase failure

3672

Not capable

3676

Write protected

3680

Tape void

3684

Tension loss

3688

Load failure

3692

Unload failure

3696

Drive equipment check

3700

End of data

3704

Tape length error

3708

Backward at beginning of tape

3712

Drive switched not ready

3716

Overrun

3720

Record sequence error

3724

Drive not ready

3732

Locate block unsuccessful

3740

Unsolicited sense

3744

Control unit ERP failed

3748

CU and drive incompatible

3752

Maximum block size exceeded

3756

Read buffered log overflow

3760

Read buffered log EOF

3764

Tape length incompatible

3768

Format 3480XF incompatible

3772

Format 34802XF incompatible

3780

Physical end of volume

3784

Recovered check one failure

3788

Global command intercept

3792

Compaction algorithm error

3796

Volume fenced

3800

Command reject

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

See [“DFSMS/VM Reason Codes”](#) on page 209.

Suggested Action

None.

FSM2007E	Error occurred while attempting to confirm completion status of request = <i>request id</i>, completion status unknown
-----------------	---

Explanation

An error has occurred while attempting to determine the completion status for this request.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Use the DFSMSRM QUERY REQUEST command to determine the status of the request.

FSM2008E	Requested volume <i>vlabel</i> already in use; request identifier = <i>request id</i>, library name = <i>libname</i>
-----------------	---

Explanation

The specified volume is in use.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Reissue the request at a later time.

FSM2009E	Requested volume <i>vlabel</i> is not in the library; request identifier = <i>request id</i>, library name = <i>libname</i>
-----------------	--

Explanation

The specified volume is not in the specified library.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Check that the volume and library specified are correct. If they are correct, ask the library administrator to add the volume to the library.

FSM2010E Requested category is empty; category = *catname*, library name = *libname*, request identifier = *request id*

Explanation

The specified category does not have any volumes assigned to it, or the request requires a volume to be specified.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Assign volumes to this category or specify a volume in this category.

FSM2011E Requested volume *vlabel* misplaced; request identifier = *request id*, library = *libname*

Explanation

The requested volume cannot be located. It has been identified in the inventory as a misplaced volume.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

Locate the misplaced volume and add it to the specified library.

Suggested Action

Contact the library administrator. Reissue the request once the volume has been located and added to the specified library.

FSM2012E Requested volume *vlabel* inaccessible; request identifier = *request id*, library = *libname*

Explanation

The requested volume is in a position that is inaccessible to the library.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

Pause the library and place the required volume where it can be accessed. Reissue the request.

Suggested Action

None.

FSM2013E Requested volume *vlabel* manually ejected; request identifier = *request id*, library = *libname*

Explanation

The requested volume has been assigned to the manual eject category.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

Insert the requested volume into the library.

Suggested Action

Ask the library administrator to insert the volume into the library.

FSM2014E Requested category in use; category = *catname* library = *libname* request identifier = *request id*

Explanation

The requested category is already in use.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

None.

FSM2015E	Request <i>request id</i> cancelled because the device <i>rdev</i> is assigned elsewhere
-----------------	---

Explanation

The requested device is not assigned to the system issuing the request.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

A different device address should be requested, or the request should be reissued at a later time.

FSM2016E	Specified volume <i>vlabel</i> does not match the volume that is currently mounted on device <i>rdev</i>, request identifier = <i>request id</i>
-----------------	---

Explanation

The volume that was specified on the DEMOUNT request does not match the volume that is currently mounted at that address.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Check that the specified volume is correct, or reissue the request without specifying the volume.

FSM2017E	Unrecognized I/O error, request identifier = <i>request id</i>, device = <i>rdev</i>
-----------------	---

Explanation

An unrecognized I/O error condition has occurred.

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

Contact the IBM Support Center and provide the message header.

Suggested Action

None.

FSM2018E	Request cancelled because of a library sequence-check, request identifier = <i>request id</i>, reason code = <i>reason code</i>
-----------------	--

Explanation

A library sequence-check has occurred. See the specific reason code for further information.

Reason Code Significance

3364
Mount is in progress or volume is mounted

3368
Mount is already pending

3372
Demount was already pending

3376
No volume is mounted

System action

The system fails the current request that it is attempting. DFSMS attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

None.

FSM2019E	Sense Data = XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX X ...
-----------------	--

Explanation

Sense data associated with messages FSM2003, FSM2006, FSM2017.

System action

None.

Library Administrator Response

None.

Suggested Action

None.

FSM2020I	DFSMS was terminated before the completion status of request = request id could be confirmed
-----------------	---

Explanation

DFSMS has accepted the STOP command for processing and terminates before the request is complete.

System action

DFSMS shuts down.

Storage Administrator Response

None.

Suggested Action

None.

FSM2021E	Request request id could not be completed successfully because of a load failure for device rdev.
-----------------	--

Explanation

The mount failed due to a load failure. Two successive load failures will result in the device being made unavailable.

System action

DFSMS fails the current request that it is processing and attempts to continue processing other requests. For failures with a 3140 reason code, RMS will vary the device offline to CP.

Library Administrator Response

None.

Suggested Action

Reissue the request to the same device or to another device. If the device was varied offline, resolve the device failure than vary the device back online.

FSM2022E	Request request id could not be completed successfully because volume vlabel is damaged. The volume is being ejected from the library.
-----------------	---

Explanation

The request failed because the hardware has detected that the volume is physically damaged. Since the volume cannot be used, it is ejected from the library.

System action

DFSMS fails the current request that it is processing, and attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Examine the tape cartridge, correct the damage, reinsert the volume into the library, and then reissue the command. Or, reissue the command using a different volume.

FSM2023I	Device rdev,TVOL,severity sev,VOLUME=vlabel,MC=mcode,ES=emcode,RC=rdev-mid-fid
-----------------	---

Explanation

Informational message from 3590 tape subsystem where:

rdev
real device address

sev
severity

vlabel

volume label

mcode

message code

emcode

exception message code

rcode

reference code

mid

media identifier

fid

format identifier

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2024I Variation 1	Device <i>rdev</i>,TCU,<i>type-mod</i>,severity <i>sev</i>,SER=<i>mmpp-ssss</i>,MC=<i>mcode</i>,ES=<i>emcode</i>,RC=<i>rcode-mid-fid</i>
FSM2024I Variation 2	Device <i>rdev</i>,TAPE,<i>type-mod</i>,severity <i>sev</i>,SER=<i>mmpp-ssss</i>,MC=<i>mcode</i>,ES=<i>emcode</i>,RC=<i>rcode-mid-fid</i>
FSM2024I Variation 3	Device <i>rdev</i>,TLIB,<i>type-mod</i>,severity <i>sev</i>,SER=<i>mmpp-ssss</i>,MC=<i>mcode</i>,ES=<i>emcode</i>,RC=<i>rcode-mid-fid</i>

Explanation

Informational message from 3590 tape subsystem where:

rdev

real device address

type-mod

machine type and model

sev

severity

mmpp-ssss

Manufacture, Plant manufacture-Machine sequence number

mcode

message code

emcode

exception message code

rcode

reference code

mid

media identifier

fid

format identifier

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2025E	The invoker already has diag 254 environment for the specified subsystem
-----------------	---

Explanation

z/VM DIAGNOSE 254 detects a condition where this user already has DIAGNOSE 254 active for the specified subsystem.

System action

DFSMS terminates operation.

Library Administrator Response

Contact your DFSMS/VM product support personnel.

Suggested Action

None.

FSM2026E	Another user currently has Diag 254 environment active for the specified subsystem
-----------------	---

Explanation

z/VM DIAGNOSE 254 detects a condition where another user has a DIAGNOSE 254 active for the specified subsystem.

System action

DFSMS terminates operation.

Library Administrator Response

Locate the user who has the DIAGNOSE 254 environment active.

Suggested Action

None.

FSM2027E **A CP close connection function is currently pending for the specified subsystem**

Explanation

z/VM DIAGNOSE 254 detects a condition where a close pending is active.

System action

DFSMS terminates operation.

Library Administrator Response

None.

Suggested Action

Re-IPL CMS.

FSM2028E **The specified subsystem does not exist in VM real IO configuration**

Explanation

z/VM DIAGNOSE 254 could not locate a tape drive in connection with the tape subsystem specified in the configuration.

System action

DFSMS terminates operation.

Library Administrator Response

Make at least one ATL tape drive available to the z/VM system and re-IPL DFSMS.

Suggested Action

None.

FSM2029E **The specified subsystem is not supported by VM for Diagnose 254.**

Explanation

The specified tape subsystem is not an automated tape library.

System action

DFSMS terminates operation.

Library Administrator Response

The sequence number specified in the RM_AUTO_LIBRARY statement in the DGTVCNTL DATA file points to a non-automated tape subsystem.

Suggested Action

None.

FSM2030E **The invoker is a V=R or V=F guest**

Explanation

z/VM DIAGNOSE 254 does not support V=R or V=F guest.

System action

DFSMS terminates operation.

Library Administrator Response

Remove the V=R or V=F OPTION from the user directory then update the directory. Re-IPL CMS after the directory has been updated.

Suggested Action

None.

FSM2031E **The invoker is in 370 mode**

Explanation

z/VM DIAGNOSE 254 does not support a guest whose virtual machine runs in 370 mode.

System action

DFSMS terminates operation.

Library Administrator Response

None.

Suggested Action

Enter a CP SET MACHINE XA or CP SET MACHINE ESA then re-IPL CMS.

FSM2100E **Request *request id* could not be completed because conflicts were encountered while processing request parameters; reason code = *reason code***

Explanation

The request parameters are in conflict with each other or with the allowable values for the particular request.

System action

DFSMS fails the current request that it is processing, and attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Reissue the command after correcting the conflicting parameters. See the specific reason code for further information.

Reason Code

Significance

3000

Specified device does not reside in specified library.

3004

Source category not defined for input library, or for library in which specified device resides.

3008

Specified real device is undefined to the RMS master.

3016

NOIDRC has been specified on a request bound for an automated library. All devices in automated libraries are IDRC-capable.

3020

The library name specified on the command is not defined in the DFSMS control file.

3024

Target category not defined for input library, or for library in which specified device resides.

3028

Target or source category defined for mount issued to manual library.

FSM2101E

A failure occurred forwarding request *request id* to the manual library *library name*

Explanation

DFSMS attempts to forward the request to the library operator for the specified library, but a failure occurs while sending the message.

System action

DFSMS fails the current request that it is processing, and attempts to continue processing other requests.

Library Administrator Response

Details about the failure can be found in the DFSMS log.

Suggested Action

Contact the library administrator.

FSM2102E

**Request identifier = *request id*:
Manual library requests are not
valid for this request type**

Explanation

A command such as QUERY or SET has been issued specifying a manual library name. This command cannot be issued to a manual library.

System action

DFSMS fails the current request that it is processing and attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

None.

FSM2103E

**Request identifier = *request id*:
Installation-wide exit *installation
exit* indicates that processing
should not be allowed to continue**

Explanation

Processing of the requested operation has been stopped on the instructions of an installation-wide exit.

System action

DFSMS fails the current request that it is processing, and attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Refer to the following information for the specified exit.

Exit Name

Significance

FSMRMATE

The specified real device cannot be attached by the RMS master.

FSMRMDTE

The specified real device cannot be detached by the RMS master.

FSMRMDEV

A real device cannot be located to process the command.

FSMRMPRE

Installation-defined preprocessing stopped processing of the command.

FSMRMSHR

Installation-defined library partitioning criteria would be violated by this command.

FSM2104W	An error occurred in request <i>request id</i> after primary processing of the command completed; reason code = <i>reason code</i>
-----------------	---

Explanation

An error has been encountered after primary processing of the command completed.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

See the specific reason code for further information.

Reason Code

Significance

3200

Errors occurred during installation-defined command post-processing.

3204

Errors occurred attempting to set logical write protect for the device after the volume was mounted.

3208

Errors occurred attempting to detach the device from the RMS master or attach it to the user. The

device may still be attached to the RMS master, or it may be free.

3212

Errors occurred in installation-defined detach processing. The device may still be attached to the RMS master.

3216

Errors occurred in installation-defined attach processing. The device may be left free.

3220

On a DEMOUNT command, the DEMOUNT is completed but the volume category cannot be changed to the specified target category.

3304

The volume's external label cannot be verified because the label is unreadable.

3512

The volume's external label cannot be verified because the library's vision system is not operational.

3520

On a MOUNT command, the MOUNT completed however it has subsequently been DEMOUNTed before command completion was returned to RMSMASTR.

FSM2105E	ATTACHTO user <i>userid</i> specified in request <i>request id</i> is not logged on
-----------------	--

Explanation

The request is not processed because the virtual machine indicated by *userid* that the device attaches to is not logged on.

System action

DFSMS fails the current request it is processing and attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Verify that the ATTACHTO user ID has been correctly specified and is logged on. Reissue the command.

FSM2106I	MOUNT VOL <i>vlabel</i> FOR USER <i>userid</i>; NOATTACH READONLY/ READWRITE IDRC/NOIDRC
-----------------	---

Explanation

This message is sent to the library notify user ID when the RMS master receives a MOUNT request specifying a manual library name.

System action

DFSMS continues processing the next request.

Library Administrator Response

Mount the requested volume.

Suggested Action

None.

FSM2107E	Volume <i>vlabel</i> conflicts with installation-defined partitioning criteria
-----------------	---

Explanation

The specified volume cannot be processed because it conflicts with library partitioning criteria as defined by the FSMRMSHR installation-wide exit. The volume was encountered while processing new volumes that were inserted into the library, or during processing of a DFSMSRM SET VOLCAT BULK command.

System action

The category of the specified volume is unchanged. DFSMS continues processing other volumes.

Library Administrator Response

The volume may belong to a different system, or it may need a new label in a range that belongs to this system. Alternatively, the volume range partitioning criteria may need to be adjusted.

Suggested Action

Ensure that the correct volume has been specified.

FSM2108E	Request <i>request id</i> could not be completed because the category <i>category name</i> is not currently assigned to device <i>device address</i>
-----------------	---

Explanation

The specified category has not been assigned to the specified device at the time of the request.

System action

DFSMS fails the current request that it is processing, and attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Reissue the command specifying the correct category or the correct device, or reissue the command without specifying a category.

FSM2109E	Request <i>request id</i> could not be completed because the source category <i>category name</i> does not match the current assignment of the volume <i>volname</i>
-----------------	---

Explanation

The source category specified did not match the assigned category of the volume at the time of the request.

System action

DFSMS fails the current request that it is processing, and attempts to continue processing other requests.

Library Administrator Response

None.

Suggested Action

Reissue the command specifying the correct source category or reissue the command without specifying a source category.

FSM2110E	Request <i>request id</i> could not be completed, reason code = <i>reason code</i> Request <i>request id</i> could not be completed, reason code = <i>reason code</i>, completion code = <i>completion code</i>
-----------------	--

Explanation

An abnormal condition has occurred while issuing an I/O operation to the device.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

See the specific reason code for further information.

Reason Code Significance

3120

The library is in the paused state and the installation has specified that requests should not be queued when the library is paused.

3140

The device became unavailable while the request was being processed.

3160

A MOUNT request failed with the library hardware indicating a logical volume mount has failed.

3320

A hardware failure condition occurred at the time the request was issued.

Completion Code Significance

16

Internal error detected

17

Resend special case

32

Specific volume in use on another cluster

33

Scratch volume selected in use on another cluster

34

Valid volume inaccessible

35

Local cluster path to volume's data no longer available

36

Remote cluster path to volume's data no longer available

37

Copy required, but cluster copying prohibited

48

Local cluster recall failed, stacked volume misplaced

49

Local cluster recall failed, stacked volume inaccessible

50

Local cluster recall failed, stacked volume unavailable

51

Local cluster recall failed, stacked volume no longer in library

52

Local cluster recall failed, stacked volume load failed

53

Local cluster recall failed, stacked volume access error

56

Remote cluster recall failed, stacked volume misplaced

57

Remote cluster recall failed, stacked volume inaccessible

58

Remote cluster recall failed, stacked volume unavailable

59

Remote cluster recall failed, stacked volume no longer in library

60

Remote cluster recall failed, stacked volume load failed

61

Remote cluster recall failed, stacked volume access error

64

Insufficient cache space

FSM2113E **Unexpected return code from CP command name command; return code = return code**

Explanation

The specified CP command has completed unsuccessfully.

System action

DFSMS continues operation.

Library Administrator Response

Consult *z/VM: CP Commands and Utilities Reference* for more information on the specific command.

Suggested Action

None.

FSM2118E **Request request id cancelled because the library libname is in manual mode**

Explanation

The QUERY LIBRARY VOLUME (AUDIT request cannot be processed, because the library is currently in manual mode.

System action

DFSMS fails the current request, and attempts to continue operation.

Library Administrator Response

None.

Suggested Action

Reissue the request after the library has been returned to the automated state.

FSM2119E	Request <i>request id</i> was cancelled by a subsequent operation
-----------------	--

Explanation

The command has been cancelled at the library manager due to order sequence (for example, a pending MOUNT request was cancelled by a subsequent DEMOUNT).

System action

DFSMS fails the current request, and attempts to continue operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2120I	Request <i>request id</i> complete; volume <i>vlabel</i>, category <i>catname</i>, mounted on device <i>rdev</i> in library <i>libname</i>
-----------------	---

Explanation

The MOUNT command has completed successfully.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2121I Variation 1	Request <i>request id</i> complete; Volume <i>vlabel</i> demounted from device <i>rdev</i>
---------------------------------	---

Explanation

The DEMOUNT command has completed successfully.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2122I Variation 2	Request <i>request id</i> complete; volume <i>vlabel</i> assigned to category <i>catname</i>
---------------------------------	---

Explanation

The SET VOLCAT command has completed successfully.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2123I	Request = <i>request id</i>: Bulk processing completed. A report file has been sent to your reader.
-----------------	--

Explanation

The SET VOLCAT BULK command has completed successfully.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2125I Request *request id*: device *rdev* attached to *userid* as *vdev*; access mode = *access mode*

Explanation

This message accompanies message FSM2120 and specifies where the device has been attached, the virtual address and access mode, following the completed MOUNT operation. The access mode will be READONLY or READWRITE.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2126I Request *request id*: device *rdev* remains free; access mode = *access mode*

Explanation

This message accompanies message FSM2120 when the NOATTACH option is specified on the DFSMSRM MOUNT command. The access mode will be READONLY or READWRITE.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2127I Request *request id* complete; demount completed without label verification

Explanation

The DEMOUNT command has completed, but the external label of the volume has not been verified. This may have occurred because the request has completed during restart. If the volume to be demounted has been specified on the DEMOUNT command, the RMS master can not verify that the actual volume demounted is the one specified in the request.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2128I Request *request id* could not be completed due to restart

Explanation

The request could not be completed because DFSMS is restarting.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

Reissue the request.

FSM2130E Inserted volumes for library *library name* could not be processed because an available device could not be found

Explanation

New volumes have been inserted into the designated library, but the RMS master is not able to process them because no available device can be found.

System action

Automatic volume insert processing is not attempted. DFSMS continues processing other requests. Those volumes that remain in the insert category will

be processed the next time that new volumes are inserted into the library.

Library Administrator Response

The volumes can be processed by issuing a DFSMSRM SET VOLCAT or DFSMSRM SET VOLCAT BULK command, specifying an available device. Details regarding the failure may be found in the RMS master log file.

Suggested Action

None.

FSM2131I Request *request id* complete;
Category *catname* assigned to
device *rdev*

Explanation

The SET DEVCAT command has completed successfully.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2132I Request *request id* complete;
Category *catname* unassigned
from device *rdev*

Explanation

The RESET DEVCAT command has completed successfully.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2133I Automatic volume insert
processing started for library
library name

Explanation

This message is the second header message (following message FSM3000) for the report file generated by automatic volume insert processing.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2134E Inserted volumes not processed
for library *library name* because an
internal error was encountered

Explanation

An internal error is encountered during automatic volume insert processing.

System action

Automatic volume insert processing is stopped. DFSMS attempts to continue operations.

Library Administrator Response

Details regarding the cause of the failure can be obtained from the RMS master log file. DFSMS attempts to process those volumes that remain in the insert category the next time new volumes are added to the library. Alternatively, the volumes can be processed by issuing a DFSMSRM SET VOLCAT or DFSMSRM SET VOLCAT BULK command.

Suggested Action

None.

FSM2135I Automatic volume insert
processing completed; *number*
volumes successfully processed

Explanation

This message is the last message for the automatic volume insert report file. The number of volumes

processed indicates the number of volumes that have been successfully set to a new category.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2136W	A failure occurred attempting to detach device <i>rdev</i> following automatic volume insert processing
-----------------	--

Explanation

The specified device cannot be detached from the RMS master following the completion of automatic volume insert processing.

System action

DFSMS continues processing.

Library Administrator Response

Determine the current state of the device by issuing a CP QUERY (real device) command. If the device is still attached to the RMS master, attempt to detach it. Details regarding the failure can be found in the RMS master log file.

Suggested Action

None.

FSM2137W	Inserted volumes were processed for library <i>library name</i> but the report file could not be sent
-----------------	--

Explanation

Automatic volume insert processing processed volumes that had been inserted into the designated library, but a failure has occurred attempting to send the report file to the designated library notify user ID.

System action

DFSMS continues operation.

Library Administrator Response

Details regarding the cause of the failure can be obtained from the RMS master log file.

Suggested Action

None.

FSM2138W	A failure occurred attempting to assign inserted volume <i>vlabel</i> to a new category
-----------------	--

Explanation

This message may appear in the automatic volume insert report file if a volume cannot be processed. This failure may occur because the volume is not listed in the bulk insert list, because it conflicts with library partitioning criteria as defined in FSMRMSHR or FSMRMPRE, the installation-wide library partitioning exit or preprocessing exit, or because an internal error has occurred.

System action

The category of the specified volume is not changed. Automatic volume insert processing continues.

Library Administrator Response

Details regarding the cause of the failure can be obtained from the RMS master log file or the previous message in the report file, or both.

Suggested Action

None.

FSM2139I	Volume <i>vlabel</i> assigned to category <i>category name</i>
-----------------	---

Explanation

This message may appear in the automatic volume insert report file or the SET VOLUME BULK command report file, once for each volume that is successfully processed.

System action

Processing continues.

Library Administrator Response

None.

Suggested Action

None.

FSM2150I	SET VOLUME BULK processing started using file <i>filename filetype directory id</i>
-----------------	--

Explanation

This message is the second header message for the report file generated by SET VOLUME BULK processing.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2151I	SET VOLUME BULK processing completed; <i>number</i> volumes successfully processed
-----------------	---

Explanation

This message is the last message for the SET VOLUME BULK command report file. The number of volumes processed indicates the number of volumes that have been successfully set to a new category.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2152E	Bulk processing file, file ID <i>filename filetype directory id</i>, not found or contains no records
-----------------	--

Explanation

The file specified for bulk processing cannot be located or contains zero records.

System action

The bulk processing fails. DFSMS attempts to continue processing requests.

Library Administrator Response

Ensure that the bulk processing file specified exists and contains one or more records.

Suggested Action

None.

FSM2153E	Bulk processing file, file ID <i>filename filetype directory id</i> has a record length that is invalid
-----------------	--

Explanation

The file specified for bulk processing has a record length greater than 240.

System action

The bulk processing fails. DFSMS attempts to continue processing requests.

Library Administrator Response

Make sure the bulk processing file specified has a record length no greater than 240.

Suggested Action

None.

FSM2154E	Bulk processing file, file ID <i>filename filetype directory id</i> contains invalid records
-----------------	---

Explanation

The file specified for bulk processing contains one or more records that are invalid. An invalid record is one that is either not specified in the correct format or one that contains an invalid volume label, an invalid range of volume labels, or an invalid category.

System action

The bulk processing fails. DFSMS attempts to continue processing requests.

Library Administrator Response

See the RMS master log file to determine exactly which records are invalid and then correct them.

Suggested Action

None.

FSM2155E **Volume *volname* is not specified in an appropriate record in the bulk processing file, file ID *filename filetype directory id***

Explanation

Either the volume is not specified in the bulk processing file or it is specified in a record with a source category other than INSERT.

System action

The category of the specified volume is not changed. Automatic insert processing continues.

Library Administrator Response

Add the specified volume to the bulk processing file in a record that either does not specify the source category name or specifies INSERT as the source category name.

Suggested Action

None.

FSM2156E **Record number *record number* in bulk processing file, file ID *filename filetype directory id* is invalid**

Explanation

The record in the bulk processing file specified is invalid. An invalid record is one that is either not specified in the correct format or one that contains an invalid volume label, an invalid range of volume labels, or an invalid category.

System action

The bulk processing fails. DFSMS attempts to continue processing requests.

Library Administrator Response

Correct the specified record in the bulk processing file.

Suggested Action

None.

FSM2157W **A failure occurred attempting to assign volume *vlabel* to category *category name***

Explanation

This message may appear in the report file for the SET VOLUME BULK function if a volume cannot be processed. This failure may occur because the volume was not found in the specified source category, because it conflicts with library partitioning criteria as defined in FSMRMSHR or FSMRMPRE, the installation-wide library partitioning exit or preprocessing exit, or because an internal error has occurred.

System action

The category of the specified volume is not changed. Processing of the rest of the volumes in the bulk file continues.

Library Administrator Response

Details regarding the cause of the failure can be obtained from the RMS master log file or the previous message in the report file, or both.

Suggested Action

None.

FSM2160I **Library *libname* is in *opstate* mode**

Explanation

The specified library is in the specified mode of operation. This message is presented in response to a DFSMSRM QUERY LIBRARY OPSTATE command.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

Refer to the following information for an explanation of the specified mode.

opstate

Significance

automated

The library is in the normal automated operational mode.

paused

All mechanical library activity has stopped. The library manager continues to accept commands.

manual

All mechanical library activity has stopped. The library manager is providing instructions to the operator.

FSM2161I Library *libname* in degraded mode
Explanation

An element of the library has failed and the library is operating in a degraded mode. Some performance degradation may be experienced. Subsequent messages provide greater detail. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2162I The safety enclosure interlock is open; library = *libname*
Explanation

The safety enclosure interlock has been opened. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Close the safety enclosure interlock.

Suggested Action

None.

FSM2163I The vision system is not operational; library = *libname*
Explanation

The vision system has failed. Some operations cannot be performed, others are completed with warnings. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2164I Library *libname* is offline to the subsystem
Explanation

The library is offline to the 3490 subsystem and does not accept any commands. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2165I Library *libname* requires operator intervention
Explanation

One or more conditions have occurred that require operator assistance to resolve. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Consult the library manager console for more information.

Suggested Action

None.

FSM2166I	Library <i>libname</i> has encountered an unrecoverable error condition
-----------------	--

Explanation

The library has encountered an unrecoverable (Check 1) condition. All prior accepted library operations and pending responses are lost. The library manager is offline to the subsystem. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2167I	All storage cells are full; library = <i>libname</i>
-----------------	---

Explanation

All storage cells in the library are used. No new volumes can be inserted into the library. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

If unneeded volumes are in the library inventory they may be ejected with a SET VOLUME CATEGORY EJECT command.

Suggested Action

None.

FSM2168I	Library <i>libname</i> is out of cleaner volumes
-----------------	---

Explanation

The library is out of cleaner volumes, and a clean operation is required. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Insert some cleaner volumes into the library.

Suggested Action

None.

FSM2169I	DFSMSRM request <i>request id</i> completed. Report has been sent to your reader
-----------------	---

Explanation

A QUERY LIBRARY request has been made specifying the DETAILS option.

System action

DFSMS has finished processing the request and returns a report file to the user's reader.

Storage Administrator Response

None.

Suggested Action

Examine the reader file.

FSM2170E	Unexpected library status returned
-----------------	---

Explanation

This message is in response to a QUERY LIBRARY command with the DETAILS option specified. The library hardware has returned unexpected status; therefore all information reported may be incorrect.

System action

DFSMS continues operation.

Library Administrator Response

Check the library hardware.

Suggested Action

None.

FSM2171I **Library *libname*, Volume *vlabel*,
Details. Date: *date***

Explanation

This message is the first line of the report header for the DFSMSRM QUERY LIBRARY VOLUME command.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2172I **Library *libname*, Opstate, Details.
Date: *date***

Explanation

This message is the first line of the report header for the DFSMSRM QUERY LIBRARY OPSTATE command.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2173I **Library *libname*, Device *rdev*,
Details. Date: *date***

Explanation

This message is the first line of the report header for the DFSMSRM QUERY LIBRARY DEVICE command.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2180I **Library *libname*, Category
catname, Inventory *date time***

Explanation

This message is the first line of the report header for the QUERY LIBRARY INVENTORY command.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2181I **Category Name Volume PI MQ EP
EJ MP UL MM ME CLASS TYPE**

Explanation

This message is the second line of the report header for the QUERY LIBRARY INVENTORY command. The column headers are defined as follows:

PI

Volume is present in library, but is inaccessible.

MQ

Volume is mounted or queued for mount.

EP

Volume is eject pending.

EJ

Volume is in the process of being ejected.

MP

Volume is misplaced.

UL

Volume has an unreadable label or is unlabeled.

MM

Volume has been used during manual mode.

ME

Volume has been manually ejected.

Class

Class of volume.

Type

Type of media.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2182I	<i>Catname vlabel attributes class type</i>
-----------------	---

Explanation

This message is the body of the report file for the QUERY LIBRARY INVENTORY command. An 'x' is placed under the appropriate column header in message FSM2181.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2183I	<i>Library libname, category catname, contains number of volumes volumes</i>
-----------------	--

Explanation

There are *number of volumes* volumes in category *catname* within library *libname*. This message is the final message in the QUERY LIBRARY INVENTORY report file, or is presented in response to a QUERY LIBRARY COUNT command.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2188I	High-capacity input/output station is not enabled for library = <i>libname</i>
-----------------	---

Explanation

The high-capacity input/output station is not enabled. This was specified at installation time during the teach operation. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2189I	High-capacity output station in library = <i>libname</i> is full
-----------------	---

Explanation

The high-capacity output station is full of volumes. No more volumes can be assigned to the EJECTB category until some of the volumes are removed. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Remove some or all of the volumes from the high-capacity output station.

Suggested Action

None.

FSM2190I	Library <i>libname</i>, accessor is not available or is not operational
-----------------	--

Explanation

The accessor in the specified library is not operational. This message may appear in a report file as part of the

response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2191I	Library <i>libname</i>, gripper number <i>number</i> is not available, or is not operational
-----------------	---

Explanation

The specified gripper is not operational. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2192I	Library <i>libname</i>, gripper number <i>number</i> vision system not operational
-----------------	---

Explanation

The specified vision system is not operational. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2193I	Library <i>libname</i>, library manager is unavailable
-----------------	---

Explanation

The library manager is installed, but is not available. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2195I	Primary hard drive is unavailable; library = <i>libname</i>
-----------------	--

Explanation

The primary hard drive is installed, but is not available. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2196I	Secondary hard drive is unavailable; library = <i>libname</i>
-----------------	--

Explanation

The secondary hard drive is installed, but is not available. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2197I	Convenience input station is unavailable; library = <i>libname</i>
-----------------	---

Explanation

The convenience input station is installed, but is not available. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2198I	Convenience output station is unavailable; library = <i>libname</i>
-----------------	--

Explanation

The convenience output station is installed, but is not available. This message may appear in a report file as part of the response to a DFSMSRM QUERY LIBRARY OPSTATE command, and is always preceded by message FSM2160.

System action

DFSMS continues operation.

Library Administrator Response

Refer to *IBM TotalStorage Enterprise Automated Tape Library (3494) Operator's Guide*.

Suggested Action

None.

FSM2200I	Device <i>rdev</i>: Device Type = <i>type</i>, Library Name = <i>library name</i>, VLABEL = <i>vlabel</i>, Mounted Category = <i>category name</i>, Assigned Category = <i>category name</i>
-----------------	---

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY DEVICE request. **Note:** If a 3592 type device is encryption capable, *type* will be '3592E'.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2201I	Device <i>rdev</i>: Installed and available
-----------------	--

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY DEVICE (DETAILS request, and is always preceded by message FSM2200.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2202I	Device <i>rdev</i>: Volume loaded
-----------------	--

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY DEVICE (DETAILS request, and is always preceded by message FSM2200.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2203I	Device rdev: Cartridge loader installed and active
-----------------	---

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY DEVICE (DETAILS request, and is always preceded by message FSM2200.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2204I	Device rdev: Selection order = order
-----------------	---

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY DEVICE (DETAILS request, and is always preceded by message FSM2200. Selection order refers to how volumes from the assigned category are chosen in response to a DFSMSRM MOUNT CATEGORY request. The two possibilities are RANDOM and SEQUENTIAL.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2205I	Device rdev: Auto-fill enabled
-----------------	---------------------------------------

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY DEVICE (DETAILS request, and is always preceded by message FSM2200. "Auto-fill enabled" means that the library keeps filling the device's automatic cartridge loader with volumes from the assigned category when volumes are demounted.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2206I	MOUNT VOL vlabel ON DEVICE rdev FOR USER userid; ATTACH TO userid as vdev, READONLY READWRITE IDRC NOIDRC
-----------------	--

Explanation

This message is sent to the library notify user ID when the RMS master receives a MOUNT request specifying a manual library name.

System action

DFSMS continues processing the next request.

Library Administrator Response

Mount the requested volume.

Suggested Action

None.

FSM2207I	MOUNT VOL vlabel FOR USER userid; ATTACH TO userid as vdev, READONLY READWRITE IDRC NOIDRC
-----------------	---

Explanation

This message is sent to the library notify user ID when the RMS master receives a MOUNT request specifying a manual library name.

System action

DFSMS continues processing the next request.

Library Administrator Response

Mount the requested volume.

Suggested Action

None.

FSM2208I	MOUNT VOL <i>vlabel</i> FOR USER <i>userid</i>; ATTACH TO <i>userid</i>, READONLY READWRITE IDRC NOIDRC
-----------------	--

Explanation

This message is sent to the library notify user ID when the RMS master receives a MOUNT request specifying a manual library name.

System action

DFSMS continues processing the next request.

Library Administrator Response

Mount the requested volume.

Suggested Action

None.

FSM2209I	MOUNT VOL <i>vlabel</i> ON DEVICE <i>rdev</i> FOR USER <i>userid</i>; NOATTACH READONLY READWRITE IDRC NOIDRC
-----------------	---

Explanation

This message is sent to the library notify user ID when the RMS master receives a MOUNT request specifying a manual library name.

System action

DFSMS continues processing the next request.

Library Administrator Response

Mount the requested volume.

Suggested Action

None.

FSM2210I	Volume <i>vlabel</i>: volume class = <i>class</i>, volume type = <i>type</i>, category
-----------------	---

= *category name*, library = *library name*

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2211I	The volume is mounted
-----------------	------------------------------

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2212I	The volume is queued for mount
-----------------	---------------------------------------

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2213I The volume is being mounted**Explanation**

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2214I The volume is queued for demount**Explanation**

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2215I The volume is being demounted**Explanation**

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2216I The volume is queued for eject**Explanation**

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2217I The volume is being ejected**Explanation**

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2218I The volume is queued for audit**Explanation**

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2219I The volume is being audited

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2220I The volume is misplaced

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2221I The volume has an unreadable label

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2222I The volume was used during manual mode

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2223I The volume was manually ejected

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2224I The volume is present in the library, but inaccessible

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2225I Request identifier = *request id*;
Audit of volume *vlabel* for library
library name completed

Explanation

The specified volume has been audited.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2226E Request id = *request id*: audit of
volume *vlabel* for library *library
name* could not be completed
because the volume has an
unreadable label

Explanation

This information may be provided in response to a DFSMSRM QUERY VOLUME (AUDIT) request, and indicates that the volume has an unreadable or missing external label.

System action

DFSMS attempts to continue processing other requests.

Library Administrator Response

The volume can be ejected from the library and its external label replaced.

Suggested Action

None.

FSM2227I The Volume is assigned with the
Fast Ready attribute set

Explanation

This information is provided in response to a DFSMSRM QUERY LIBRARY VOLUME request and is always preceded by message FSM2210.

System action

DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2229I Copy Export Status = *status*

Explanation

Message is issued in response to a copy export operation. The message is issued based on responses returned from the hardware ATL detailing progress status of the copy export operation.

System action

The hardware copy export operation continues.

Library Administrator Response

None.

Suggested Action

None.

FSM2230E Request *request id* could not be
completed because device *rdev*
not available

Explanation

The device specified in the command is not available for use.

System action

The system fails the current action it is attempting. DFSMS continues processing other requests.

Library Administrator Response

None.

Suggested Action

Reissue the command specifying another device.

FSM2231E	Request <i>request id</i> could not be completed because an available device could not be found
-----------------	--

Explanation

No device is available to process the request.

System action

The system fails the current action it is attempting. DFSMS continues processing other requests.

Library Administrator Response

None.

Suggested Action

Reissue the command specifying an available device.

FSM2232I	Copy Export operation complete for volume <i>volume ID</i> return code <i>return code</i>
-----------------	--

Explanation

Hardware has completed the requested copy export operation. The completion code is included with the message response.

System action

The hardware copy export operation has completed.

Library Administrator Response

Review the return code returned from the hardware.

Suggested Action

If the operation did not complete successfully, correct the cause of the failure then reissue the copy export command.

FSM2233E	Request <i>Request ID</i> could not be completed because an active copy export operation for library <i>Library ID</i> is already in progress
-----------------	--

Explanation

Only one copy export operation can be active at a time for each library configured to RMS.

System action

The requested copy export operation is terminated.

Library Administrator Response

None.

Suggested Action

Wait for the current copy export operation to complete before issuing further copy export requests.

FSM2234E	Request <i>Request ID</i> could not be completed because not enough physical drives are available
-----------------	--

Explanation

A copy export operation was rejected by the hardware due to the indicated reason.

System action

The requested copy export operation is terminated.

Library Administrator Response

Ensure enough drives are available before initiating a copy export operation.

Suggested Action

Once enough drives are available, initiate a copy export operation.

FSM2235E	Copy Export request <i>Request ID</i> could not be completed because no volumes were found to export
-----------------	---

Explanation

Hardware has rejected a copy export request because the library determined there were no changes in volumes to copy since the last copy export operation.

System action

The requested copy export operation is terminated.

Library Administrator Response

Investigate the reason why there are no volumes within the library ready to export.

Suggested Action

Initiate[®] a copy export operation once there is volume information to export.

FSM2236E Request *request id* could not be completed because a failure occurred attempting to attach or detach device *rdev*

Explanation

The device specified in the command cannot be attached or detached.

System action

DFSMS fails the current action it is attempting, and continues processing other requests.

Library Administrator Response

None.

Suggested Action

Reissue the command, specifying another device.

FSM2240W The library sequence number *library sequence number* reported by device *rdev* does not match any defined library

Explanation

The specified device has been queried to determine its library sequence number, and the number it returned does not match any library sequence number that has been defined.

System action

DFSMS leaves the specified device uninitialized, and does not add it to the RM configuration.

Library Administrator Response

Check the DFSMS control file and ensure that all of the 3495 libraries have been correctly identified by an RM_AUTO_LIBRARY parameter. If so, the device may not be in any defined library.

Suggested Action

None.

FSM2241W Device *rdev* could not be initialized

Explanation

Initialization processing for the device has not been completed, probably because the device was not available to attach.

System action

DFSMS leaves the device uninitialized, and does not add it to the RM configuration. Initialization processing is attempted again for this device the first time that the device is specified in a command. DFSMS continues operation.

Library Administrator Response

None.

Suggested Action

None.

FSM2242E Invalid record found in RM configuration file at line *line number*

Explanation

The RM configuration file contains records that do not conform to the specified format.

System action

DFSMS continues to process the configuration file records and then stops.

Library Administrator Response

See the *z/VM: DFSMS/VM Customization* for the correct configuration file format.

Suggested Action

None.

FSM2243E RM configuration file not found, or this machine is not authorized to it

Explanation

The RM configuration file is not found, or this machine lacks the authorization to open and read it.

System action

Initialization of the RMS master ends.

Library Administrator Response

Create the RM configuration file and ensure that the RMS master virtual machine has authorization to open and read it.

Suggested Action

None.

FSM2244E **RM configuration file not fixed record format**

Explanation

The RM configuration file has a variable record-length format and requires a fixed format.

System action

Initialization of the RMS master ends.

Library Administrator Response

Recreate the RM configuration file with a fixed record-length format.

Suggested Action

None.

FSM2245E **RM configuration file is empty**

Explanation

The RM configuration file has been opened, but it contains no records.

System action

Initialization of the RMS master is terminated.

Library Administrator Response

The configuration information needs to be supplied in the file.

Suggested Action

None.

FSM2246E **RM configuration file logical record length exceeds allowed maximum**

Explanation

The logical record length of the RM configuration file exceeds 240.

System action

Initialization of the RMS master ends.

Library Administrator Response

Recreate the RM configuration file with logical record length less than or equal to 240.

Suggested Action

None.

FSM2999E **Request *request id* could not be completed successfully because an error occurred in DFSMS processing**

Explanation

DFSMS experienced an error condition that caused it to fail this request.

System action

The system fails the current request, and attempts to continue operation.

Library Administrator Response

See the RMS master log file for more information.

Suggested Action

Contact the library administrator.

FSM3000I **DFSMS Function Level *function level date time***

Explanation

This message indicates the function level of DFSMS/VM, as well as the date and time processing of this command started. The date and time are omitted when issued by the QUERY DFSMSLEVEL command.

System action

DFSMS/VM continues processing.

Storage Administrator Response

None.

Suggested Action

None.

FSM3001E **Duplicate parameter *parameter name* found in DFSMS control file at line *line number***

Explanation

Duplicate definitions of a DFSMS control file parameter have been made when only one is allowed.

System action

When this error occurs during initialization, DFSMS validates the remaining control file parameters and then terminates. When this error occurs during FILEPOOL BACKUP or FILEPOOL RESTORE, the migrated files are not backed up or restored.

Storage Administrator Response

Remove the duplicate DFSMS control file parameter.

Suggested Action

None.

FSM3003E	DFSMS control file is empty
-----------------	------------------------------------

Explanation

The DFSMS control file has been opened, but it contains no records.

System action

When this error occurs during DFSMS initialization, initialization of DFSMS fails. When this error occurs during FILEPOOL BACKUP or FILEPOOL RESTORE, the backup or restore of migrated data fails.

Storage Administrator Response

The parameters need to be supplied in the DFSMS control file.

Suggested Action

None.

FSM3004E	Invalid value <i>value</i> for parameter <i>name</i> at line <i>line number</i> in DFSMS control file
-----------------	--

Explanation

An invalid value has been given for a DFSMS control file parameter.

System action

When this error occurs during DFSMS initialization, DFSMS validates the remaining control file parameters and then terminates. When this error occurs during

FILEPOOL BACKUP or FILEPOOL RESTORE, the backup or restore of migrated files fails.

Storage Administrator Response

Correct the invalid value.

Suggested Action

None.

FSM3005E Variation 1	Invalid parameter <i>name</i> at line <i>line number</i> in DFSMS control file
---------------------------------	---

FSM3005E Variation 2	Invalid parameter at line <i>line number</i> in DFSMS control file
---------------------------------	---

Explanation

An invalid DFSMS parameter has been specified in the DFSMS control file or extraneous text appears on the line (comments) without being prefaced with the required asterisk (*).

System action

DFSMS/VM validates the remaining control file parameters and then terminates.

Storage Administrator Response

If the parameter is invalid, correct or remove the parameter. If extraneous text appears on the line, place an asterisk in front of the comments.

Suggested Action

None.

FSM3006E	Required parameter <i>name</i> not found in DFSMS control file
-----------------	---

Explanation

The specified required parameter has not been found in the control file.

System action

When this error occurs during DFSMS initialization, DFSMS validates the remaining control file parameters and then terminates. When this error occurs during FILEPOOL BACKUP or FILEPOOL RESTORE, the backup or restore of migrated files fails.

Storage Administrator Response

Supply the missing parameter in the DFSMS control file.

Suggested Action

None.

FSM3007E Invalid text found at line *line number* in DFSMS control file

Explanation

The only information having been allowed on each noncomment line of the DFSMS control file is a parameter name and those values associated with it. These can be optionally followed by a comment (comments begin with an asterisk). Any text having been placed between the parameter values and either the end of the line or a comment is invalid. This includes having more than one parameter on a line.

System action

When this error occurs during DFSMS initialization, DFSMS/VM validates the remaining control file parameters and then stops. When this error occurs during FILEPOOL BACKUP or FILEPOOL RESTORE, the backup or restore of migrated files fails.

Storage Administrator Response

The second parameter or extra text must be removed from the record.

Suggested Action

None.

FSM3008E Errors were encountered in DFSMS control file processing

Explanation

Errors have been found in the DFSMS control file. These may be due to:

- the invalid contents of the DFSMS control file. See accompanying messages for details of the error.
- internal errors occurring in the DFSMS control file processing routines. An "internal error" message has been logged.
- a CSL routine invoked during DFSMS control file processing in which a failing return code has been received. The message FSM0513 was issued containing the name of the CSL routine called and the return and reason code.

System action

DFSMS/VM stops.

Storage Administrator Response

Refer to the console error messages related to the DFSMS control file and correct the error conditions.

Suggested Action

None.

FSM3009E Errors have caused DFSMS initialization to stop

Explanation

Errors encountered during DFSMS/VM initialization have prevented DFSMS from initializing. The error messages have been written to the console.

System action

DFSMS/VM stops.

Storage Administrator Response

Refer to the console error messages and correct the error conditions.

Suggested Action

None.

FSM3010I DFSMS has restarted but was unable to restart *command*, request identifier *request id*. Please resubmit

Explanation

When DFSMS restarts after an abnormal end, only certain requests will be restarted and processed. This message indicates the request is one that will not be restarted.

System action

The attempt to restart the request ends and a response file is sent to the requester.

Storage Administrator Response

None.

Suggested Action

Check the report file and the report file completion message and determine whether or not to resubmit the command.

FSM3011I DFSMS stopped while processing request identifier *request id*.

Processing of this request is being reinitialized

Explanation

DFSMS stopped as a result of an abnormal end during the processing of this request. As part of DFSMS initialization, this request is restarted.

System action

The user's specified request is restarted.

Storage Administrator Response

None.

Suggested Action

None.

FSM3012E	DFSMS control file not found or this machine is not authorized to it
-----------------	---

Explanation

The DFSMS control file has not been found or the machine lacks the authorization to open and read it.

System action

When this error occurs during DFSMS initialization, initialization of DFSMS fails. When this error occurs during FILEPOOL BACKUP or FILEPOOL RESTORE, the backup or restore of migrated files fails.

Storage Administrator Response

Create the DFSMS control file and ensure that all master and server virtual machines are administrators to file pool VMSYS. If this error occurred during FILEPOOL BACKUP or FILEPOOL RESTORE, ensure that the issuer of the command has authority to open and read the control file.

Suggested Action

None.

FSM3013E	DFSMS control file not fixed record format
-----------------	---

Explanation

The control file has a variable record-length format and it requires a fixed format.

System action

When this error occurs during DFSMS initialization, initialization of DFSMS fails. When this error occurs during FILEPOOL BACKUP or FILEPOOL RESTORE, the backup or restore of migrated files fails.

Storage Administrator Response

Recreate the control file with a fixed record-length format.

Suggested Action

None.

FSM3014E	Dirid <i>dirid</i> of parameter <i>name</i> at line <i>line number</i> in DFSMS control file could not be created
-----------------	--

Explanation

DFSMS has determined that the *dirid* does not exist, and so has attempted to create it. This attempt has failed. Either the file space does not already exist or errors have occurred while creating subdirectories.

System action

DFSMS validates the remaining control file parameters and then terminates.

Storage Administrator Response

If the file space does not exist, create the file space prior to initializing DFSMS. Refer to *z/VM: DFSMS/VM Customization*. If the file space does exist, see accompanying messages FSM3192 and FSM0513 for further details of the error.

Suggested Action

None.

FSM3015W	No minidisk servers defined in the Variation 1 DFSMS control file
-----------------	--

Explanation

No minidisk servers are defined in the DFSMS control file. If minidisk work is submitted (MOVE or CHECK), it will not be processed.

System action

DFSMS/VM initialization continues.

Storage Administrator Response

If minidisk work is planned, define minidisk servers in the DFSMS control file and then stop and restart DFSMS.

Suggested Action

None.

FSM3015E Variation 2	No minidisk servers defined in the DFSMS control file
---------------------------------------	--

Explanation

No minidisk servers are defined in the DFSMS control file.

System action

The DFSMS command fails.

Storage Administrator Response

Define minidisk servers in the DFSMS control file and then stop and restart DFSMS.

Suggested Action

Contact the storage administrator.

FSM3016E	Parameter <i>parameter name</i> specifies duplicate userid <i>userid</i> at line <i>line number</i> in DFSMS control file
-----------------	--

Explanation

This parameter is attempting to use the same user ID specified in the control file for another virtual machine; for example, a minidisk server or a DFSMS master or server.

System action

DFSMS validates the remaining control file parameters and then terminates.

Storage Administrator Response

Change the user ID to one not specified in another control file parameter, refer to [z/VM: DFSMS/VM Customization](#).

Suggested Action

None.

FSM3017W	Default value NONETWRK.NOLUNAME used
-----------------	---

for **FULLY_QUALIFIED_LUNAME** parameter

Explanation

During DFSMS control file processing, the FULLY_QUALIFIED_LUNAME parameter is not specified, and DFSMS/VM uses the default value NONETWRK.NOLUNAME. DFSMS/VM has detected this condition and issued this warning message.

System action

Processing continues.

Storage Administrator Response

If the z/VM system running DFSMS is in a TSAF collection or an AVS global gateway, or this inclusion is planned for the future, planning and thought need to be taken when choosing a value for this parameter. The value used for this parameter is also used by DFSMS in the directory structure for secondary storage. If this value is changed after any files have been migrated, the installation has to manually perform some renaming in the secondary storage directory structure. Consult [z/VM: Connectivity](#) for TSAF and AVS considerations in choosing appropriate names for this control file parameter. If migration level 2 data is stored, the value for FULLY_QUALIFIED_LUNAME may not change if there is migration level 2 data. Consult [z/VM: DFSMS/VM Customization](#) for a description of the secondary storage naming considerations. If after investigation, the installation determines that default value for the FULLY_QUALIFIED_LUNAME parameter NONETWRK.NOLUNAME is sufficient, no further action needs to be taken.

Suggested Action

None.

FSM3018I	Migration level 1 file space is <i>file space</i>
-----------------	--

Explanation

This message indicates the file space name used for storing migrated data in migration level 1.

System action

Processing continues.

Storage Administrator Response

None.

Suggested Action

None.

FSM3019E	Missing value for parameter <i>name</i> at line <i>line number</i> in DFSMS control file
-----------------	---

Explanation

The DFSMS control file parameter value has not been given as required.

System action

When this error occurs during DFSMS initialization, DFSMS/VM validates the remaining DFSMS control file parameters and then stops. When this error occurs during FILEPOOL BACKUP or FILEPOOL RESTORE, the backup or restore of migrated files fails.

Storage Administrator Response

Supply the missing value.

Suggested Action

None.

FSM3020E	Invalid values for parameters <i>logging parm 1</i> and <i>logging parm 2</i>. Both cannot be <i>logging value</i>
-----------------	---

Explanation

During DFSMS control file processing, both of the *logging parms* have been specified—either explicitly in the DFSMS control file or implicitly by default values or a combination of both—to log errors at the 0 level. This is invalid. At least one of the logging parms must be changed to another logging value.

System action

DFSMS/VM validates the remaining DFSMS control file parameters and then stops.

Storage Administrator Response

Correct the invalid value. Refer to [z/VM: DFSMS/VM Customization](#).

Suggested Action

None.

FSM3021E	Log messages will be sent to console due to internal errors
-----------------	--

Explanation

An internal DFSMS/VM error has occurred that prevents messages from being written to the log file as specified in the DFSMS control file.

System action

System log messages are sent to the service machine's console instead of the log file.

Storage Administrator Response

Refer to the accompanying FSM0506, FSM0513, or FSM3024 message for an explanation of the error.

Suggested Action

None.

FSM3022E	Error opening system log file <i>fn ft dirid</i>. Log messages will be sent to console until log file can be opened
-----------------	--

Explanation

DFSMS/VM has attempted to open a DFSMS log file, but an error has occurred.

System action

DFSMS/VM continues to attempt to open the file. Until the file can be opened, system log messages are sent to the service machine's console instead of the log file.

Storage Administrator Response

Refer to the accompanying FSM0513 or FSM3060 message for the return and reason codes, and release all locks on the file.

Suggested Action

None.

FSM3023I	Log file <i>fn ft dirid</i> now open after previous attempts to open failed. Writing log messages to file is now resumed
-----------------	---

Explanation

Previous attempts to open the log file have failed and log messages have been sent to the console instead, regardless of the DFSMS_LOG_TO_CONSOLE setting in the DFSMS control file DGTVCNTL DATA in VMSYS:DFSMS.CONTROL. The latest call to open the

log file has been successful and messages are now written to the log file.

System action

DFSMS/VM writes log messages to the file.

Storage Administrator Response

None.

Suggested Action

None.

FSM3024E	Error opening system log file <i>fn ft dirid</i> due to ACS processing error. Log messages will be sent to the console until the log file can be opened
-----------------	--

Explanation

DFSMS/VM has attempted to open the DFSMS log file, but automatic class selection processing refused creation of the file.

System action

DFSMS/VM does not attempt to reopen the file for the remainder of the day. An attempt is made to reopen the file on the following day. Until then, system log messages are sent to the service machine's console instead of the log file.

Storage Administrator Response

Correct the installation's ACS processing to allow creation of the log file. Once this is done, messages can be written to the log file immediately if DFSMS/VM has been stopped and started again.

Suggested Action

None.

FSM3025W	File pool unavailable for ML1 file space <i>file space</i>
-----------------	---

Explanation

The name of the directory used for storing migrated data is specified but its file pool server is not available. Any commands needing access to migration level 1 (MIGRATE and RECALL) will fail until migration level 1 becomes available.

System action

DFSMS continues reading the control file.

Storage Administrator Response

If the migration level 1 file pool is not in the process of becoming available, investigate the problem with the migration level 1 server and resolve.

Suggested Action

None.

FSM3026E	File pool <i>file pool</i> is unavailable
-----------------	--

Explanation

The file pool *file pool* is unavailable. If the file pool referred to is the file pool on the WORK_DIRECTORY control file parameter, then initialization cannot continue until that file pool becomes available.

System action

When issued by initialization processing on the DFSMS master or server, initialization fails.

Storage Administrator Response

Investigate why the file pool server is not ready to process requests.

Suggested Action

None.

FSM3027E	Directory <i>dirid</i> not found or you are not authorized to it
-----------------	---

Explanation

This message is issued during FILEPOOL BACKUP when the user is not authorized to the specified directory or the directory does not exist.

System action

Backup of primary storage continues, but no backup is made of secondary storage.

Storage Administrator Response

Verify that the correct file pool and file space have been specified in the DFSMS control file. If the correct parameter has been specified, ensure that the file pool is started before reissuing the FILEPOOL BACKUP command. Verify that the virtual machine detecting

the error has authority to the specified file pool and file space.

Suggested Action

None.

FSM3028E **DFSMS control file record length exceeds 240**

Explanation

The control file's record length exceeds the maximum length allowed.

System action

Initialization of DFSMS/VM fails.

Storage Administrator Response

Edit or use CMS COPYFILE on the existing control file to create the control file with a record length less than or equal to 240.

Suggested Action

None.

FSM3029E **File space *file space of parameter name* does not exist in file pool *file pool specified on that same parameter* or you are not authorized to it**

Explanation

This message is displayed on the DFSMS master's console during initialization when the control file parameter specifying both a file pool and file space, contains a file space that is not enrolled in the file pool or the virtual machine does not have authority to that file space.

System action

Initialization of the DFSMS master fails.

Storage Administrator Response

Verify that the correct file pool and file space have been specified on the control file parameter. If they are correct, make sure the file space is enrolled in the file pool with the appropriate amount of space. See [z/VM: DFSMS/VM Customization](#) for details. Ensure that the master and server virtual machines have authority to this file pool and file space.

Suggested Action

None.

FSM3030E **File pool *file pool* specified in parameter *name* is unavailable**

Explanation

The file pool specified in the control file parameter is unavailable.

System action

DFSMS/VM initialization stops.

Storage Administrator Response

Verify that the correct file pool and file space have been specified. If the correct parameter has been specified, ensure that the file pool is started before restarting DFSMS.

Suggested Action

None.

FSM3031W **Migration level 2 is not currently specified in the DFSMS control file**

Explanation

Because migration level 2 is not currently specified in the DFSMS control file, backup or restore of the migration level 2 data (if there is any) has not occurred. If the installation is not using migration level 2, then this warning can be ignored.

System action

The FILEPOOL BACKUP or FILEPOOL RESTORE continues.

Storage Administrator Response

If the installation has migration level 2 data, then the migration level 2 parameter should be specified in the DFSMS control file and the FILEPOOL BACKUP or RESTORE command should be resubmitted.

Suggested Action

None.

FSM3032I **Virtual machine name is stopping**

Explanation

Virtual machine *virtual machine name* is stopping as a result of either a STOP command or an abend, and is no longer accepting new requests.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3033W	Accounting data will not be accurate since this is a second level z/VM system
-----------------	--

Explanation

This DFSMS system is running on a second level system and therefore the accounting data will not be accurate. Accounting data is only accurate on a first level z/VM system.

System action

DFSMS/VM initialization continues, but accounting numbers will not be accurate.

Storage Administrator Response

None.

Suggested Action

None.

FSM3034E	When control file parameter MIGRATION_LEVEL_1 or MIGRATION_LEVEL_2 is specified, parameter DFSMS_SERVER_VM must also be specified
-----------------	--

Explanation

In order to use space management capabilities of DFSMS/VM, space management servers must be specified in the DFSMS control file. MIGRATION_LEVEL_1 and MIGRATION_LEVEL_2 are part of the space management portion of DFSMS/VM and therefore require a DFSMS_VM_SERVER to be specified in the DFSMS control file.

System action

Processing of the DFSMS control file ends.

Storage Administrator Response

If space management functions are required, specify at least one DFSMS_SERVER_VM parameter in the DFSMS control file and then restart DFSMS/VM. If space management functions are not required, then comment out MIGRATION_LEVEL_1 and MIGRATION_LEVEL_2 and restart DFSMS/VM.

Suggested Action

None.

FSM3035E	No authority to the specified file pool file pool and file space
-----------------	---

Explanation

This message is displayed when an attempt is made by the virtual machine to access the specified file pool and file space and the virtual machine does not have authority to that file pool.

System action

The command fails. If this error is detected during initialization, an additional message indicates what DFSMS control file parameter caused the error and initialization stops.

Storage Administrator Response

Verify that the virtual machine detecting the error has authority to the specified file pool and file space.

Suggested Action

None.

FSM3036E	LE/370 not available
-----------------	-----------------------------

Explanation

DFSMS/VM requires that the IBM SAA® AD/Cycle® Language Environment®/370 (program #5688-198) be installed and accessible to the DFSMS master and the DFSMS server machines when the product is enabled for space management. This environment is also required for the SFS utilities (FILEPOOL BACKUP, FILEPOOL RESTORE, or FILEPOOL FILELOAD) if migration level 2 is specified in the DFSMS/VM control file. This message is issued when the LE/370 environment is not available or not accessible.

System action

If the error occurred during initialization, DFSMS/VM initialization stops. If the error occurred during a FILEPOOL BACKUP, FILEPOOL RESTORE, or FILEPOOL FILELOAD the command fails.

Storage Administrator Response

Ensure that the DFSMS master and DFSMS server virtual machines have access to the LE/370 product. If the error occurred during DFSMS/VM initialization, ensure that LE/370 is on an accessed disk at the time of DFSMS/VM initialization and ensure that LOADLIB SCEERUN exists on that accessed disk. If the error occurred during a FILEPOOL BACKUP, FILEPOOL RESTORE, or FILEPOOL FILELOAD command, ensure that LE/370 is on an accessed disk and that the library SCEERUN is specified as a LOADLIB. To find out what libraries have been specified, issue the QUERY LOADLIB command. Consult [z/VM: DFSMS/VM Customization](#) for installation instructions.

Suggested Action

None.

FSM3037E	No authority for dirid <i>dirid</i> of parameter <i>name</i> at line <i>line number</i>
-----------------	--

Explanation

The master and server virtual machines lack the proper authority to the directory specified in this DFSMS control file parameter.

System action

DFSMS/VM validates the remaining DFSMS control file parameters and then stops.

Storage Administrator Response

Ensure that the master and server virtual machines have authority to the directory specified in this parameter.

Suggested Action

None.

FSM3038E	DFSMS/VM virtual machines must have administrator authority to migration file pool <i>file pool</i>
-----------------	--

Explanation

The master and server virtual machines need administrator authority to the migration level 1 file pool.

System action

DFSMS/VM validates the remaining control file parameters and then terminates.

Storage Administrator Response

Ensure that the master and server virtual machines have administrator authority to the migration level 1 file pool. This can be accomplished temporarily using the CMS ENROLL ADMINISTRATOR command while the file pool is running, but is made permanent by using the ADMIN statement in the DMSPARMS file for the migration level 1 file pool virtual machine.

Suggested Action

None.

FSM3039E	This virtual machine <i>virtual machine id</i> is not defined in the DFSMS control file
-----------------	--

Explanation

All virtual machines running DFSMS must be defined in the DFSMS control file. This virtual machine is attempting to run DFSMS but is not defined in the DFSMS control file as either the DFSMS master, DFSMS server, minidisk server, or RMS master.

System action

DFSMS/VM stops.

Storage Administrator Response

Ensure that the virtual machine is defined in the DFSMS control file as either the DFSMS master, DFSMS server, minidisk server, or RMS master.

Suggested Action

None.

FSM3040E	Either DFSMS servers or minidisk servers must be defined in the DFSMS control file
-----------------	---

Explanation

At least one server machine must be defined in the DFSMS control file. If minidisk functions are required,

then at least one minidisk server should be defined. If space management functions are required, then at least one DFSMS server should be defined. If both functions are required then define both types of servers.

System action

DFSMS/VM stops after verifying the rest of the control file.

Storage Administrator Response

Ensure that at least one server virtual machine is defined in the DFSMS control file.

Suggested Action

None.

FSM3041W **No DFSMS servers defined in the control file**

Explanation

No DFSMS servers are defined in the DFSMS control file.

System action

Initialization continues.

Storage Administrator Response

If space management functions are desired, stop DFSMS/VM, install the space management function, and restart DFSMS/VM. Refer to *z/VM: DFSMS/VM Customization* for instructions on installing space management.

Suggested Action

None.

FSM3041S **No DFSMS servers defined in the control file and space management work was requested**

Explanation

No DFSMS servers are defined in the DFSMS control file and space management work requiring a space management server has been requested.

System action

The request is ignored.

Storage Administrator Response

Stop the system with the DFSMS STOP SMS (IMMED and update your system to include space management, then restart the system and resubmit the request. Refer to *z/VM: DFSMS/VM Customization* for instructions on installing space management.

Suggested Action

None.

FSM3042W **ML2 password not specified in the DFSMS control file**

Explanation

The migration level 2 password is not specified in the DFSMS control file. If authentication is used on the migration level 2 server, then a password must be specified on the MIGRATION_LEVEL_2 keyword. Failure to specify this password results in the failure of migration level 2 transactions and queries. If authentication is not enabled on the ML2 server, ML2 data integrity may be compromised. It is recommended that authentication always be enabled on the ML2 server.

System action

DFSMS/VM initialization continues.

Storage Administrator Response

If authentication processing on the migration level 2 server is desired, then specify a password on the MIGRATION_LEVEL_2 keyword that matches the password for the node DFSMS on the ML2 server, and stop and restart the DFSMS master machine.

Suggested Action

None.

FSM3043E **Parameter name at line line number contains too many subdirectory levels**

Explanation

The work directory parameter can contain only seven levels of subdirectories.

System action

DFSMS/VM validates the remaining control file parameters and then stops.

Storage Administrator Response

Correct the control file parameter and then restart DFSMS/VM.

Suggested Action

None.

FSM3050S **APPC/VM resource *resource ID* cannot be initialized**

Explanation

There has been an error identifying an APPC/VM resource.

System action

The system fails initialization.

Storage Administrator Response

The APPC/VM resource given in the DFSMS control file should be verified to ensure it is a valid global resource identifier. For instance, the APPC/VM resource must not have already been identified within the system, or if it is a global resource, within the TSAF collection. Also, the DFSMS_MASTER_VM machine CP directory entry should be checked to verify it is authorized to identify any APPC/VM resource (local or global).

Suggested Action

None.

FSM3051W **DFSMS global APPC/VM resource connected to by userid *userid***

Explanation

A communications connection has been made with the global APPC/VM resource. Connections to this APPC/VM resource are unsupported.

System action

The attempt to connect to the DFSMS global resource is logged, the connection is severed, and DFSMS continues processing.

Storage Administrator Response

Determine the source of the connection to the DFSMS global resource.

Suggested Action

None.

FSM3052S **Critical DFSMS task ended abnormally**

Explanation

A critical DFSMS/VM task has ended abnormally.

System action

When this message is issued on the DFSMS master or RMS master, it refers to a critical subprocess without which DFSMS/VM begins termination processing.

When this message is issued on the DFSMS server, it refers to one of the server tasks specified on the DFSMS control file parameter DFSMS_SERVER_VM (refer to *z/VM: DFSMS/VM Customization* for details about these tasks). The server continues to run until all such server tasks have ended normally or abnormally. If all of the server tasks end, the server stops, but the master continues to process. The ability of DFSMS/VM to do work is inhibited by the total number of ended tasks on all servers.

Storage Administrator Response

Check the log messages for errors that would explain the cause of the task termination, and correct the error.

Suggested Action

None.

FSM3053I **All DFSMS local APPC/VM resources initialized**

Explanation

During DFSMS initialization, all local APPC/VM resources are identified to CP.

System action

Initialization of DFSMS continues.

Storage Administrator Response

None.

Suggested Action

None.

FSM3054I **DFSMS global APPC/VM resource *resource id* initialized**

Explanation

During DFSMS/VM initialization, DFSMS/VM identifies the DFSMS global resource to CP. The identified global resource is obtained from the control file's GLOBAL_RESOURCE_ID parameter.

System action

Initialization of DFSMS/VM continues.

Storage Administrator Response

None.

Suggested Action

None.

FSM3055E	APPC/VM connection could not be made to <i>virtual machine</i>
-----------------	---

Explanation

A DFSMS server has attempted to establish an APPC/VM connection with the DFSMS master, but is unable to do so. The DFSMS master must be available to a DFSMS server within 15 minutes of the server's first attempt to make the connection.

System action

The server terminates.

Storage Administrator Response

Ensure the DFSMS master is able to successfully initialize. Resolve any errors that you encounter.

Suggested Action

None.

FSM3056I	Server task ended. <i>Number of tasks of total tasks</i> tasks now active
-----------------	--

Explanation

A task running on a DFSMS server has ended.

System action

The server continues to run with *number of tasks* tasks.

Storage Administrator Response

If the task has ended as part of DFSMS termination processing, this is a normal condition. If not, check the log file for error messages indicating the reason for the task ending, and correct any error conditions. If a large number of tasks have failed, DFSMS can be stopped and restarted in order to start those tasks again.

Suggested Action

None.

FSM3057S	CP has revoked APPC/VM resource <i>resource id</i>
-----------------	---

Explanation

An APPC/VM resource has been revoked. If this resource is the one identified by the GLOBAL_RESOURCE_ID parameter in the DFSMS control file, the revocation is most likely due to another DFSMS system using the same global resource ID at the time communications with the other system is established.

System action

DFSMS terminates.

Storage Administrator Response

Ensure that the DFSMS APPC/VM resource given in the control file is a valid and unique global resource identifier. If there is already migrated data for a system, care must be exercised when renaming the global resource ID. See [z/VM: DFSMS/VM Customization](#) for more information.

Suggested Action

None.

FSM3058E	DFSMS server could not communicate with DFSMS master
-----------------	---

Explanation

This message is issued by a DFSMS server machine when communications with the DFSMS master machine fails.

System action

The server task ends.

Storage Administrator Response

None.

Suggested Action

None.

FSM3059E	DFSMS is unable to write messages to the log file because of an out of space condition. Log messages will be written to the console instead
-----------------	--

Explanation

DFSMS is unable to log more messages to the log file. The directory's storage group or file space limits have been exceeded.

System action

Log messages will be written to the console instead of the log file.

Storage Administrator Response

Check the log directory as specified by the DFSMS_LOG_TO_FILE or RM_LOG_TO_FILE. Issue the CMS QUERY LIMITS command for the log directory's file space to determine the space availability in that file space, or issue the CMS QUERY FILEPOOL STORGRP command for the log directory's file pool to determine if the storage group is out of space. Increase the amount of space available to the log directory accordingly. Also, erase files not needed or keep log files in a file pool managed by DFSMS and migrate in a timely manner. Refer to *z/VM: CMS Commands and Utilities Reference* for instruction on the use of these SFS commands and on increasing the available space.

Suggested Action

None.

FSM3060E	DFSMS system log file is locked by another user
-----------------	--

Explanation

DFSMS/VM is unable to write messages to the log file because it is currently locked by another user. One possible cause is that another user may be editing the system log file.

System action

Log messages are written to the console.

Storage Administrator Response

Issue the CMS QUERY LOCK command against the file to determine who has the file locked.

Suggested Action

None.

FSM3061E	Previous attempt to autolog server <i>server name</i> failed. The server is now eligible to be autologged again
-----------------	--

Explanation

The server never connected to the DFSMS master. Investigate why the server is not coming up by logging on to the server virtual machine and watching it initialize.

System action

This server is now eligible to be autologged if needed.

Storage Administrator Response

If the problem preventing the server from autologging has not been corrected, correct the problem. Otherwise future attempts to autolog the server continue to fail.

Suggested Action

None.

FSM3062E	Unable to restore migration level 2 data
-----------------	---

Explanation

Migration level 2 data exists in the backup data but cannot be restored because migration level 2 is not specified in the DFSMS control file.

System action

The FILEPOOL RESTORE command fails.

Storage Administrator Response

Ensure that the migration level 2 parameter is specified in the DFSMS control file and resubmit the restore command.

Suggested Action

None.

FSM3063W Unable to return GLOBAL LOADLIB to the original state**Explanation**

DFSMS/VM may issue a GLOBAL LOADLIB for certain libraries needed to perform a FILEPOOL BACKUP, FILEPOOL RESTORE, or FILEPOOL FILELOAD. When processing of any of these SFS commands is complete, DFSMS/VM attempts to return the GLOBAL LOADLIB back to the state it was before the SFS command was issued. This message is issued if an error occurred while returning these libraries.

System action

Processing of the SFS command continues.

Storage Administrator Response

None.

Suggested Action

None.

FSM3064E File not found in ML2**Explanation**

The FILEPOOL FILELOAD command cannot restore a file ID specified in the CONTROL FILELOAD file, either because the file did not exist in the storage group at the time the FILEPOOL BACKUP command was run, or the file exists in the backup file but no migrated data is found in the ML2 repository. Missing migrated data can occur if the data in the ML2 repository was previously erased or the ML2 backup entry was deleted with the DFSMS DELETE ML2BACKUP command.

System action

Processing of the SFS command stops.

Storage Administrator Response

None.

Suggested Action

Verify that you are using the correct backup file or that you have specified the correct file ID in the CONTROL FILELOAD file and reissue the command. Or, restore the failing file with a more recent backup file.

FSM3065E Required TSM file spaces not defined**Explanation**

When MIGRATION_LEVEL_2 is specified in the DFSMS control file, DFSMS/VM requires that there be TSM file spaces defined to hold migrated data. These are defined when the DFSMS master machine initializes.

When this message is displayed on the DFSMS master machine console or log, it means that the TSM server is available, but for some reason the file spaces could not be defined.

When this message is displayed on a DFSMS server machine console or log, it means that the server waited for fifteen minutes for the DFSMS master machine to define the file spaces, but they were never defined.

When this message is displayed during file pool backup or restore operations, it means that the DFSMS master machine has not successfully defined the file spaces.

System action

On the DFSMS master or server machine, initialization fails.

On a user machine performing file pool backup or restore activities, the backup or restore operation fails.

Storage Administrator Response

On the DFSMS master machine, ensure that the migration level 2 server is configured properly so that the DFSMS master machine can define the file spaces.

On the DFSMS server machine, ensure that the DFSMS master machine is logged on before the DFSMS server machines are logged on.

On a user machine performing file pool backup or restore operations, ensure that the DFSMS master machine has successfully initialized at least once since the MIGRATION_LEVEL_2 parameter was placed into the DFSMS control file.

Suggested Action

None.

FSM3101E Storage group's catalog is locked by another user or command**Explanation**

The catalog for a storage group in a file pool has already been opened via DMSOPCAT. This is most likely due to another DFSMS MANAGE or CONVERT command having been issued for the same storage group in this file pool, although another installation

application may have performed the DMSOPCAT. Use the ISMF QUERY command to determine if a DFSMS MANAGE or CONVERT command is active.

System action

Processing of the command is ended.

Storage Administrator Response

Check that the correct storage group number and file pool have been specified in the command. If either a DFSMS CONVERT or MANAGE command or another running installation application issues DMSOPCATs against that storage group, you must wait until these other commands finish before running this command again.

Suggested Action

None.

FSM3102E Variation 1	DFSMS work directory is out of space
---------------------------------------	---

Explanation

There is not enough room in the DFSMS work directory, which holds DFSMS temporary files, to process DFSMS commands. Either the directory's storage group or file space limits have been exceeded. This condition could be caused by many commands running concurrently or by commands such as DFSMS MANAGE. Extra space may also be depleted if the work directory is being used for other purposes, such as storing the DFSMS system log files (check the DFSMS_LOG_TO_FILE or RM_LOG_TO_FILE parameter in the DFSMS control file).

System action

Processing of currently running commands continue but any report files from those commands may be incomplete, and report files may be truncated. All other commands with the WAIT or NOWAIT option will fail.

Storage Administrator Response

The name of the work directory is specified in the DFSMS control file by the WORK_DIRECTORY parameter. If possible, do not use this directory in the LOG_TO_FILE parameter of the DFSMS control file. Issue the CMS QUERY LIMITS for the work directory's file space to determine the space availability in that file space, or issue the CMS QUERY FILEPOOL STORGRP command for the work directory's file pool to determine if the storage group is out of space.

Increase the amount of space available to the work directory accordingly. Refer to *z/VM: CMS Commands and Utilities Reference* for instruction on the use of these SFS commands and on increasing the available space.

Suggested Action

Contact the storage administrator.

FSM3103E	ML2 is unavailable; processing of files using ML2 not performed
-----------------	--

Explanation

The ML2 server is not logged on or not running, and files cannot be moved to or from migration level 2.

System action

The MIGRATE and RECALL commands fail. The MANAGE command with LEVELS ALL or LEVELS ML1 continues, but is limited to expiring files that are not migrated and to migrating files to migration level 1. The MANAGE command with LEVELS ML2 fails.

Storage Administrator Response

Ensure that the migration level 2 server is logged on and running, and that the value for the MIGRATION_LEVEL_2 parameter in the DFSMS control file is correct.

Suggested Action

Contact the storage administrator.

FSM3105I	nnnn files eligible to be migrated
-----------------	---

Explanation

This message indicates the total number of files eligible for migration, according to the level and threshold options specified in the management class attributes.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3106I Variation 1	<i>nnnn</i> blocks available in primary storage group
---------------------------------	--

FSM3106I Variation 2	<i>nnnn</i> blocks available in ML1
---------------------------------	--

Explanation

This message indicates how many blocks are available at the end of MANAGE command processing. When *nnnn* is -1, it indicates that the attempt to get the number of free blocks in the storage group has resulted in an error.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3107E Variation 1	MANAGE cannot migrate or move files to ML2, or erase migrated files, due to errors
---------------------------------	---

Explanation

The ML2 server, handling migration level 2, cannot process the MANAGE command request.

System action

MANAGE command processing continues, but is limited to erasing files that are not migrated and to migrating files to migration level 1.

Storage Administrator Response

Check the log messages for more information, and correct the condition affecting the migration level 2 server.

Suggested Action

Contact the storage administrator.

FSM3107E Variation 2	MANAGE with LEVELS ML2 ended due to errors
---------------------------------	---

Explanation

The ML2 server, handling migration level 2, cannot process the MANAGE command request.

System action

MANAGE command processing ends because the LEVELS option specified migrating of files only to migration level 2.

Storage Administrator Response

Check the log messages for more information, and correct the condition affecting the migration level 2 server. The MANAGE command may be able to be run successfully with LEVELS ML1.

Suggested Action

Contact the storage administrator.

FSM3108E Variation 1	ML1 file pool <i>file pool</i> is unavailable
---------------------------------	--

FSM3108E Variation 2	Primary storage file pool <i>file pool</i> is unavailable
---------------------------------	--

FSM3108E Variation 3	ML2 server <i>server userid</i> is unavailable
---------------------------------	---

Explanation

The file pool or migration level 2 server is not logged on or is not running. When a file pool or migration level 2 server is unavailable, any attempt to migrate or recall a file to or from the affected server fails. Note that this includes migrates that are the result of DFSMS MANAGE processing. When this message is issued after a DFSMS QUERY STATUS command, if the migration level 2 server is unavailable and the server is actually logged on and running then the server could be having problems communicating with the DFSMS master machine.

System action

DFSMS/VM continues but migrate and recall requests to the affected file pool or migration level 2 server fail until the file pool or migration level 2 server becomes available. The MANAGE command stops if it detects that the migration level 1 or the primary storage file pool is unavailable. If the migration level 2 server is unavailable, the MANAGE command may be able to continue processing, but without moving files into migration level 2. The latter case depends on the LEVELS option used when the MANAGE command is issued. The REPORT command stops if it detects that either migration level 1 or the primary storage file pool are unavailable. The REPORT command will also stop if the migration level 2 server is unavailable but is defined in the DFSMS control file.

Storage Administrator Response

Investigate why the file pool or server is not available. Ensure that the values for the `MIGRATION_LEVEL_1` and the `MIGRATION_LEVEL_2` parameter in the DFSMS control file are correct. If migration level 2 is unavailable, the `MANAGE` command can be submitted with the `LEVELS ML1` option, which limits `MANAGE` processing to migrating files to migration level 1. However, migration level 1 must be available for the `MANAGE` and `MIGRATE` commands to process any files, even with the `LEVELS ML2` option. Refer to the DFSMS `MANAGE` command in the *z/VM: DFSMS/VM Storage Administration* for a description of the `LEVELS` option.

If the command issued is `DFSMS MIGRATE` then ensure that the values for `MIGRATION_LEVEL_1` in the DFSMS control file are correct. Also make sure that the migration level 1 server is operational.

If the command issued is `DFSMS QUERY STATUS` and the migration level 2 server is unavailable then verify that the migration level 2 server is logged on and running. If the migration level 2 server is logged on and running, then verify that the migration level 2 server is communicating with the DFSMS master machine. Refer to *z/VM: DFSMS/VM Customization* for information on defining the migration level 2 server.

Suggested Action

Contact the storage administrator.

FSM3110E Variation 1	ML1 is out of space
---------------------------------------	----------------------------

FSM3110E Variation 2	ML2 is out of space
---------------------------------------	----------------------------

Explanation

There is not enough room in the migration level 1 file space or storage group, or in the migration level 2 repository to store any more migrated files.

System action

If a file is being migrated, processing of the file fails. If this condition is detected by the `MANAGE` command, the `MANAGE` processing of files being migrated or moved to the affected migration level ends.

Storage Administrator Response

See accompanying log messages for more information on the error that occurred, and increase the amount of space available to the migration level. The problem can be prevented by issuing the `MANAGE` command more often, expiring files sooner, or in the case of

migration level 1 being full, changing the management class parameters to move more data to migration level 2.

Suggested Action

Contact the storage administrator.

FSM3110E Variation 3	Primary storage is out of space
---------------------------------------	--

Explanation

There is not enough room in primary storage to store the recalled file.

System action

If a file is being recalled, processing of the file fails.

Storage Administrator Response

See accompanying log messages for more information on the error that occurred, and increase the amount of space available in primary storage.

Suggested Action

Contact the storage administrator.

FSM3111E	Unable to move file <i>primary file name</i> from ML1 to ML2
-----------------	---

Explanation

This message is written to the report file for a `MANAGE` command if an error occurs and the file *primary file name* cannot be moved. This may be caused by space problems, file pool availability, or other errors.

System action

The file is not moved, and processing proceeds to the next file to be moved.

Storage Administrator Response

Check the messages in the log or the report file for more information.

Suggested Action

Contact the storage administrator.

FSM3112E Variation 1	No value for the <code>MIGRATION_LEVEL_2</code> parameter has been defined in the control file
---------------------------------------	---

Explanation

An ML2 server has to be defined in the DFSMS control file in order for files to be migrated to or deleted from migration level 2.

System action

If a file is being migrated, processing of the file fails. If this condition is detected by the MANAGE command, the MANAGE command ends. If this condition is detected by the DELETE ML2BACKUP command, the DELETE ML2BACKUP command ends.

Storage Administrator Response

Ensure that the MIGRATION_LEVEL_2 control file keyword and values are defined correctly.

Suggested Action

Contact the storage administrator.

FSM3112W Variation 2	No value for the MIGRATION_LEVEL_2 parameter has been defined in the control file
---------------------------------	--

Explanation

An ML2 server has to be defined in the DFSMS control file in order for files to be migrated to migration level 2.

System action

If a file is being migrated, processing of the file continues with the file migrated to migration level 1.

Storage Administrator Response

Ensure that the MIGRATION_LEVEL_2 control file keyword and values are defined correctly.

Suggested Action

None.

FSM3114I Variation 1	ML1 file pool <i>file pool id</i> is available
---------------------------------	---

Explanation

This message is displayed during DFSMS QUERY STATUS command processing when the migration level 1 file pool is available.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3114I Variation 2	ML2 server <i>server userid</i> is available
---------------------------------	---

Explanation

This message is displayed during DFSMS QUERY STATUS command processing when the migration level 2 server is available.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3114I Variation 3	Minidisk server <i>server userid</i> is waiting for work
---------------------------------	---

Explanation

This message is displayed during DFSMS QUERY STATUS command processing when the minidisk server is waiting for work.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3114I Variation 4	Minidisk server <i>server userid</i> is busy
---------------------------------	---

Explanation

This message is displayed during DFSMS QUERY STATUS command processing when the minidisk server is busy.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3115I **Number of entries backup entries were deleted from ML2 storage**

Explanation

This message indicates the number of backup entries that have been deleted during DFSMS DELETE ML2BACKUP command processing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3116E **Number of waiting requests cannot be determined**

Explanation

This message is displayed on the user's console during DFSMS QUERY STATUS processing when a problem occurs while determining the total number of requests for the system.

System action

The DFSMS QUERY STATUS command completes.

Storage Administrator Response

Investigate why the number of requests could not be determined. Examine the log files for any other messages.

Suggested Action

None.

FSM3117I **DFSMS REPORT
SPACEMANAGEMENT STORGROUP**

**summary for file pool *file pool* and
storage group *storage group***

Explanation

This is a section header message on a storage group report. The summary following this header represents summary data for the entire storage group. The data is accumulated from the individual file space summaries for all users enrolled in the storage group. The message contains the following fields:

- File pool—File pool for the report
- Storage group—Storage group for the report

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3118I **The following files are migrated but DFSMS has migrated data in both ML1 and ML2:**

Explanation

This message is a section header for both the file space and storage group report. The list of files following this message shows files migrated in both migration level 1 and migration level 2. Migrated data in migration level 1 always takes precedence over data in migration level 2. Therefore, if a file is recalled, the migration level 1 data is recalled.

System action

None.

Storage Administrator Response

Delete the migration level 2 data with the DFSMS DELETE command. Refer to *z/VM: DFSMS/VM Storage Administration* for more information.

Suggested Action

None.

FSM3119I **The following tokens represent migrated data for which there are no files in primary storage:**

Explanation

This message is a section header for the storage group report. The list of files following this message shows files which have either migration level 1 entries or migration level 2 entries with no corresponding files in primary storage.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3120I **The following files are migrated:**

Explanation

This is a section header for the file space report. A list of all migrated files that the user has the authority to see follows this message.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3121I **The following files are not migrated but DFSMS has migrated data for them:**

Explanation

This message is a section header for the file space and storage group reports. The list of files following this message shows files that are not migrated but DFSMS/VM has migrated data for them.

System action

None.

Storage Administrator Response

Use the DELETE command to erase files not migrated but DFSMS/VM shows migrated data for them.

Suggested Action

Contact the storage administrator.

FSM3122I **The following files are migrated but no migrated data exists for them:**

Explanation

This is the section header for the file space and storage group reports. The list of files following this message shows files that are migrated but DFSMS/VM has no migrated data for them.

System action

None.

Storage Administrator Response

Verify that the DFSMS control file parameters used to specify secondary storage (MIGRATION_LEVEL_1 and MIGRATION_LEVEL_2 parameters) have not been changed. These parameters may only be changed if there is no migration level 2 capability. If the parameters have been changed, the original directory where the migrated data resides needs to be renamed to correspond to the new directory naming scheme. If the directory has not changed, this file needs to be restored from a backup copy.

Suggested Action

Contact the storage administrator.

FSM3123I **Primary Management Date Last Date Migration Token for**

Explanation

This message is the first header for the body of the file space or storage group report. It identifies the fields in the body of the report. The message contains the following fields:

- Migrated—Date Migrated column header
- Level—Migration Level column header
- Delete Command—Token for Delete Command column header

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3124I	Filename Filetype 4K Blocks Class Referenced <i>Migrated Level Delete</i> <i>Command</i>
-----------------	---

Explanation

This message is the second header for the body of the file space or storage group report. It identifies the fields in the body of the report. The message contains the following fields:

- Migrated—Date Migrated column header
- Level—Migration Level column header
- Delete Command—Token for Delete Command column header

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3125I	<i>filename filetype size management class last referenced date migrated date migration level delete token</i>
-----------------	---

Explanation

This is the body of the file space report or storage group report. It contains the following fields:

- File name—name of file.
- File type—type of file.
- Size—size of file in 4K blocks. This is the number of 4K blocks that would have been required if the file were not migrated.
- Management class—management class of the file (--NULL-- and --NONE--).
- Last referenced date—last date this file has been referenced (mm/dd/yy).
- Migrated date—date this file has been migrated.
- Migration level—migration level file exists on.
- Delete token—Delete token. If this file is in primary storage and shows as not being migrated, but there is migrated data for it, this token can be used on the DELETE command to erase the migrated data. This is

done to resolve out-of-synch conditions. This token only appears on the report if this condition exists.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3126I Variation 1	Files migrated for this file space: <i>number of migrated files</i>
FSM3126I Variation 2	Files migrated for this storage group: <i>number of migrated files</i>

Explanation

For a file space report, this summary message indicates the total number of files in this file space that are migrated. For a storage group report, this summary message indicates all files migrated for the storage group. It contains the following fields:

- Report type—Displays either file space or storage group
- Number of migrated files—The number of files migrated

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3127I Variation 1	Physical 4K blocks in use by secondary storage for this file space: <i>number of blocks</i>
FSM3127I Variation 2	Physical 4K blocks in use by secondary storage for this storage group: <i>number of blocks</i>

Explanation

For a file space report, this summary message indicates the number of 4K blocks in use by secondary storage. For a storage group report, this summary message indicates the total number of 4K blocks in

use by secondary for this entire storage group. It contains the following fields:

- Report type—Displays either file space or storage group
- Number of blocks—The number of 4K blocks used in secondary storage

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3128I Variation 1	Physical 4K blocks in use by this file space: <i>number of blocks</i>
FSM3128I Variation 2	Physical 4K blocks in use by this storage group: <i>number of blocks</i>

Explanation

For a file space report, this summary message indicates the number of physical 4K blocks in use by this file space. For a storage group report, this summary message indicates the number of physical 4K blocks in use by this storage group. When files are migrated, they no longer use space in primary storage; however, they do use space in secondary storage. The physical space number consists of what the user is actually using in primary storage and secondary storage. The message contains the following fields:

- Report type—Displays either file space or storage group
- Number of blocks—The number of physical 4K blocks in use

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3129I Variation 1	Logical 4K blocks currently in use by this file space: <i>number of blocks</i>
---------------------------------	---

FSM3129I Variation 2	Logical 4K blocks currently in use by this storage group: <i>number of blocks</i>
---------------------------------	--

Explanation

For a file space report, this summary message indicates the number of logical 4K blocks in use (committed blocks used) by primary storage for this file space. For a storage group report, this summary message indicates the total number of logical 4K blocks in use (committed blocks used) by primary storage for all enrolled users in the storage group. This is the amount of storage that would have been used by this file space or storage group if files were not migrated. The message contains the following fields:

- Report type—Displays either file space or storage group
- Number of blocks—The number of logical 4K blocks in use

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3130I	<i>Number of files</i> files recalled from migration level 1
-----------------	---

Explanation

This message appears in the RECALL report and indicates the total number of files successfully recalled from migration level 1.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3131E	File <i>fn ft dirid</i> not recalled due to error
-----------------	--

Explanation

This message is sent to the user if an error has occurred and a file cannot be recalled. Further information appears in the log.

System action

The file is not recalled, and processing proceeds to the next file.

Storage Administrator Response

Check the reader files and log messages to resolve the problem.

Suggested Action

Contact the storage administrator.

FSM3132I **Number of files files migrated to migration level 1**

Explanation

This message appears in the MIGRATE report and indicates the total number of files successfully migrated to migration level 1.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3133E **File *fn ft dirid* not migrated due to error**

Explanation

An error has occurred migrating the specified file. Further information regarding the error appears in the report file or in the log.

System action

The file is not migrated.

Storage Administrator Response

Check the reader files and log messages to resolve the problem.

Suggested Action

Contact the storage administrator.

FSM3134W **No files found which match the specified criteria**

Explanation

No files have been found that match the criteria specified with the ALTER, MIGRATE, or RECALL command. Criteria includes pattern-matching characters specified for the file name or file type. This message also appears when files have been found that match the specified criteria but all files are not selected for processing because of an error (requester is not authorized to the file, the file is not a base file or an alias file, the file is not migrated [for recall], the file is already migrated [for migrate], and so on).

System action

None.

Storage Administrator Response

None.

Suggested Action

Verify the pattern-matching character specification on the command, and the authorization to the files to be processed.

FSM3135E **Files in directory *dirid* not eligible for migration**

Explanation

A request has been received to migrate files from a file space whose top directory name begins with DFSMS. DFSMS/VM will not migrate files from such a directory.

System action

The MIGRATE command is terminated.

Storage Administrator Response

Ensure file spaces to be managed by DFSMS/VM do not have a top directory name that begin with DFSMS.

Suggested Action

None.

FSM3136I **Migration of file *fn ft dirid* not allowed by FSMMECHK exit, return code = *return code***

Explanation

Migration of the specified file has been disallowed by the FSMMECHK installation-wide exit.

System action

The file is not migrated.

Storage Administrator Response

Verify that the FSMMECHK installation-wide exit is controlling the migration of files as desired. If it is not operating as desired, recode and retest the routine.

Suggested Action

Contact the storage administrator.

FSM3137E Variation 1	Migration of file <i>fn ft dirid</i> not allowed due to management class <i>management class</i> attributes
---------------------------------	--

FSM3137E Variation 2	Migration of file <i>fn ft dirid</i> not allowed due to system management class attributes
---------------------------------	---

Explanation

This message indicates that a file failed to migrate during migrate processing because the management class has indicated this file is not eligible for migration.

System action

This file is not migrated.

Storage Administrator Response

If the resulting action (no migration) is intended, then no further action is necessary. However, if the management class attributes are incorrect, then they should be updated and the configuration containing the new attributes must be activated before the file will be migrated. If the file has an inappropriate management class, the routines that the installation uses to assign management classes needs to be reviewed and updated. The ALTER or CONVERT commands can be used to change the management class as appropriate.

Suggested Action

Contact the storage administrator.

FSM3138E	Recall of file <i>fn ft dirid</i> rejected by ACS processing, reason = <i>reason code</i>
-----------------	--

Explanation

If ACS processing fails a request because the installation-wide exit requests that failure, this message is logged and put in the report file that is sent to the user who requested the RECALL. The reason in the message is determined by the installation, by one of the following:

1. ACS routine exit code
2. ACS REXX exit return code
3. ACS module exit reason code

System action

Recall for this file stops.

Storage Administrator Response

If the intent is to fail the recall operation, no further action is necessary. If ACS processing is not operating in a manner that you have intended, then you need to tailor ACS processing appropriately and reactivate the configuration before the file can be recalled. Check the log for further information.

Suggested Action

Contact the storage administrator.

FSM3139I Variation 1	<i>Number of processed files out of number of eligible files</i> files moved from ML1 to ML2 for storage group <i>storage group</i> in file pool <i>file pool</i>
---------------------------------	--

FSM3139I Variation 2	<i>Number of processed files out of number of eligible files</i> files migrated from primary storage to ML1 storage group <i>storage group</i> in file pool <i>file pool</i>
---------------------------------	---

FSM3139I Variation 3	<i>Number of processed files out of number of eligible files</i> files migrated from primary storage to ML2 storage group <i>storage group</i> in file pool <i>file pool</i>
---------------------------------	---

Explanation

This message indicates the status of file movement and migration during MANAGE command processing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3140I	Erasure and migration of files not performed. Storage group is below high threshold
-----------------	--

Explanation

If THRESHOLD is specified or defaulted to the MANAGE command, space in use by primary storage is checked before beginning erasure and migration. If the space utilization is below the high threshold level specified by the storage administrator in the control file, MANAGE command processing is not performed.

System action

The MANAGE command is terminated.

Storage Administrator Response

None.

Suggested Action

None.

FSM3141I	File <i>fn ft dirid</i> was erased
-----------------	---

Explanation

When a file is erased as part of MANAGE command processing, this message appears in the report sent to the command issuer.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3142E	File <i>fn ft dirid</i> not erased due to error
-----------------	--

Explanation

An error has occurred in erasing the specified file during MANAGE command processing.

System action

MANAGE command processing continues.

Storage Administrator Response

See the DFSMS log messages or the report file, or both, for prior messages that describe the error.

Suggested Action

None.

FSM3143I	Migration of files not performed. Erasure of expired files brought storage group below low threshold
-----------------	---

Explanation

The MANAGE command performs erasure and migration of files based on threshold values. If storage group utilization has been brought below the low threshold value by erasing expired files, this message is issued and MANAGE command processing is completed.

System action

The MANAGE command processing is completed.

Storage Administrator Response

None.

Suggested Action

None.

FSM3144I	DFSMS MANAGE STORGRP command summary:
-----------------	--

Explanation

This message is the first line of the summary section of the MANAGE command.

System action

The MANAGE command summary is printed.

Storage Administrator Response

None.

Suggested Action

None.

FSM3145I	Number of files files occupying number of blocks 4K blocks erased
-----------------	--

FSM3145I	Number of files files occupying number of blocks 4K blocks
-----------------	---

have been migrated from primary storage to ML1

FSM3145I
Variation 3 *Number of files files occupying number of blocks 4K blocks have been migrated from primary storage to ML2*

FSM3145I
Variation 4 *Number of files files occupying number of blocks 4K blocks have been moved from ML1 to ML2*

Explanation

This message indicates the number of files and 4K blocks processed during the MANAGE command.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3146I **DFSMS MANAGE processing started for storage group *storage group* in file pool *file pool***

Explanation

This message is written at the beginning of each MANAGE command to identify this as a manage report.

System action

The MANAGE command processing continues.

Storage Administrator Response

None.

Suggested Action

None.

FSM3147I **High Threshold: *high threshold* Low Threshold: *low threshold***

Explanation

The high and low thresholds specified in this message are the high and low shared file system storage group thresholds specified by the installation in the DFSMS control file. If thresholds are specified on a MANAGE command, processing is started only if the storage

group utilization is above the high threshold. When thresholds are specified, processing continues until storage group utilization reaches low threshold.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3148I **Storage group percent utilization before MANAGE: *percent utilization***

Explanation

This message indicates the percentage of storage group in use by shared file system before MANAGE command expiration and migration processing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3149I **Storage group percent utilization after MANAGE: *percent utilization***

Explanation

This message indicates the percentage of the storage group in use by shared file system after the MANAGE command expiration and migration processing have occurred. When *percent utilization* is -1, it indicates that the attempt to obtain the storage group utilization has resulted in an error.

System action

None.

Storage Administrator Response

Check the log in the DFSMS master for a message indicating that calling CSL routine DMSQUSG resulted in an error.

Suggested Action

None.

FSM3150I	DFSMS <i>command</i> completed with no errors
-----------------	--

Explanation

The specified DFSMS command has been completed.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3151I	DFSMS STOP SMS command accepted. DFSMS is stopping
-----------------	---

Explanation

DFSMS has accepted the STOP command for processing and is about to terminate.

System action

DFSMS shuts down.

Storage Administrator Response

None.

Suggested Action

None.

FSM3152I	DFSMS <i>command</i> processing started for <i>fn ft dirid</i>
-----------------	---

Explanation

This message indicates processing has started for the DFSMS command.

System action

DFSMS/VM continues processing.

Storage Administrator Response

None.

Suggested Action

None.

FSM3153I	DFSMS <i>command</i> request identifier <i>request id</i>
-----------------	--

Explanation

This message identifies the command associated with this report and the identifier assigned to the request. This request identifier can be used to DISCARD the command.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3154I	Erasure of file <i>fn ft dirid</i> not allowed by FSMMECHK exit, return code = <i>return code</i>
-----------------	--

Explanation

This file has expired, but its erasure is disallowed by the FSMMECHK installation-wide exit. The return code in this message is the return code from the FSMMECHK exit.

System action

The file is not erased.

Storage Administrator Response

Verify that the FSMMECHK installation-wide exit is controlling the erasure of files as desired. Refer to *z/VM: DFSMS/VM Customization* for return code information.

Suggested Action

None.

FSM3155W Variation 1	Unable to process request. Installation specified DFSMS as expiration only
---------------------------------	---

FSM3155W Variation 2	No migration of files is performed. Installation specified DFSMS as expiration only
---------------------------------	--

Explanation

The `MIGRATION_LEVEL_1` parameter in DFSMS control file `DGTVCNTL DATA` in `VMSYS:DFSMS.CONTROL` has not been specified by this installation. This means that DFSMS/VM is operating in an expiration-only mode and can perform no migration and no recall of files. If the user has issued a `DFSMS REPORT SPACEMANAGEMENT FILESPACE` command, which gives a report on migrated files, the command ends. If the user has issued a `MANAGE` command, the only processing of the storage group is the erasure of expired files.

System action

`MANAGE` command processing ends after expired files are erased. Other requests are not processed (migration of file, recall of file, or report file space).

Storage Administrator Response

Verify that you want DFSMS/VM to be in expiration-only mode. If expiration-only mode is not intended, there may have been some error specifying the `MIGRATION_LEVEL_1` parameter in DFSMS control file `DGTVCNTL DATA` in `VMSYS:DFSMS.CONTROL`. Check the DFSMS master machine console log for messages issued when DFSMS/VM was initialized and take appropriate action.

Suggested Action

Contact the storage administrator.

FSM3156E	File <i>fn ft d</i>rid missing migrated data and cannot be recalled
-----------------	--

Explanation

This message appears on the `RECALL` report when an attempt is made to recall a file, and the migrated data for that file is missing. This may occur if control file parameters `GLOBAL_RESOURCE_ID` and `FULLY_QUALIFIED_LUNAME` have been renamed, and the procedures documented in the *z/VM: DFSMS/VM Storage Administration* have not been followed. This may also occur if secondary storage has been modified.

System action

Processing continues with the next file or directory.

Storage Administrator Response

Verify that the control file parameters `GLOBAL_RESOURCE_ID` and `FULLY_QUALIFIED_LUNAME` have not been renamed.

These values are used for the naming hierarchy for secondary storage. These values can only be changed if there is no migration level 2 data, or if all migrated data in migration level 2 has been recalled. These values can be changed if there is migration level 1 data, by following the procedures documented in the *z/VM: DFSMS/VM Storage Administration*. Ensure that secondary storage cannot be modified. Restore the file from a backup copy if the problem cannot be resolved.

Suggested Action

Contact the storage administrator.

FSM3157E	Userid not enrolled in file pool
-----------------	---

Explanation

An invalid user ID has been entered for the `DFSMS REPORT SPACEMANAGEMENT FILESPACE` or the `DFSMS REPORT SPACEMANAGEMENT` command. The requested user ID is not enrolled in the requested file pool.

System action

Processing of this command stops.

Storage Administrator Response

None.

Suggested Action

Check the user ID that has been entered and reissue the command if necessary.

FSM3158I	DFSMS <i>command</i> completed, but warning or error conditions have occurred
-----------------	--

Explanation

The specified DFSMS command has completed processing but errors have been found. Further information about the errors may be found in the log and in the report file.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3159I DFSMS command could not complete

Explanation

The specified DFSMS command cannot be completed because errors have been found during processing. Further information regarding the errors may be found in the log or in the report.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3160I DFSMS master is stopping

Explanation

DFSMS master is stopping as a result of a STOP command and is no longer accepting new requests.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3161I DFSMS master is running

Explanation

This message indicates that DFSMS master is running, and is able to accept requests.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3162I DFSMS has nnnn outstanding requests

Explanation

This message indicates the total number of requests that have not yet started processing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3163I Migration Level 1: insert value

Explanation

- For a file space report: When this summary message follows FSM3126, it indicates the number of files migrated to migration level 1. The insert value represents a count of all files migrated for the specified file space. When this summary message follows FSM3127, it indicates the number of 4K blocks in use by migration level 1. The insert value represents the number of 4K blocks used in migration level 1 for the specified file space.
- For a storage group report: When this summary message follows FSM3126, it indicates the total number of files migrated to migration level 1. This value is a summation of the number of files migrated for each file space enrolled in this storage group. The insert value represents a total count of files migrated for all users enrolled in the storage group. When this summary message follows FSM3127, it indicates the total number of 4K blocks in use by migration level 1. This value is a summation of the number of 4K blocks used in migration level 1 for each file space enrolled in this storage group. The insert value represents the total number of 4K blocks used in migration level 1 for all users enrolled in the storage group.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3164I **Migration Level 2: *insert value***

Explanation

- For a file space report: When this summary message follows FSM3126, it indicates the number of files migrated to migration level 2. The insert value represents a count of all files migrated for the specified file space. When this summary message follows FSM3127, it indicates the number of 4K blocks in use by migration level 2. The insert value represents the number of 4K blocks used in migration level 2 for the specified file space.
- For a storage group report: When this summary message follows FSM3126, it indicates the total number of files migrated to migration level 2. This value is a summation of the number of files migrated for each file space enrolled in this storage group. The insert value represents a total count of files migrated for all users enrolled in the storage group. When this summary message follows FSM3127, it indicates the total number of 4K blocks in use by migration level 2 when used following the physical 4K blocks in use by secondary storage message. This value is a summation of the number of 4K blocks used in migration level 2 for each file space enrolled in this storage group. The insert value represents the total number of 4K blocks used in migration level 2 for all users enrolled in the storage group.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3165I **Physical 4K blocks in use by
Variation 1 primary storage for this file space:
*number of blocks***

FSM3165I **Physical 4K blocks in use by
Variation 2 primary storage for this storage
*group: number of blocks***

Explanation

This summary message indicates the number of physical 4K blocks in use by primary storage for either this file space or this storage group. The physical

space number consists of what the user is actually using in primary storage for a file space report or a summation of the actual primary storage for all users enrolled in a storage group for a storage group report. The message contains the following fields:

- Report type—Displays either file space or storage group
- Number of blocks—The number of physical 4K blocks in use in primary storage

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3166I **Physical 4K blocks saved for this
Variation 1 file space due to compaction:
*number of blocks***

FSM3166I **Physical 4K blocks saved for this
Variation 2 storage group due to compaction:
*number of blocks***

Explanation

This summary message indicates the number of 4K blocks saved due to compaction for this file space for a file space report. For a storage group report, this summary message indicates the total number of 4K blocks saved for this storage group due to compaction. The message contains the following fields:

- Report type—Displays either file space or storage group
- Number of blocks—The number of 4K blocks saved due to compaction

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3167E **Management class for *fn ft dirid*
not in the active configuration**

Explanation

This message indicates that a management class is not in the active configuration during RECALL, MIGRATE, MANAGE, or CONVERT processing. Note that the management class that is not in the active configuration is the new management class that the ACS routines have determined for this file or directory.

System action

If a RECALL is being processed, the file is assigned no management class and the file is recalled. If any other function is being performed (MIGRATE, MANAGE, or CONVERT), the file or directory is not processed and processing continues with the next eligible file or directory.

Storage Administrator Response

Other messages will be displayed on the console or to the log with further information.

Suggested Action

Contact the storage administrator.

FSM3168W	Installation failed ACS request for <i>fn ft dirid</i>, reason code = <i>reason code</i>
-----------------	---

Explanation

Automatic class selection processing has rejected this request. Reason is the ACS exit code. The request may be failed either by the ACS routine, the installation REXX exit, or the module exit.

System action

Automatic class selection processing fails for this file or directory. A management class is not assigned to this file or directory. Processing continues with the next file or directory.

Storage Administrator Response

Verify that the system processing that occurred is consistent with your installation's policies. If it is consistent, no action is necessary. If it is not consistent, tailor your ACS processing according to your installation's policies, and activate your configuration.

Suggested Action

None.

FSM3169I	DFSMS <i>command</i> processing started for file pool <i>file pool</i> and storage group <i>storage group</i>
-----------------	--

Explanation

This message indicates the file pool and storage group that the DFSMS command has been run against. The following fields are displayed in this message:

- Command—Command insert for DFSMS REPORT SPACEMANAGEMENT STORGROUP
- File Pool—The file pool the command is processing
- Storage Group—The storage group the command is processing

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3170I	The command has been discarded as a result of a <i>command</i> request
-----------------	---

Explanation

This message is included in a report sent to the user if the request has been discarded while waiting to be processed or while being processed. *Command* will be either STOP or DISCARD.

A request will be discarded for one of the following reasons:

- DFSMS DISCARD command issued
- ISMF DISCARD command issued
- DFSMS STOP SMS IMMEDIATE command issued
- ISMF STOP command issued
- The 3494 operator cancelled the library request.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3171I **File *fn ft dirid* assigned management class *management class***

Explanation

This message indicates that a file has been assigned another management class by the DFSMS CONVERT command.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3172I **File with token *delete token* deleted from ML1**

FSM3172I **File with token *delete token* deleted from ML2**

Explanation

The specified file has been deleted from ML1 or ML2 storage. This action is initiated by a DFSMS DELETE command or a CMS ERASE. The DFSMS DELETE command erases an extraneous file from ML1 storage. The CMS ERASE command removes ML1 or ML2 data and references to a migrated file that has been erased.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3173E **File *fn ft* not deleted from secondary storage due to error**

Explanation

An attempt to delete the specified file from secondary storage has failed, but the primary catalog entry for the file has been erased. This action has been initiated by a DFSMS DELETE command or a CMS ERASE command. For the DFSMS DELETE command, an

erasure of an extraneous file from secondary storage has failed. For the CMS ERASE command, removal of secondary storage data and all references to a migrated file have failed. The failure of this file deletion implies that this file remains in secondary storage as an extraneous file.

System action

The DFSMS DELETE command or CMS ERASE command fails.

Storage Administrator Response

The specified file in secondary storage should be deleted. Check the log file for additional details as to why the command has failed.

Suggested Action

None.

FSM3174I ***nnnn* files and directories converted**

Explanation

This message indicates the total number of files and directories that were successfully processed during the CONVERT or MANAGE command.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3175E **Errors occurred while attempting to load ACS exits**

Explanation

ACS exits cannot be loaded. If a CONVERT command issues this message, the command terminates because without the ACS exits, CONVERT is unable to determine the management class assignments for files and directories. If a MANAGE command issues this message, MANAGE continues, but assignment of management classes to files with no management class does not occur.

System action

Command processing terminates if a CONVERT has been issued. Command processing continues if MANAGE has been issued, but no conversion occurs for files or directories that have no management class, therefore these files are ignored in the manage process.

Storage Administrator Response

Check the log messages of the server that has been running the command for further information regarding the problem with loading the ACS exits. Correct the problem and resubmit the CONVERT or MANAGE command.

Suggested Action

None.

FSM3176I	<i>nnnn files and directories could not be converted</i>
-----------------	---

Explanation

This message indicates the total number of files and directories that have not had a management class assigned to them during CONVERT processing. This count also includes items not converted because ACS processing has rejected the assignment of a management class to a file or directory, or that ACS processing has attempted to assign a management class that is not in the active configuration. More information regarding the error can be found in the command report file or the DFSMS log files, or both.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3177I	<i>DFSMS CONVERT processing started for storage group <i>storage group</i> in file pool <i>file pool</i></i>
-----------------	---

Explanation

This message, issued at the start of the CONVERT command, indicates which file pool and storage group that the CONVERT command is being run against.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3178E	<i>Management class <i>management class</i> not in the active configuration</i>
-----------------	--

Explanation

This message is issued during DFSMS MANAGE or MIGRATE when processing a file managed with a management class that is not in the active configuration. No space management operations can be made on this file.

System action

The file is not migrated or erased. DFSMS MANAGE or MIGRATE processing continues with the next file.

Storage Administrator Response

If this management class should be in the active configuration, then update the configuration and reactivate it. If the file or directory needs a different management class, then use the CONVERT or ALTER command to update the management class of the file or directory.

Suggested Action

Contact the storage administrator.

FSM3179E	<i>File <i>fn ft dirid</i> not converted due to error</i>
-----------------	--

Explanation

An error has occurred during processing and the file has not had a new management class assigned to it.

System action

Processing continues with the next eligible file.

Storage Administrator Response

Check the log messages for further information regarding the error.

Suggested Action

None.

FSM3180E **Token *token* not found**

Explanation

The token specified on the DFSMS DELETE command is invalid. This token does not map to any valid DFSMS file that needs to be deleted. Either the token has been entered incorrectly, or the file has already been deleted.

System action

No file in DFSMS secondary storage is deleted.

Storage Administrator Response

Verify that you have entered the correct token and resubmit the command if necessary. If you have obtained the token from a report that is out-of-date, the file may already have been deleted. Reissue the DFSMS REPORT command to determine if the token is still valid.

Suggested Action

None.

FSM3181E **File *fn ft dirid* is currently locked by another user and cannot be processed, reason code = *reason code***

Explanation

If the ALTER command has been issued, the file's management class cannot be changed due to the file being locked. If the CONVERT command has been issued, the file cannot have another management class assigned to it due to a lock. If a MANAGE command has been issued, the file cannot be erased. If a MIGRATE or RECALL command has been issued, the request cannot be processed.

System action

The file is not processed. Processing continues with the next eligible file for MANAGE or CONVERT. Command processing stops for others.

Storage Administrator Response

Issue CMS QUERY LOCK to determine if the lock is an explicit one held by another user. After that user has released the lock, resubmit the command. If the lock is implicit or is held by the system, resubmitting

the request at a later time, after the lock is released, should remove the problem.

Suggested Action

If the user has an explicit lock on the file in question, the user must release the lock and reissue the command. Otherwise, contact the storage administrator.

FSM3182E **User not authorized to issue command**

Explanation

The issuer of this command is not authorized to perform this function. If the command issued is a MANAGE or CONVERT, the issuer must be a DFSMS administrator in order to issue the command. If the command issued is a DFSMS REPORT SPACEMANAGEMENT FILESPACE, the issuer must be a DFSMS administrator and an SFS administrator if the command is issued against a file space other than the issuer's own file space. If the command issued is a DFSMS REPORT SPACEMANAGEMENT STORGROUP, the issuer must be a DFSMS administrator and an SFS administrator.

System action

Processing of this command stops.

Storage Administrator Response

If the user should be authorized to issue this command, update the appropriate user's authorization and ask the user to resubmit the command.

Suggested Action

Contact the storage administrator.

FSM3183I **DFSMS *command* processing started for file pool *file pool* and userid *userid***

Explanation

This message indicates the file pool and user ID that the DFSMS command has been run against.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3184I	File <i>fn ft dirid</i> assigned a null management class
-----------------	---

Explanation

This message indicates that a file has been successfully assigned the NULL management class during convert processing. This means that during migration and manage processing, the parent directory management class is used to determine management class characteristics. If the parent management class is also null, then the default management class is used during migrate and manage to determine the criteria by which the file is to be processed.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3185E	File <i>fn ft dirid</i> not found or you are not authorized
-----------------	--

Explanation

This message appears in the ALTER, MIGRATE, and RECALL reports when the command issuer does not have the appropriate authority to the indicated file. Write authority is needed to migrate a file and read authority is needed to alter or recall a file.

System action

Processing continues with the next file or directory.

Storage Administrator Response

None.

Suggested Action

Contact the owner of the file and ask for the appropriate level of authority to the file.

FSM3186I Variation 1	MANAGE processing for storage group <i>storage group</i> in file pool <i>file pool</i> now moving files from ML1 to ML2
---------------------------------	--

FSM3186I Variation 2	MANAGE processing for storage group <i>storage group</i> in file pool <i>file pool</i> now migrating files from primary storage to ML1
---------------------------------	---

FSM3186I Variation 3	MANAGE processing for storage group <i>storage group</i> in file pool <i>file pool</i> now migrating files from primary storage to ML2
---------------------------------	---

Explanation

This message indicates the start of file movement or migration during MANAGE command processing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3187E	File <i>fn ft dirid</i> not migrated, cannot be recalled
-----------------	---

Explanation

This message appears in the RECALL report when an attempt is made to recall a file that is not migrated.

System action

Processing continues with the next file or directory.

Storage Administrator Response

None.

Suggested Action

None.

FSM3188E	File <i>fn ft dirid</i> is empty and cannot be migrated
-----------------	--

Explanation

This message appears in the MIGRATE report when an attempt is made to migrate an empty file.

System action

Processing of this request stops.

Storage Administrator Response

None.

Suggested Action

None.

FSM3189E **File *fn ft dirid* not base file or alias,
cannot be processed**

Explanation

This message appears in the MIGRATE or RECALL report when an attempt is made to migrate or recall an external object, or revoked or erased alias. Only base and alias files can be migrated or recalled.

System action

Processing of this request stops.

Storage Administrator Response

None.

Suggested Action

None.

FSM3190I **DFSMS DELETE ML2BACKUP
processing started for storage
group *storage group* in file pool
file pool for entries with dates
previous to *date***

Explanation

This message is written at the beginning of each DELETE ML2BACKUP command to identify this as a DELETE ML2BACKUP report.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3191I **File *fn ft dirid* assigned no
management class**

Explanation

This message indicates that a file has not been assigned a management class. This action causes no impact to the end user; however, DFSMS requires a management class in order to manage the file. Assigning no management class may have been caused by one of the following conditions:

- DFSMS has encountered an internal error while determining the management class for the file during creation, or during recall.
- DFSMS has been operational but there is no active configuration.
- An attempt has been made to assign a management class that is not in the active configuration.
- The installation module exit encountered errors during DFSMS ACS processing.
- The installation REXX exit has abended during DFSMS ACS processing.

System action

Processing of the user's request continues.

Storage Administrator Response

Check the DFSMS logs for further information on the error. To assign a management class to the file, run DFSMS MANAGE, DFSMS MIGRATE or DFSMS CONVERT against the storage group, or use the ALTER line operator. For additional details, see [z/VM: DFSMS/VM Storage Administration](#).

Suggested Action

None.

FSM3192E **Error creating directory *dirid***

Explanation

Only a top directory has been specified or DFSMS/VM has called CSL routine DMSCRDIR to create directory *dirid*, but an error has occurred. If a DMSCRDIR error has occurred, the return code and reason codes returned from the CSL routine are given in message FSM0513.

System action

Directory creation is a critical DFSMS/VM function. DFSMS/VM stops if this error occurs during initialization processing.

Storage Administrator Response

Consult *z/VM: CMS Callable Services Reference* and attempt to resolve the condition that has caused the error.

Suggested Action

None.

FSM3193I **Directory *dirid***

Explanation

This message is a header for the file space report. It identifies the directory of the files.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3194E **File *fn ft dirid* with migration token *delete token* is migrated and cannot be deleted**

Explanation

The specified file has not been deleted from secondary storage. A migration token has been provided, but the file that matches that migration token is migrated. When a file is migrated, you cannot delete the migrated data. The DELETE command is used only to resolve out-of-synch conditions.

System action

None.

Storage Administrator Response

None.

Suggested Action

Verify the migration token that has been entered is valid and resubmit the request if necessary.

FSM3195E **Directory *dirid* is under directory control and cannot be processed**

Explanation

A request has been received to process files in a directory under directory control. Files cannot be migrated or recalled if they reside in a directory under directory control.

System action

The request is terminated.

Storage Administrator Response

None.

Suggested Action

None.

FSM3196E **Directory *dirid* not found or you are not authorized**

Explanation

This message appears in the ALTER, MIGRATE, and RECALL reports when the command issuer does not have the authority to alter, recall, or migrate a file from the specified directory. It also appears if the directory does not exist.

System action

Processing of the request ends and the report is sent to the command issuer.

Storage Administrator Response

None.

Suggested Action

None.

FSM3197E **File *fn ft dirid* already migrated**

Explanation

This message appears in the MIGRATE report when an attempt is made to explicitly migrate a file that has already been migrated.

System action

Processing ends.

Storage Administrator Response

None.

Suggested Action

None.

FSM3198E Invalid file *fn ft* found in ML1

Explanation

This message appears in the REPORT STORGROUP report when an invalid file is found in migration level 1. Creation of files in migration level 1 should only be done by DFSMS/VM or by a restore product that properly uses DFSMS/VM interfaces.

If you have allowed users to create files in migration level 1, this access should be removed and files that have been created by those users should be deleted. If this file has been created as a result of your restore process, this error indicates that a file has not been properly restored. Verify that your restore process is working properly and is using the proper DFSMS/VM interfaces.

System action

Processing continues.

Storage Administrator Response

Determine the cause of the invalid files in migration level 1. Delete the invalid files and secure migration level 1 as necessary.

Suggested Action

None.

FSM3199E Storage group specified is not defined in the file pool

Explanation

The storage group specified in the CONVERT or MANAGE command is not one that is defined in the specified file pool.

System action

Processing of this command ends. The next command is processed.

Storage Administrator Response

Enter a valid storage group number and resubmit the command.

Suggested Action

None.

FSM3200I DFSMS server *server userid* has *number of tasks* tasks available for work and *number of tasks* tasks busy

Explanation

This message is displayed on the user's console, is issued once for each DFSMS server that is active, and indicates the number of tasks on that server that are currently processing DFSMS requests and the number of tasks on that server that are inactive. The number of tasks available for work should equal the number of tasks that the installation has defined in the DFSMS control file for that server. If it is less, some tasks may have abended.

System action

None.

Storage Administrator Response

If some tasks have abended, consult the DFSMS logs or console files to determine the causes. If a significant number of the tasks have abended, stop DFSMS (by issuing DFSMS STOP command) and restart DFSMS.

Suggested Action

None.

FSM3201E No DFSMS servers running

Explanation

This message is displayed on the user's console during DFSMS QUERY STATUS processing when the DFSMS master machine determines that there are no DFSMS servers available to accept work.

System action

None.

Storage Administrator Response

Investigate why no DFSMS servers are available and log them on as necessary. Examine the DFSMS control file to determine if there are DFSMS servers identified in the DFSMS_SERVER_VM records. Note that if any change is made to the control file, DFSMS must be stopped (by issuing DFSMS STOP command) and restarted to use those changes. Also, the minidisk servers could have been defined but not operational since no work has been issued to the servers.

Suggested Action

None.

FSM3202E **Send or receive of work from DFSMS master to server DFSMS server userid has failed**

Explanation

An attempt has been made to either send work to a DFSMS server or receive work back from a DFSMS server and APPC/VM communications have failed. This message appears in the log and indicates the user ID of the server that encountered the problem. If the command that failed has a report file associated with it, this message also appears in the report file. However, the specific server that encountered the problem will not be listed in the message that is displayed in the report file.

System action

If an attempt has been made to send the request to a server, the request fails and a response is sent back to the user indicating that an error has occurred. If an attempt has been made to receive the completed work from the server, the user gets an indication that an error has occurred, but all of the messages that the user normally receives in a report file may not be there. The log file can be checked for messages pertinent to the command that the send or receive failed on.

Storage Administrator Response

Verify that the DFSMS servers are operational. If they are not operational, autolog the servers.

Suggested Action

Check to see if the command has actually completed and resubmit it, if necessary.

FSM3203I **Virtual machine name is running**

Explanation

This message indicates that the virtual machine *virtual machine name* is running and is able to accept requests.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3204E **File pool file pool not available**

Explanation

A file pool is not operational. This can be either the migration level 1 file pool specified in the DFSMS control file, the user's file pool, or the VMSYS file pool.

System action

The processing for this request is failed.

Storage Administrator Response

Verify that the named file pool is operational. If it is operational, and the command issued is DFSMS REPORT SPACEMANAGEMENT FILESPACE or DFSMS REPORT SPACEMANAGEMENT STORGROUP, then ensure that the migration level 1 file pool specified in the DFSMS control file is correct. Autolog the file pool if it is not operational.

If the command issued is DFSMS MIGRATE, then the file pool could be either the migration level 1 file pool or a user's file pool.

Suggested Action

Contact the storage administrator.

FSM3205E **DFSMS server status not determined**

Explanation

This message is displayed during DFSMS QUERY STATUS command processing if the status of the DFSMS servers cannot be determined.

System action

None.

Storage Administrator Response

Check the logs to determine what errors are occurring that prevent the status of the servers from being obtained. Correct the problem and rerun the DFSMS QUERY STATUS command to verify that the servers are operational.

Suggested Action

None.

FSM3207E **Unable to recall file from secondary to primary storage**

Explanation

This message is sent to the user on a RECALL command if an error has occurred and a file cannot be recalled.

System action

The file is not recalled, and processing proceeds to the next file.

Storage Administrator Response

Check the log messages for more information.

Suggested Action

Contact the storage administrator.

FSM3208E **Unable to process file *fn ft dirid* due to error**

Explanation

An error has occurred while trying to process the specified file. This error has occurred during MANAGE command processing.

System action

The MANAGE command continues processing the storage group.

Storage Administrator Response

See the DFSMS log and report file for further details.

Suggested Action

None.

FSM3209I **File *fn ft dirid* was migrated to migration level *migration level***

Explanation

This message appears in the log when a MIGRATE command has been completed.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3210I **File *fn ft dirid* was recalled**

Explanation

This message appears in the log when a RECALL command has been completed.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3211I ***nnnn* files matched the fileid specified**

Explanation

This message appears in the MIGRATE, RECALL, and ALTER reports. It indicates the number of files that have matched the input criteria specified in the command. If pattern-matching characters have been used (* or %), the number indicates the number of files that have matched the specified pattern before eligibility criteria can be considered. If no pattern-matching criteria have been used in the file ID, then this number will be a one (1).

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3212I ***nnnn* files were eligible for processing**

Explanation

This message appears in the ALTER, MIGRATE, and RECALL reports to indicate the total number of files eligible to be processed out of the total number of files that match the input file ID. A file is ineligible when DFSMS finds one of the following to be true for the file:

- File does not exist
- User requesting the ALTER, MIGRATE, or RECALL is not properly authorized to a file (for MIGRATE, write authority to the file is required; for ALTER or RECALL, read authority is required)
- Type or status of file is not base or alias (MIGRATE or RECALL)
- Base file resides in a file space whose top directory starts with DFSMS
- File is already migrated (MIGRATE only)
- File is not migrated (RECALL only)
- File contains no records (it is empty) (MIGRATE or RECALL)

Be aware that it is possible for an eligible file to fail alteration, migration, or recall due to an error in processing the request. For example, SFS may encounter an error while processing the file, or a DFSMS error may occur.

System action

None.

Storage Administrator Response

None.

Suggested Action

Error messages indicating why the request has failed may be found in the report file. The message that follows this message in the report file indicates the total number of files that have been successfully migrated or recalled.

FSM3213I DFSMS will not restart the request. Please resubmit

Explanation

DFSMS has been stopped as a result of a DFSMS STOP command. This request has been discarded and will not be restarted once DFSMS restarts.

System action

None.

Storage Administrator Response

None.

Suggested Action

Resubmit the request.

FSM3214I DFSMS will restart the request

Explanation

DFSMS has been stopped as a result of a DFSMS STOP command. This request was discarded but will be restarted once DFSMS restarts.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3215E File *fn ft dirid* could not be migrated because the migration level 1 file pool is full

Explanation

This message is logged and put in a report file that is sent to the user during a migrate if the migration level 1 file pool is full.

System action

The file is not migrated, and processing proceeds to the next file.

Storage Administrator Response

Increase the space for migration level 1 storage.

Suggested Action

Contact the storage administrator.

FSM3216W No files eligible for MIGRATE Variation 1

FSM3216W No files eligible for RECALL Variation 2

FSM3216W No files eligible for ALTER Variation 3

Explanation

An ALTER, MIGRATE, or RECALL command has been issued with a file ID containing pattern-matching characters and files have been found but all files do not meet eligibility criteria. DFSMS/VM found one or more of the following:

- File does not exist
- User requesting the command is not properly authorized to a file (for MIGRATE, write authority to the file is required; for RECALL, read authority is required)
- Type or status of file is not base or alias (MIGRATE and RECALL)
- Type or status of file is not base (ALTER)
- File resides in a file space whose top directory starts with DFSMS
- File resides in a storage group where migration level 1 is defined (MIGRATE and RECALL)
- File is already migrated (MIGRATE only)
- File is not migrated (RECALL only)
- File contains no records; it is empty (MIGRATE and RECALL)
- The management class of the file is identical to the management class submitted with the ALTER request

System action

None.

Storage Administrator Response

None.

Suggested Action

Verify specification of file ID in the command, check for proper authorization, and check status of file or files.

FSM3218W **Deadlock detected from CSL routine *CSL routine*, reason code = *reason code*. Retrying request for migration of *fn ft dirid***

Explanation

DFSMS has called CSL routine *CSL routine* to perform processing, but an SFS deadlock condition has been detected during processing, and the CSL routine failed returning reason code *reason code*.

System action

DFSMS/VM retries the request.

Storage Administrator Response

None.

Suggested Action

None.

FSM3219I **DFSMS master is waiting for access to *file pool file space* before continuing initialization**

Explanation

This message is displayed on the DFSMS master console during initialization when a file pool that the master needs to access is not yet available. The master periodically issues this message until the file pool becomes available and initialization continues or the master times out and terminates.

System action

None.

Storage Administrator Response

Start the file pool.

Suggested Action

None.

FSM3220E **File space portion of the *MIGRATION_LEVEL_1* parameter must be an enrolled user of the file pool specified on that parameter**

Explanation

This message is displayed on the DFSMS master console during initialization when a *MIGRATION_LEVEL_1* parameter has been specified with a file space that is not enrolled in the file pool specified on the *MIGRATION_LEVEL_1* parameter.

System action

Initialization of the DFSMS master fails.

Storage Administrator Response

Verify that the correct file pool and file space have been specified. If they are correct, make sure the file space is enrolled in the file pool with the appropriate amount of space. See [z/VM: DFSMS/VM Customization](#) for details.

Suggested Action

None.

FSM3221E **Storage group *group number* in file pool *file pool* cannot be managed by DFSMS**

Explanation

DFSMS cannot manage files residing in the same storage group where migration level 1 secondary storage is defined. The storage group *group number* in the file pool *file pool*, both specified in a MANAGE command, is the same as the storage group where migration level 1 secondary storage is defined. This is defined by the MIGRATION_LEVEL_1 parameter in the DFSMS control file.

System action

MANAGE request is not processed.

Storage Administrator Response

None.

Suggested Action

Make sure files to be managed by DFSMS do not exist within a file pool and storage group where secondary storage is defined.

FSM3222E **File *fn ft dirid* is in a storage group where ML1 file space is defined**

Explanation

DFSMS/VM does not migrate a file that resides in the same storage group where secondary storage is defined.

System action

File is not migrated.

Storage Administrator Response

None.

Suggested Action

Make sure files to be managed by DFSMS do not exist within a file pool and storage group where secondary storage is defined.

FSM3224E **ML2 data unavailable due to an error**

Explanation

An unexpected error has occurred while trying to access migration level 2 data during a REPORT FILESPACE or a REPORT STORGROUP command.

System action

The DFSMS REPORT STORGROUP and DFSMS REPORT FILESPACE commands fail until either the migration level 2 error is resolved or the definition for migration level 2 is removed from the DFSMS control file.

Storage Administrator Response

Check the log files for additional error messages that document the problem concerning the migration level 2 repository. Resolve the problem and resubmit the command.

Suggested Action

Contact the storage administrator.

FSM3225E **Invalid value in control file. Low threshold must be less than high threshold**

Explanation

During DFSMS control file processing, both low threshold and high threshold have been specified—either explicitly in the control file or implicitly by default values or a combination of both. The low threshold must be less than the high threshold.

System action

DFSMS/VM validates the remaining control file parameters and then stops.

Storage Administrator Response

Correct the invalid value. Refer to [z/VM: DFSMS/VM Customization](#).

Suggested Action

None.

FSM3226I **Number of Date Migration Token for**

Explanation

This message is the first header for the storage group report. It identifies the fields in the list representing migrated data for which there are no corresponding files in primary storage.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3227I	4K Blocks Migrated Level Delete Command
-----------------	--

Explanation

This message is the second header for the storage group report. It identifies the fields in the list representing migrated data for which there are no corresponding files in primary storage.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3228I	Size date migrated migration level delete token
-----------------	--

Explanation

This is a data line for the list of files migrated and not having corresponding primary storage data.

- Size—size of file in 4K blocks. This is the number of 4K blocks that would have been required if the file were not migrated.
- Migrated date—date this file has been migrated.
- Migration level—migration level file exists on. A 1 in this field indicates migration level 1. A 2 in this field indicates migration level 2.
- Delete token—delete token. This token may be used on the DELETE command to erase the migrated data since no primary storage reference exists for this token. This is done to resolve out-of-synch conditions.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3230I	Directory <i>dirid</i> assigned management class <i>management class</i>
-----------------	---

Explanation

This message indicates that a directory has had a new management class assigned to it during CONVERT processing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3231E	Directory <i>fn ft dirid</i> not converted due to error
-----------------	--

Explanation

An error has occurred and the directory has not had a new management class assigned to it during CONVERT processing. The log contains further information regarding errors that have occurred.

System action

The directory is not processed. Processing continues with the next eligible directory.

Storage Administrator Response

Check the log messages for more information.

Suggested Action

None.

FSM3232E	Directory <i>dirid</i> is currently locked by another user and cannot be processed, reason code = <i>reason code</i>
-----------------	---

Explanation

If the CONVERT command has been issued, the directory cannot be converted due to a lock.

System action

The directory is not processed. Processing continues with the next eligible directory.

Storage Administrator Response

Issue CMS QUERY LOCK to determine if the lock is an explicit one held by another user. After that user has released the lock, resubmit the command. If the lock is implicit or is held by the system, resubmitting the request at a later time, after the lock is released, removes the problem.

Suggested Action

If the user has an explicit lock on the directory in question, the user must release the lock and reissue the command. Otherwise, contact the storage administrator.

FSM3233I **Directory *dirid* assigned a NULL management class**

Explanation

This message indicates that a directory has been successfully converted from one management class to another during convert processing. The management class assigned is the NULL management class. This means that during migration and manage processing, files with the NULL management class in this directory will be managed by the system default management class.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3234I **Directory *dirid* assigned no management class**

Explanation

This message indicates that a directory has not been assigned a management class. A directory that has

not been assigned a management class causes no impact to the end user; however, DFSMS requires a management class in order to manage the files in that directory with the null management class. Assigning no management class may have been caused by one of the following conditions:

- DFSMS has encountered an internal error while determining the management class for the directory during creation.
- DFSMS has been operational but there is no active configuration.
- An attempt has been made to assign a management class that is not in the active configuration.
- The installation module exit encountered errors during DFSMS ACS processing.
- The installation REXX exit has abended during DFSMS ACS processing.

System action

Processing of the user's request continues.

Storage Administrator Response

Check the DFSMS logs for the virtual machines for further information on the error. To assign a management class to the directory:

- Issue DFSMS MANAGE or DFSMS CONVERT against the storage group
- Issue DFSMS MIGRATE against the file in the directory with no or null management class
- Issue the ALTER line operator or issue ISMF ALTER FILESPACE command

For additional details, see [z/VM: DFSMS/VM Storage Administration](#).

Suggested Action

None.

FSM3235E **Communication severed between DFSMS master and DFSMS server**

Explanation

Communication has been severed between the master and server. This generally occurs when a system administrator forces off the master or the server machine.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Log on the master or server, or both.

Suggested Action

None.

FSM3236W	Installation specified DFSMS as expiration only
-----------------	--

Explanation

The MIGRATION_LEVEL_1 parameter in DFSMS control file DGTVCNTL DATA in VMSYS:DFSMS.CONTROL has not been specified by this installation. If migrated files exist during backup or restore and the MIGRATION_LEVEL_1 parameter is not specified, then migrated files cannot be backed up or restored.

System action

If no migrated files exist, backup or restore processing of primary files continue. If migrated files do exist, backup or restore processing fails.

Storage Administrator Response

For backup and restore purposes, either the files should be recalled so the migrated version does not need to be backed up, or the DFSMS control file should be updated with the correct MIGRATION_LEVEL_1 parameter. Do not put DFSMS/VM in expiration-only mode until all migrated files have been recalled.

Suggested Action

Contact the storage administrator.

FSM3237W	Unable to reopen the report file after an SFS-detected deadlock
-----------------	--

Explanation

In attempting to write a message to the report file, a system deadlock has been detected by SFS and the request has not been processed. An attempt is then made to reopen the report file but is not successful.

System action

Processing of the request continues. Additional messages are not written to the report file but they may appear in the log file or console.

Storage Administrator Response

Investigate the cause of the system deadlock. Messages preceding this message may provide additional information.

Suggested Action

None.

FSM3238E	When control file parameter MIGRATION_LEVEL_2 is specified, parameter MIGRATION_LEVEL_1 must also be specified
-----------------	---

Explanation

In order to use MIGRATION_LEVEL_2, there must also be a MIGRATION_LEVEL_1 in the control file. Having MIGRATION_LEVEL_1 specified in the control file does not necessarily mean that there will be migration level 1 data stored, but DFSMS requires a migration level 1 file space.

System action

Processing of the control file ends.

Storage Administrator Response

Either delete MIGRATION_LEVEL_2 from the control file or specify the MIGRATION_LEVEL_1 parameter in the control file and then restart DFSMS/VM.

Suggested Action

None.

FSM3239E	FILEPOOL RESTORE of ML2 data failed for file pool = <i>file pool</i>, storage group = <i>storage group</i>
-----------------	---

Explanation

During a CMS FILEPOOL RESTORE operation of the storage group indicated in *storage group* and the file pool indicated by *file pool*, an error occurred with the ML2 server which prevented the FILEPOOL RESTORE command from completing successfully.

System action

The FILEPOOL RESTORE command stops.

Storage Administrator Response

Examine the accompanying messages on the virtual machine console that issued the FILEPOOL RESTORE command and resolve the problem. If the problem

cannot be resolved, restore the storage group from another backup tape.

Suggested Action

None.

FSM3240E	FILEPOOL BACKUP of ML2 data failed for file pool = <i>file pool</i>, storage group = <i>storage group</i>
-----------------	--

Explanation

During a CMS FILEPOOL BACKUP of the storage group indicated in *storage group* and the file pool indicated by *file pool*, an error occurred with the ML2 server which prevented the operation from completing successfully.

System action

The FILEPOOL BACKUP command completes.

Storage Administrator Response

Examine the accompanying messages on the virtual machine console that issued the FILEPOOL BACKUP request and resolve the problem. After the problem is resolved, issue the request again.

Suggested Action

None.

FSM3241E	Backup of ML2 entry failed for file pool = <i>filepool</i>, storage group = <i>storage_group</i>, object identifier = <i>X"hexnumX"</i>
-----------------	--

Explanation

While performing a backup of the ML2 entry for the file indicated by *filepool*, *storage_group*, and *X"hexnumX"*, an error has occurred that prevents the operation from completing successfully.

System action

The backup of this file fails.

Storage Administrator Response

Examine the accompanying messages on the virtual machine console that was performing the backup and resolve the problem. After the problem is resolved, issue the request again.

Suggested Action

None.

FSM3242I	<i>Number of ML2 files</i> ML2 files backed up for file pool = <i>file pool</i>, storage group = <i>storage group</i>
-----------------	--

Explanation

A CMS FILEPOOL BACKUP operation has finished backing up files stored in ML2, and this informational message is displayed to indicate the actual number of files that have been backed up.

If an error occurs during the CMS FILEPOOL BACKUP operation, *number of ML2 files* indicates the number of files stored in ML2 that were backed up before the failure occurred.

System action

The FILEPOOL BACKUP command completes.

Storage Administrator Response

If no errors have occurred during processing, verify that *number of ML2 files* is a reasonable number. This should be the number of files migrated to ML2 for the storage group that was backed up. The DFSMS REPORT command can be issued, for the storage group that was backed up, to obtain the number of files migrated to ML2.

If there is a discrepancy between these numbers, further investigation is needed.

Suggested Action

None.

FSM3243I	<i>Number of ML2 files</i> ML2 files restored for file pool = <i>file pool</i>, storage group = <i>storage group</i>
-----------------	---

Explanation

A CMS FILEPOOL RESTORE operation has completed restoring files stored in ML2, and this informational message is displayed to indicate the number of files that have been successfully restored in the storage group indicated by *storage group* and the file pool indicated by *file pool*.

If an error occurs during the FILEPOOL RESTORE operation, *number of ML2 files* indicates the actual number of files that were restored before the failure occurred.

System action

The FILEPOOL RESTORE command completes.

Storage Administrator Response

If no errors have occurred during processing, verify that *number of ML2 files* is a reasonable number. If it is not, you may wish to investigate further. For example, if there were many files migrated in a file pool that has been backed up, but during the FILEPOOL RESTORE *number of ML2 files* is a small number, check to see if some parameters in the DFSMS control file have been changed which would result in some ML2 files not being found.

If errors occur during a FILEPOOL RESTORE operation, resolve the errors and restore the storage group again.

Suggested Action

None.

FSM3244E	Problem with required directory <i>dirid</i>
-----------------	---

Explanation

A directory required by DFSMS/VM has been erased, or the DFSMS/VM machine issuing this message does not have the authority to create or replace a file in this directory.

System action

This request fails.

Storage Administrator Response

Replace directories that have been erased. Ensure that DFSMS/VM master and server machines are administrators in the VMSYS file pool.

Note: ACS exit directories are required even if no exits are used.

Suggested Action

None.

FSM3245E	No ML2 entry found for file pool = <i>filepool</i>, storage group = <i>storage_group</i>, object identifier = X"<i>hexnumX</i>"
-----------------	--

Explanation

While performing a backup of the ML2 entry for the file indicated by *filepool*, *storage_group*, and X"*hexnumX*", no ML2 entry was found on the ML2 server.

System action

The backup of this file fails.

Storage Administrator Response

Verify that the file is actually migrated. If it is, restore the file from an earlier backup version using a product which supports the restoration of ML2 data. After it has been restored, the backup operation may be attempted again.

Suggested Action

None.

FSM3250I	Migration level 2 server is <i>server</i>
-----------------	--

Explanation

The server that will process the migration level 2 files is specified.

System action

Processing continues.

Storage Administrator Response

None.

Suggested Action

None.

FSM3260E	User not authorized to discard request
-----------------	---

Explanation

This message is sent to the user if the user is not authorized to discard this request.

System action

The request is not discarded.

Storage Administrator Response

Grant the user authority for discards if applicable.

Suggested Action

Verify that the request identifier was correct. If you specified an incorrect request identifier, resubmit the request with the appropriate request identifier. If the request identifier was correct, contact the storage administrator.

FSM3261W **Request identifier *request id* not found**

Explanation

This message is issued if a user requests a discard and the request identifier specified cannot be found.

System action

Processing is discontinued.

Storage Administrator Response

None.

Suggested Action

Verify that the correct request identifier has been entered. If an incorrect request identifier has been entered, resubmit the request with the appropriate request identifier. If a correct request identifier has been specified, either the request has completed processing or the request has been previously discarded.

FSM3262E **Invalid request identifier *request id* specified**

Explanation

An invalid request identifier has been specified for discard. You may verify items eligible for discard by issuing the DFSMS QUERY REQUEST command, or DFSMSRM QUERY REQUEST for removable media services.

System action

Processing is discontinued.

Storage Administrator Response

None.

Suggested Action

Verify that the request identifier that you entered was valid via the DFSMS QUERY REQUEST or DFSMSRM QUERY REQUEST command. Resubmit the request with a valid request identifier.

FSM3263W **Discard request already in progress**

Explanation

This message is sent to the user when the user tries to discard a request that is already in the process of being discarded.

System action

This discard request is ignored.

Storage Administrator Response

None.

Suggested Action

None.

FSM3264E **Management class *management class name* not defined in the active configuration**

Explanation

This message appears in the report file when a request has been made to change the management class of a file or directory not defined in the active configuration.

System action

The management class is not changed and the ALTER request is discontinued.

Storage Administrator Response

Verify that the management class is correct. If an incorrect management class has been specified, resubmit the request with the appropriate management class name. If the management class is correct, resubmit the ALTER command with the optional FORCE parameter. Because the management class is not in the active configuration, the file is not managed by the system until the source configuration that contains the new management class is activated.

Suggested Action

None.

FSM3265I **Request identifier *request id* was discarded successfully**

FSM3265I **Request identifier *request id* has been scheduled for discard**

Explanation

This message indicates that the discard of the request has completed successfully or the scheduling for the discard has completed successfully. Scheduling occurs

when discarding either a CONVERT or a MANAGE request. Because these commands can be discarded after being dispatched for processing, the actual discard may not occur if the request completes before the discard status is recognized by DFSMS/VM.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3266I	Directory assigned management class <i>new management class</i>, old management class was <i>old management class</i>
-----------------	--

Explanation

This message appears in a report file and indicates a request to alter a directory's management class has completed successfully.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3267I	<i>Fn ft newmc</i>
-----------------	---------------------------

Explanation

This message is received after the request to alter a file's management class completes successfully.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3268I	REQUEST ISSUED BY TIME STATUS OF REQUEST COMMAND TEXT
-----------------	--

Explanation

This message is a result of a QUERY REQUESTS command and appears on the user's virtual machine console.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3269I	<i>Request issued by time status command</i>
-----------------	---

Explanation

This is a summary message for a QUERY REQUESTS command that provides information on requests that are found in the system.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3270I	<i>Request issued by time processed of created status command</i>
-----------------	--

Explanation

This is a summary message for a QUERY REQUESTS command that provides information on the requests that are found in the system.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3271W *Command request id not found*

Explanation

The user has tried to query a request ID that has completed processing, or the user has tried to query a specific request without the proper authority, or the specified request ID does not exist.

System action

Command processing stops.

Storage Administrator Response

Grant authority if appropriate.

Suggested Action

Contact the storage administrator to obtain authority.

FSM3273W **Unable to discard request
identifier *request id*, request
already in process**

Explanation

The user has tried to discard a request that is already in process and it cannot be interrupted.

System action

The discard request is ignored.

Storage Administrator Response

None.

Suggested Action

None.

FSM3274I ***Command operand1 operand2
operand3 operand4 operand5***

Explanation

This is a part of the summary message for a QUERY REQUESTS command that provides information on the requests that are found in the system.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM3275E **User not authorized to query other
user's request**

Explanation

The user has tried to query another user's request without having the proper authority to do so.

System action

The request to query another user's request is not permitted.

Storage Administrator Response

Grant the user authority to query the other user's request if applicable.

Suggested Action

Contact your storage administrator for authorization to query. If this message has been received in error, try again.

FSM3276W **No request found for user *userid* or
issuer not authorized**

Explanation

Either no requests have been found in the system or the user is not authorized to query requests.

System action

Command processing stops.

Storage Administrator Response

Grant the user authority to query requests, if appropriate.

Suggested Action

Contact the storage administrator to obtain authority to query requests.

FSM3277W **No requests found or issuer not
authorized**

Explanation

The user has made a request to query all requests in the system. Either no requests have been found or the user is not authorized to query requests.

System action

Command processing stops.

Storage Administrator Response

Grant the user authority to query requests, if appropriate.

Suggested Action

Contact the storage administrator to obtain authority to query requests.

FSM3278W	Invalid QUERY or issuer not authorized
-----------------	---

Explanation

The user has attempted to query a specific request in the system. Either the request made to query is invalid because it was issued against an item that cannot be queried, or the user is not authorized to query requests.

System action

Command processing stops.

Storage Administrator Response

Grant the user authority to query requests, if appropriate.

Suggested Action

Reissue the command with a valid request ID or contact the storage administrator to obtain authority to query requests.

FSM3279E Variation 1	File <i>fn ft dirid</i> no longer exists due to the file being erased during command processing.
---------------------------------	---

FSM3279E Variation 2	Directory <i>dirid</i> no longer exists due to the directory being erased during command processing.
---------------------------------	---

Explanation

Either the file or the directory specified by the user is not found because it has been erased during command processing, or the server performing the

ALTER request is not authorized to the file pool containing the file or directory.

System action

This file or directory is not processed. Processing continues.

Storage Administrator Response

None.

Suggested Action

If you receive this message because the server is not authorized, authorize the server to the file pool containing the file or directory you want to alter.

FSM4000I	DFSMS command request identifier <i>request id (userid address)</i> succeeded
-----------------	--

Explanation

The specified DFSMS command has completed successfully.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4001E	User-specified option <i>option</i> conflicts with DFSMS control file
-----------------	--

Explanation

The specified *option* conflicts with the corresponding DFSMS control file option.

System action

The DFSMS command fails.

Storage Administrator Response

Change the DFSMS control file to accept the user-specified option, if appropriate. DFSMS must be stopped and restarted for the control file option to be used.

Suggested Action

Reissue the DFSMS command with an option that does not conflict with the DFSMS control file, or contact the storage administrator and request that the DFSMS control file be changed.

FSM4002E **User-specified option *option* missing or invalid**

Explanation

The *option* specified by the user is missing or invalid.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command with the correct option.

FSM4003E **User-specified options *option1* and *option2* conflict**

Explanation

The options specified by the user are conflicting.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command with options that do not conflict.

FSM4004E **User specified option *option1* requires user specified option *option2***

Explanation

When specifying *option1*, *option2* is required.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command including the required option.

FSM4005E **Source minidisk user *userid* invalid or does not exist**

Explanation

The specified *userid* is invalid or does not exist.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command with a valid user ID.

FSM4006E **Source minidisk user *userid* not permitted**

Explanation

DFSMS is not permitted to move the specified minidisk.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

None.

FSM4007E **Source minidisk address *address* invalid or does not exist**

Explanation

The specified minidisk address is invalid or does not exist.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command with a valid minidisk address.

FSM4008E	User option <i>option</i> specified more than once
-----------------	---

Explanation

The user has specified the option more than once.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command with the option specified only once.

FSM4009E	User option <i>option</i> cannot be specified with the GROUP keyword
-----------------	---

Explanation

The user options STARTCYL and DEVTYPE are not permitted with the GROUP keyword.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command with the correct combination of options.

FSM4010I	DFSMS command <i>option</i> completed
-----------------	--

Explanation

The specified DFSMS command has completed successfully.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4011I	DFSMS command <i>option</i> completed, but warning or error conditions have occurred
-----------------	---

Explanation

The specified DFSMS command has completed. Errors have occurred during processing. Further information regarding the error may be found in the log. If this is a command that sends a report back to the user, further information may also be found in the report.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4012I	DFSMS command <i>option</i> could not complete
-----------------	---

Explanation

The specified DFSMS command cannot be completed because errors have occurred during processing. Further information regarding the error may be found in the log. If this is a command that sends a report back to the user, further information may also be found in the report.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4013E *Minidisk is reason***Explanation**

The DFSMS command failed for the specified *reason*. Minidisk can be either the source minidisk or target minidisk.

System action

The DFSMS command fails.

Storage Administrator Response

If the *reason* is RESERVED, change MINIDISK_RESERVED_LIMIT to Y in the DFSMS control file.

Suggested Action

If the *reason* is RESERVED, select the appropriate command option or contact the storage administrator. If the *reason* is EMPTY, select the appropriate command option. If the *reason* is non-CMS, this command is not allowed.

FSM4014E **CP/CMS size in cylinders mismatch for source minidisk****Explanation**

A size mismatch has occurred for the source minidisk.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command and specify the option that permits a size mismatch.

FSM4015E **User-specified option *option* conflicts with *minidisk*****Explanation**

The status option specified by the user conflicts with the status of the minidisk. The various values reported for the minidisk status are explained in the [z/VM: DFSMS/VM Storage Administration](#).

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command with the appropriate status option.

FSM4016E **Source minidisk record count is greater than target minidisk record count****Explanation**

The source minidisk is larger than the target minidisk.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command with a target minidisk specification large enough to contain the source minidisk.

FSM4017E **Source minidisk block size does not match target minidisk block size****Explanation**

The block size of the source minidisk does not match the block size of the target minidisk.

System action

The DFSMS command fails.

Storage Administrator Response

None.

Suggested Action

Reissue the DFSMS command and do not specify the REBLOCK option.

FSM4020E **Error from *system* command *command*, return code = *return code***

Explanation

An attempt has been made to execute a *system* command *command*, but an error has occurred. System can be either CP or CMS. *Return code* is the return code from the CP/CMS command.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Consult *z/VM: CP Commands and Utilities Reference* or *z/VM: CMS Commands and Utilities Reference* for information associated with the command and attempt to resolve the condition that has caused the problem. Consult the log file for more information.

Suggested Action

Consult *z/VM: CP Commands and Utilities Reference* or *z/VM: CMS Commands and Utilities Reference* for information associated with the command and attempt to resolve the condition that has caused the problem. Consult the log file for more information, if you have access to it.

FSM4030E	Directory maintenance interface timeout
-----------------	--

Explanation

A response has not been received from the directory maintenance facility within the time specified by `DIRECTORY_TIMEOUT` in the DFSMS control file.

System action

The DFSMS command fails.

Storage Administrator Response

Increase the `DIRECTORY_TIMEOUT` value in the DFSMS control file. Stop and restart DFSMS for the option to take effect.

Suggested Action

None.

FSM4031E	Exit function, function failed
-----------------	---------------------------------------

Explanation

The installation-wide exit did not complete the requested function successfully.

System action

The DFSMS command fails.

Storage Administrator Response

Further information regarding the error may be found in the log.

Suggested Action

Contact the storage administrator.

FSM4032I	Operation
-----------------	------------------

Explanation

Operation, is the syntax of the operation being performed by the minidisk server.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4033E	Minidisk server has insufficient directory maintenance facility authorization
-----------------	--

Explanation

The minidisk server has insufficient directory maintenance facility authorization.

System action

Initialization of the minidisk server fails.

Storage Administrator Response

Give the minidisk server the required directory maintenance facility authorization.

Suggested Action

None.

FSM4034E	EXECLOAD of exec failed, return code = return code
-----------------	---

Explanation

An attempt to load the specified installation-wide exit, *exec*, has failed. *Return code* is the return code from the EXECLOAD command.

System action

Initialization of the minidisk server fails.

Storage Administrator Response

Consult *z/VM: CMS Commands and Utilities Reference* for information associated with the command and attempt to resolve the condition that has caused the problem.

Suggested Action

None.

FSM4035W	<i>Exit responded with return code return code</i>
-----------------	---

Explanation

The installation-wide exit responded with a nonzero return code, *return code*.

System action

DFSMS continues processing the command.

Storage Administrator Response

Evaluate the accuracy of the return code.

Suggested Action

Contact the storage administrator.

FSM4036E	<i>Exit caused termination of the DFSMS command</i>
-----------------	--

Explanation

The installation-wide exit gave a return code which resulted in the termination of the DFSMS command.

System action

The DFSMS command fails.

Storage Administrator Response

Further information regarding the error may be found in the log. Evaluate the accuracy of the return code.

Suggested Action

Contact the storage administrator.

FSM4037E	<i>Server server userid has incorrect CP privilege class</i>
-----------------	---

Explanation

The directory entry for the specified server does not contain all of the required CP privilege classes.

System action

Initialization of the server fails.

Storage Administrator Response

Give the server the required CP privilege classes. Refer to *z/VM: DFSMS/VM Customization* for more information.

Suggested Action

None.

FSM4080I	<i>Target minidisk on volume at cyl startcyl for number cyls</i>
-----------------	---

Explanation

The target minidisk is on *volume* beginning at cylinder *startcyl* and its size is *number* cylinders.

System action

Processing continues.

Storage Administrator Response

None.

Suggested Action

None.

FSM4087I	<i>Output User: Userid Output System: System Results Level: Level</i>
-----------------	--

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4088I *Number* minidisks were eligible for processing

Explanation

The minidisk list contained *number* entries that were eligible for processing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4089I *Number* minidisks were successfully processed by the *command* command

Explanation

The specified number of minidisks have processed successfully.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4090I The following options were specified for the *minidisk*:

Explanation

This is a header message for the minidisk options section of the report. *Minidisk* indicates to which minidisk the option applies.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4091I IPLTEXT Present: *value* Size Mismatch: *value* Reserved Minidisk: *value*

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4092I Empty Minidisk: *value* Format Source: *value* Existing Links: *value*

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4093I Link Retries: *value* Link Interval: *value*

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4094I **Group: *value* Volume: *value* Status: *value***

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4095I **Minidisk Type: *value* Creation Date: *value* Minidisk Size: *value***

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4096I **Pace Level: *value* Buffer Size: *value* Continue On Error: *value***

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4097I **Pack Option: *value* Reblock Files: *value* Reblock Size: *value***

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4098I **DevType: *value* StartCyl: *value***

Explanation

This message indicates the options the user has specified.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4099I **DFSMS *command* Request identifier *request id (userid address)* was discarded**

Explanation

This message is included in a report sent to the user. It indicates the request has been discarded while waiting to be processed. A request is discarded either

by the DISCARD command or the STOP IMMEDIATE command.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM4100E **DFSMS command Request identifier request id (userid address) failed**

Explanation

The specified DFSMS command has failed. Further information regarding the error may be found in the log.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM8005W **Named construct not found**

Explanation

A specified named construct has not been found in the active configuration.

System action

This is a warning condition. See associated log messages for further information.

Storage Administrator Response

See associated log messages for response.

Suggested Action

None.

FSM8006S **Attempt to load shared segment shared segment name failed, return code = return code**

Explanation

A SEGMENT LOAD command for the shared segment has failed.

System action

The request that needed access to the shared segment has failed.

Storage Administrator Response

Check that the shared segment has been installed properly. Also check that the storage range occupied by the shared segment is not occupied by something else. See the *Program Directory for function level 221* for instructions on shared segment installation. See *z/VM: CMS Commands and Utilities Reference* for further information on the SEGMENT LOAD command and errors loading the segment.

Suggested Action

None.

FSM8007S **Shared segment segment name does not exist**

Explanation

The shared segment used to store the active configuration does not exist.

System action

No access to the active configuration is possible, and all requests to access or modify the active configuration fail.

Storage Administrator Response

Check that the shared segment has been properly installed. See the *Program Directory for function level 221* for instructions on shared segment installation.

Suggested Action

None.

FSM8008S **No access to shared segment DFSMSSEG**

Explanation

The shared segment is created with restricted access and this virtual machine has not been granted read/write access to the segment.

System action

No access to the active configuration is possible, and all requests to access or modify the active configuration fail.

Storage Administrator Response

Check that the shared segment is properly installed. Check that the affected virtual machine has a CP directory entry that contains a NAMESAVE control statement granting access to the shared segment. See the *Program Directory for function level 221* for information on which virtual machines require access to the shared segment.

Suggested Action

None.

FSM8021E No configuration currently active

Explanation

The active configuration is null. A valid source configuration has not been activated.

System action

Active configuration data is unavailable for viewing in the ISMF Configuration Services application, and no automatic classification of storage constructs occur for files or directories.

Storage Administrator Response

Activate a valid source configuration if it is desired to apply storage constructs to files and directories.

Suggested Action

Contact the storage administrator.

FSM8027I Attempt made to reference an outdated or corrupted shared segment DFSMSSEG

Explanation

An attempt has been made to access a shared segment that no longer exists, has been replaced, or has been damaged.

System action

The processing for this request is discontinued or retried.

Storage Administrator Response

If the problem persists, stop DFSMS/VM, ensure that all the servers are stopped, and restart DFSMS/VM.

Suggested Action

None.

FSM8031I ACS REXX exit does not exist

Explanation

DFSMS has lost access to one of the following two files:

1. IGDACSMC DFSMS
VMSYS:DFSMS.ACTIVEACSEXITS
2. IGDACSMC DFSMS VMSYS:DFSMS.ACSEXITS

Possible reasons for losing accessibility: the file pool server has stopped unexpectedly, the directory does not exist, or this virtual machine is not authorized to the directory.

System action

The processing for activation, ACS processing, or initialization is not completed.

Storage Administrator Response

Identify and correct the problem.

Suggested Action

None.

FSM8032I ACS module exit does not exist

Explanation

DFSMS has lost access to one of the following two files:

1. IGDACSMC MODULE
VMSYS:DFSMS.ACTIVEACSEXITS
2. IGDACSMC MODULE VMSYS:DFSMS.ACSEXITS

Possible reasons for losing accessibility: the file pool server has stopped unexpectedly, the directory does not exist, or this virtual machine is not authorized to the directory.

System action

The processing for activation, ACS processing, or initialization will not be completed.

Storage Administrator Response

Identify and correct the problem.

Suggested Action

None.

FSM8033S	Shared segment DFSMSSEG not initialized
-----------------	--

Explanation

The shared segment is not available for DFSMS use.

System action

Initialization has failed.

Storage Administrator Response

Run FSMSEGDF, checking to see that it has completed successfully. See *z/VM: DFSMS/VM Customization* for information on running FSMSEGDF.

Suggested Action

None.

FSM8050E	ACS module exit not created with AMODE(31)
-----------------	---

Explanation

The module exit must be generated as AMODE(31).

System action

DFSMS does not activate the configuration or the ACS exits.

Storage Administrator Response

Generate the module specifying the AMODE(31) option.

Suggested Action

None.

FSM8055E	Source configuration file not found
-----------------	--

Explanation

The source configuration specified by the storage administrator is not found on the designated directory, either because it does not exist or because the DFSMS master is not authorized to use it.

System action

The source configuration cannot be activated.

Storage Administrator Response

Ensure that the source configuration resides on the directory specified in the activate and that the DFSMS master is authorized to use that source configuration.

Suggested Action

None.

FSM8056E	Source configuration file is in a file pool which cannot be accessed
-----------------	---

Explanation

The source configuration specified by the storage administrator cannot be activated because the file pool is not available. This can occur because the DFSMS master machine is not enrolled in the file pool, or because the file pool went down after the ACTIVATE command was issued.

System action

The source configuration cannot be activated.

Storage Administrator Response

Ensure that the DFSMS master is enrolled (as a user or administrator) in the file pool containing the source configuration or that the file pool has public access, and that the file pool is available.

Suggested Action

None.

FSM8057E	Invalid version of source configuration
-----------------	--

Explanation

The source configuration file specified by the storage administrator cannot be activated because it has been created at a version of DFSMS/VM that does not match the current version of DFSMS/VM.

System action

The ACTIVATE command fails and this configuration is not activated.

Storage Administrator Response

Ensure that the source configuration file has been converted to the current version of DFSMS/VM and reissue the ACTIVATE command. If the problem persists, contact the IBM Support Center for further assistance.

Suggested Action

None.

FSM8061W **Active configuration file not found**

Explanation

No active configuration file has been found, either because it does not exist or because the DFSMS master is not authorized to use it. If a configuration has never been activated, or the ACTIVE_CONFIG_FILE_ID has been changed in the control file, this situation is normal.

System action

DFSMS/VM initialization proceeds, but there is no active configuration.

Storage Administrator Response

Ensure that the DFSMS master is an SFS administrator for the VMSYS file pool and activate a valid source configuration.

Suggested Action

None.

FSM8062E **Active configuration file not found or not usable**

Explanation

The active configuration file has either not been found or it has a problem such as invalid data or an incorrect record format or logical record length.

System action

System activation has failed.

Storage Administrator Response

Ensure that a valid active configuration file exists and that its record length is 4K and its record format is fixed, or that there is no active configuration file.

Suggested Action

None.

FSM8063W **Active configuration file is not at the current version of DFSMS/VM**

Explanation

The active configuration file has been created and activated at a different version of DFSMS/VM.

System action

DFSMS/VM initialization proceeds, but there is no active configuration.

Storage Administrator Response

Activate a configuration that has been created on the current version of DFSMS/VM, or has been created using the CONVERSION routine supplied to convert configurations from previous versions of the product.

Suggested Action

None.

FSM8070I **File *fn ft dirid* activated**
Variation 1

Explanation

DFSMS has been called to ACTIVATE a configuration. Activation has been successfully completed.

System action

Processing of this command is complete.

Storage Administrator Response

None.

Suggested Action

None.

FSM8071I **ACS module exit activated**
Variation 2 **ACS REXX exit activated**

Explanation

The ACS exit (module or REXX) specified in the message text has been found in the directory VMSYS:DFSMS.ACSEXITS and has been loaded successfully.

System action

Processing continues. The configuration activation must successfully complete for the specified ACS exit to be activated.

Storage Administrator Response

None.

Suggested Action

None.

FSM8072I	ACS module exit not activated
Variation 2	ACS REXX exit not activated

Explanation

The ACS exit (module or REXX) specified in the message text has not been found in the directory VMSYS:DFSMS.ACSEXITS. This is a normal condition and does not represent an error unless you intended to activate the ACS exit.

System action

Processing of this command continues.

Storage Administrator Response

None.

Suggested Action

None.

FSM8073E	Module exit load failure
Variation 2	REXX exit load failure

Explanation

The ACS exit (module or REXX) specified in the message text cannot be loaded successfully. Possible reasons for the exit load failure could be a problem with the exit or an internal error.

System action

Configuration activation failed due to exit load failure. Processing of this command stops.

Storage Administrator Response

Correct the problem in the exit that failed or remove it from the source directory and activate the configuration again. Check the DFSMS log messages for further information.

Suggested Action

None.

FSM8074E	Configuration file not found or you are not authorized
-----------------	---

Explanation

You have specified a configuration file name that does not exist, or the configuration file exists but you are not authorized to use it. You may have entered the name of a configuration file that is in a file pool which is unavailable.

System action

Processing of this command stops.

Storage Administrator Response

Specify a configuration file name that exists and for which you have proper authorization, or define a configuration file with the desired name. If you specified a file pool, verify that the file pool is available. It may be helpful to check the DFSMS log messages for further information.

Suggested Action

None.

FSM8075E	Unauthorized to open configuration file
-----------------	--

Explanation

If the file is in a file control directory, you should have READ/WRITE authority to open the file. If the file is in a dircontrol directory, you should have DIRWRITE authority to open the file.

System action

Processing of this command stops.

Storage Administrator Response

Obtain the proper authorization.

Suggested Action

None.

FSM8076E **Not a configuration file**

Explanation

The function that you requested is only valid for configuration files.

System action

Processing of this command stops.

Storage Administrator Response

Enter a source configuration file name. It must be 3 to 17 characters including the blank character to separate the file name and file type. Ensure that the source configuration file record length is 4K and its record format is fixed.

Suggested Action

None.

FSM8077E **Error occurred opening source configuration file**

Explanation

Due to an error, the source configuration file cannot be opened successfully.

System action

Processing of this command stops.

Storage Administrator Response

Correct the problem in the source configuration file and retry the DFSMS ACTIVATE command.

Suggested Action

None.

FSM8078E **Error occurred reading source configuration file**

Explanation

An error occurred while reading the source configuration file and it cannot be read successfully.

System action

Processing of this command stops.

Storage Administrator Response

Correct the problem in the source configuration file and retry the DFSMS ACTIVATE command.

Suggested Action

None.

FSM8079E **Damaged source configuration file**

Explanation

The source configuration file contains some invalid records and cannot be used.

System action

Processing of this command stops.

Storage Administrator Response

Enter a source configuration file that is not damaged.

Suggested Action

None.

FSM8080E **Source configuration file in use**

Explanation

DFSMS/VM has been called to access the file. DFSMS/VM indicates that the file is in use.

System action

Processing of this command stops.

Storage Administrator Response

Try the requested function again later.

Suggested Action

None.

FSM8081E **Invalid source configuration file**

Explanation

The source configuration file specified on the DFSMS ACTIVATE command is not a valid configuration file. You can only DFSMS ACTIVATE a configuration file that is valid.

System action

Processing of this command stops.

Storage Administrator Response

Make sure the configuration file is valid by using the VALIDATE option through the ISMF Configuration Application and retry the DFSMS ACTIVATE command once the file is valid.

Suggested Action

None.

FSM8082E **Unauthorized to DFSMS ACTIVATE a source configuration**

Explanation

You have attempted to activate a source configuration, but your user ID is not authorized to perform activations.

System action

Processing of this command stops.

Storage Administrator Response

Obtain the proper authorization and try to activate the configuration again.

Suggested Action

Contact the storage administrator.

FSM8083E **DFSMS communication error**

Explanation

DFSMS/VM has been invoked to perform configuration activation. It has returned with a communication error.

System action

Processing of this command stops.

Storage Administrator Response

DFSMS/VM may not be operational at this time. Retry this function later. Check the log messages for further information. If the error persists, contact the IBM Support Center for assistance.

Suggested Action

None.

FSM8084E **DFSMS master is down**

Explanation

DFSMS/VM has been called to perform configuration activation. The DFSMS master machine is unavailable.

System action

Processing of this command stops.

Storage Administrator Response

The DFSMS master machine is unavailable at this time. Retry this function. Check the logs for further information. If the error persists, contact the IBM Support Center for assistance.

Suggested Action

None.

FSM8085E **Directory not found**

Explanation

A directory required by DFSMS has been erased, or the DFSMS virtual machine issuing this message does not have the authority to create or replace a file in this directory. The processing for this request has failed. Check the DFSMS log messages for further information.

System action

Processing of this command ends.

Storage Administrator Response

Replace the directories that have been erased and ensure that the DFSMS master and server machines are administrators in the VMSYS file pool. The ACS exit directories are required even if no exits are used.

Suggested Action

None.

FSM8086E **File pool not available**

Explanation

A file pool required by DFSMS/VM is not operational. This can either be the migration file pool specified in the control file DGTVCNTL DATA, the user's file pool, or the VMSYS file pool. The processing for this request has failed. Check DFSMS log messages for further information.

System action

Processing of this command ends.

Storage Administrator Response

Ensure that the specified file pool is operational.

Suggested Action

None.

FSM8090I	Configuration conversion complete
Variation 1	

Explanation

The Configuration Conversion Utility has been invoked to create an equivalent FL221 source configuration file using the values from an existing FL220 source configuration file. Configuration conversion has successfully completed.

System action

Processing of this command is complete.

Storage Administrator Response

None.

Suggested Action

None.

FSM8090E	Configuration conversion
Variation 2	command syntax error

Explanation

The Configuration Conversion Utility has been called with invalid syntax. The correct format for invocation is:

```
FSMCSCFG infn inft infm outfn outft outfm sec_nonu defer
```

Operands:

INFN INFT INFM are required parameters specifying the file name, file type, and file mode of an existing FL220 source configuration to be converted to FL221. INFN and INFT must be 1-8 characters in length, and contain only valid SFS file-naming characters. INFM must be a single alphabetic character representing an accessed SFS directory.

OUTFN OUTFT OUTFM are required parameters specifying the file name, file type, and file mode of a nonexistent SFS file to contain the converted FL221 source configuration. OUTFN and OUTFT must

be 1-8 characters in length, and contain only valid SFS file naming characters. OUTFM must be a single alphabetic character representing an SFS directory accessed in READ/WRITE mode.

SEC_NONU is a required parameter specifying a value for the FL221 SECONDARY STORAGE NON-USAGE attribute for all management classes specifying MANAGE processing contained within the configuration. Valid values are 0-9999 or NOLIMIT.

DEFER is an optional parameter which specifies a DEFER value for the FL221 INVOKE ACS FOR FILE CREATION base configuration attribute. If present, this must be specified by the word DEFER.

System action

Processing of this command stops.

Storage Administrator Response

Invoke FSMCSCFG using valid parameters. Consult the *z/VM: DFSMS/VM Customization* for complete documentation of the Configuration Conversion Utility.

Suggested Action

None.

FSM8090E	FL221 configuration file already
Variation 3	exists

Explanation

The fully qualified file name you have specified as a target for the converted FL221 source configuration file already exists.

System action

Processing of this command stops.

Storage Administrator Response

Invoke FSMCSCFG specifying the name of a nonexistent SFS file to contain the converted FL221 source configuration.

Suggested Action

None.

FSM8090E	FL221 directory not found,
Variation 4	insufficient authority, or access
	error

Explanation

The output file mode you have specified representing the target directory for the converted FL221 source configuration file cannot be found, or you do not have sufficient authority to it, or you do not have it correctly accessed. This error can occur if you have specified a file mode representing a minidisk. You must specify an output file mode which represents an SFS directory accessed in READ/WRITE mode.

System action

Processing of this command stops.

Storage Administrator Response

Invoke FSMCSCFG specifying an output file mode which represents an SFS directory you have accessed in READ/WRITE mode.

Suggested Action

None.

FSM8090E Variation 5	FL220 directory access error
---------------------------------------	-------------------------------------

Explanation

The input file mode you have specified representing the directory containing the FL220 source configuration file has not been correctly accessed. This error can occur if you have specified a file mode representing a minidisk. The file must reside in an accessed SFS directory. If the file is in a file control directory, you may access it in R/O mode. If the file is in a directory control directory, you must access it in DIRWRITE mode.

System action

Processing of this command stops.

Storage Administrator Response

Ensure that the input file mode you have specified represents a correctly accessed SFS directory and invoke FSMCSCFG again.

Suggested Action

None.

FSM8090E Variation 6	Invalid version of source configuration
---------------------------------------	--

Explanation

The input source configuration you have specified to be converted to DFSMS/VM version FL221 has not been created on DFSMS/VM FL220.

System action

Processing of this command stops.

Storage Administrator Response

Invoke FSMCSCFG specifying an input source configuration that has been created on DFSMS/VM version FL220.

Suggested Action

None.

FSM8090E Variation 7	Error writing FL221 source configuration
---------------------------------------	---

Explanation

The Configuration Conversion Utility has been invoked to perform configuration conversion, however, an error has occurred while writing the FL221 source configuration file. This condition can occur with no storage blocks allocated to your file space, or attempting to exceed the maximum number of 4 KB file space blocks allowed, or exceeding the storage group limit.

System action

Processing of this command stops.

Storage Administrator Response

Correct the storage error and invoke FSMCSCFG again.

Suggested Action

None.

FSM8100E	The segment resides outside the range of the virtual machine
-----------------	---

Explanation

The DFSMSSEG shared segment is located at an address beyond the size of your virtual machine. In order to initialize the segment, it must be contained within the address range of your virtual machine. Since CMS resides at the upper end of your virtual machine range, the size of the virtual machine should be at least 3MB larger than the starting address of the shared segment.

System action

The shared segment has not been initialized.

Storage Administrator Response

Either increase the size of your virtual machine, or modify the FSMSEGDF EXEC to change the location of the segment.

Suggested Action

None.

FSM8101E	Error from CMS command SEGMENT RESERVE, return code = return code
-----------------	--

Explanation

The SEGMENT RESERVE command failed. The SEGMENT RESERVE command has been issued to reserve the area of virtual storage that is to be occupied by the DFSMSSEG segment.

System action

The process requiring the segment is stopped.

Storage Administrator Response

This problem can happen if CMS has allocated other data to the address range the segment occupies. Check to see what is occupying the storage that the SEGMENT RESERVE command is attempting to reserve.

Suggested Action

None.

FSM8110E	Undefined construct name set
-----------------	-------------------------------------

Explanation

A statement in an ACS routine attempts to set the &MGMTCLAS variable to a management class name not defined in the source configuration.

System action

The source configuration is flagged as invalid for activation.

Storage Administrator Response

Either define the management class in the source configuration, or remove the reference to the management class from the ACS routine.

Suggested Action

None.

FSM8111W	Warning: Undefined construct name referenced
-----------------	---

Explanation

A statement in an ACS routine compares the &MGMTCLAS variable to a management class name not defined in the source configuration.

System action

The configuration is marked as valid.

Storage Administrator Response

This is only a warning condition; so no action is required. To prevent this condition, either define the referenced management class name, or update the ACS routine to remove the invalid reference.

Suggested Action

None.

FSM8112E	Default management class name not defined
-----------------	--

Explanation

The default management class name, which is part of the base configuration information, is not defined in the management class list in the source configuration.

System action

The source configuration is flagged as invalid for activation.

Storage Administrator Response

Either provide a definition for the management class name or change the default management class in the base to a management class name that is already defined.

Suggested Action

None.

FSM8113E	Source configuration contains no base information
-----------------	--

Explanation

The source configuration contains no base information. In order to be valid, a source configuration must contain base information.

System action

The source configuration is marked as invalid for activation.

Storage Administrator Response

Enter base information on the correct ISMF panel.

Suggested Action

None.

FSM8114I	Information: Source configuration has no ACS object
-----------------	--

Explanation

The source configuration is considered valid, even though an ACS routine is not defined as part of the configuration.

System action

The configuration is marked as valid.

Storage Administrator Response

None.

Suggested Action

None.

FSM8120E	Unable to load ACS REXX exit during initialization
-----------------	---

Explanation

An attempt to load the ACS REXX exit has failed during initialization.

System action

The system fails initialization until the condition is resolved.

Storage Administrator Response

Look for messages that indicate the reason for the failure to load the ACS REXX exit from the active directory, VMSYS:DFSMS.ACTIVEACSEXITS. If the REXX exit is not loadable (for example, because

it is an empty file), erase it or replace it with a valid exit. This REXX exit exists in file IGDACSMC DFSMS VMSYS:DFSMS.ACTIVEACSEXITS.

Suggested Action

None.

FSM8121E	Unable to load ACS module exit during initialization
-----------------	---

Explanation

An attempt to load the ACS module exit has failed during initialization.

System action

The system fails initialization until the condition is resolved.

Storage Administrator Response

Check the log messages that indicate the reason for the failure to load the ACS module exit from the active directory VMSYS:DFSMS.ACTIVEACSEXITS. If the module is not loadable, erase it or replace it with a valid exit. If the module is loadable, make sure the module has been created with AMODE(31). The module exit is located in IGDACSMC MODULE VMSYS:DFSMS.ACTIVEACSEXITS.

Suggested Action

None.

FSM8122E	Unable to load ACS REXX exit during activation
-----------------	---

Explanation

An attempt to load the ACS REXX exit has failed during activation. The ACS REXX exit in file IGDACSMC DFSMS VMSYS:DFSMS.ACSEXITS cannot be loaded. Check the log file for accompanying messages that indicate the cause of failure.

System action

The system fails activation until the condition is resolved.

Storage Administrator Response

Identify the problem, correct it, and make another attempt to reactivate.

Suggested Action

None.

FSM8123E **Unable to load ACS module exit during activation**

Explanation

An attempt to load the ACS module exit has failed during activation. The ACS module exit in file IGDACSMC MODULE VMSYS:DFSMS.ACSEXITS cannot be loaded. Check the log file for accompanying messages that indicate the cause of failure.

System action

The system fails activation until the condition is resolved.

Storage Administrator Response

Identify the problem, correct it, and make another attempt to reactivate.

Suggested Action

None.

FSM9900S **Internal error occurred, return code = return code, status = status code**

Explanation

An internal DFSMS/VM error has occurred. The nature of the condition is such that DFSMS/VM cannot issue a message, and a hard-coded message is issued directly to the terminal.

System action

Depending on the issuing module, and the condition causing this message, processing may or may not continue.

Storage Administrator Response

Ensure that message repositories are available to the user; if they are available, contact the IBM Support Center and provide the message header and the entire message.

Suggested Action

Contact the storage administrator.

FSM9901S **Internal error occurred, return code = return code, reason code = reason code, status = status code**

Explanation

An internal DFSMS/VM error has occurred. The nature of the condition is such that DFSMS/VM cannot issue a message, and a hard-coded message is issued directly to the terminal.

System action

An attempt is made to reload the repository and to continue with initialization.

Storage Administrator Response

An error has been encountered while executing CMS macro DMSMSG to reference a user repository during DFSMS initialization. Documentation on this macro may be used in an attempt to determine why the repository cannot be read. If a determination cannot be made, contact the IBM Support Center and provide the entire message, including the message header.

Suggested Action

Contact the storage administrator.

FSM9902S **Error from CMS command CMS command, return code = return code**

Explanation

The failing CMS command and the return code from the command are given. The nature of the condition is such that DFSMS cannot issue a message, and a hard-coded message is issued directly to the terminal.

System action

Depending on the CMS command failing, processing may or may not continue.

Storage Administrator Response

Consult *z/VM: CMS Commands and Utilities Reference* for information associated with the command in an attempt to resolve the condition that has caused the problem. Also, verify that file LOAD MAP is not on a read/write disk and locked EXCLUSIVE. This file is used by CMS when message repositories are loaded. If unsuccessful in resolving the problem, contact the IBM Support Center and provide the message header, the failing *CMS command*, the *return code* and any preceding DMS messages.

Suggested Action

Consult *z/VM: CMS Commands and Utilities Reference* for information associated with the command in an attempt to resolve the condition that has caused the problem. Also, verify that file LOAD MAP is not on a read/write disk and locked EXCLUSIVE. If this is unsuccessful, contact the storage administrator.

FSM9903S **Language forced to *language id***

Explanation

Message repositories in the requested language cannot be loaded. Repositories in *language id* can be loaded however. The nature of the condition is such that DFSMS/VM cannot issue a message, and a hard-coded message is issued directly to the terminal.

System action

Processing continues. Messages are issued in language *language id*.

Storage Administrator Response

Using the previous FSM9902S message determine the reason that the first attempt to load repositories has failed. This message only appears if DFSMS is unable to load repositories in a specified language, and an alternate language is forced.

Suggested Action

Contact the storage administrator.

FSM9904E **Insufficient free storage available**

Explanation

An attempt has been made to obtain storage, but there is not enough free storage available in the virtual machine to satisfy the request.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Free storage by releasing minidisks that are not needed, exit from some applications that are inactive, or log on with a greater virtual machine storage size.

FSM9905E **Insufficient free storage available,
status = *status code***

Explanation

An attempt has been made to obtain storage, but there is not enough free storage available in the virtual machine to satisfy the request. *Status code* is a value used by IBM for problem determination.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

None.

Suggested Action

Free storage by releasing minidisks that are not needed, exit from applications that are inactive, or log on with a greater virtual machine storage size.

FSM9906E **Internal error from routine *routine number*,
return code = *return code*,
status = *status code***

Explanation

An internal DFSMS error has occurred. *Status code* is a value used by IBM for problem determination.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, and the *status code*.

Suggested Action

Contact the storage administrator.

FSM9907S **ABEND code NNNNNNNN in
DFSMS at PSW = *hhhhhhh*
*hhhhhhh***

Explanation

A severe error has occurred. The program status word at the time of error is given.

System action

The system will dump virtual storage.

Storage Administrator Response

Contact the IBM Support Center and provide the message header and program status word.

Suggested Action

Contact the storage administrator.

FSM9908S General Purpose Registers at time of ABEND:

Explanation

A severe error has occurred. The general purpose register contents at time of the error are given, in this format:

```
GPR 0 = hhhhhhhh  
hhhhhhh hhhhhhhh  
hhhhhhh  
GPR 4 = hhhhhhhh  
hhhhhhh hhhhhhhh  
hhhhhhh  
GPR 8 = hhhhhhhh  
hhhhhhh hhhhhhhh  
hhhhhhh  
GPR 12 = hhhhhhhh  
hhhhhhh hhhhhhhh  
hhhhhhh
```

System action

None.

Storage Administrator Response

Contact the IBM Support Center and provide the message header and register contents.

Suggested Action

Contact the storage administrator.

FSM9909S VMDUMP of virtual storage suppressed

Explanation

An abend occurred shortly after another abend occurred. Following the first abend, a CP VMDUMP was taken of the virtual machine, but the dump for this abend has been suppressed.

System action

DFSMS/VM reinitializes the virtual machine.

Storage Administrator Response

Contact the IBM Support Center.

Suggested Action

None.

FSM9910S Dump of virtual storage is in progress

Explanation

A severe error has occurred.

System action

The system has begun a virtual storage dump.

Storage Administrator Response

Contact the IBM Support Center.

Suggested Action

Contact the storage administrator.

FSM9911S Dump of virtual storage has completed

Explanation

A severe error has occurred.

System action

The system has completed a virtual storage dump.

Storage Administrator Response

Contact the IBM Support Center and provide the dump of virtual storage.

Suggested Action

Contact the storage administrator.

FSM9912S **Dump of virtual storage failed,
VMDUMP return code = *return code***

Explanation

A severe error has occurred.

System action

In the process of taking a virtual storage dump an error occurred. The storage dump is incomplete.

Storage Administrator Response

Contact the IBM Support Center and provide the message header and the *return code*.

Suggested Action

Contact the storage administrator.

FSM9913E **Internal errors have caused
DFSMS initialization to stop**

Explanation

Internal errors have been encountered that prevent DFSMS from initializing. The errors have been logged.

System action

DFSMS stops.

Storage Administrator Response

See the console for error messages and correct the errors.

Suggested Action

None.

FSM9914S **Internal error from routine *routine number*,
return code = *return code*,
status = *status code***

Explanation

An internal DFSMS error has occurred. The nature of the condition is such that DFSMS cannot issue a message, and a hard-coded message is issued directly to the terminal.

System action

Depending on the issuing module, and the condition causing this message, processing may or may not continue.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, and the *status code*.

Suggested Action

Contact the storage administrator.

FSM9915S **DFSMS is stopping**

Explanation

This message is generated when a condition has occurred that causes DFSMS to stop.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

FSM9916S **DFSMS is stopping due to
insufficient free storage**

Explanation

An attempt has been made to obtain storage, but there is not enough free storage available in the virtual machine to satisfy the request.

System action

DFSMS will stop and attempt to reinitialize itself.

Storage Administrator Response

None.

Suggested Action

None.

Chapter 4. DFSMS/VM IGD Messages

IGD0502E **Insufficient free storage available**

Explanation

An attempt has been made to obtain storage, but there is not enough free storage available in the virtual machine to satisfy the request.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Assign a greater virtual machine storage size to the DFSMS machine that is experiencing insufficient storage problems.

Suggested Action

None.

IGD0505E **Internal error from routine *routine number*, return code = *return code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, and the *return code*.

Suggested Action

None.

IGD0506E **Internal error from routine *routine number*, return code = *return code*, status = *status code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, and the *status code*.

Suggested Action

None.

IGD0507E **Internal error from routine *routine number*, return code = *return code*, reason code = *reason code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, and the *reason code*.

Suggested Action

None.

IGD0508E **Internal error from routine *routine number*, return code = *return code*, reason code = *reason code*, status = *status code***

Explanation

An internal DFSMS error has occurred.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *routine number*, the *return code*, the *reason code*, and the *status code*.

Suggested Action

None.

IGD0509E **Internal error, return code = *return code***

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header and the *return code*.

Suggested Action

Contact the storage administrator.

IGD0510E **Internal error, return code = *return code*, reason code = *reason code***

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *return code*, and *reason code*.

Suggested Action

Contact the storage administrator.

IGD0511E **Internal error, return code = *return code*, reason code = *reason code*, status = *status***

Explanation

An internal DFSMS error has occurred.

System action

The system makes no further attempt to process the command.

Storage Administrator Response

Contact the IBM Support Center and provide the message header, the *return code*, *reason code*, and the *status*.

Suggested Action

Contact the storage administrator.

IGD0513E **Error from CSL routine *CSL routine*, return code = *return code*, reason code = *reason code***

Explanation

The CSL routine was called and has encountered an error.

System action

The system fails the current action that it is attempting. If this action is a critical DFSMS function, DFSMS terminates; however, if this is not a critical DFSMS function, DFSMS attempts to continue processing other requests.

Storage Administrator Response

Consult *z/VM: CMS Callable Services Reference* for the CSL routine and attempt to resolve the condition that has caused the error.

Suggested Action

None.

IGD1001W **ACS processing rejected by the ACS routine, reason = *reason code***

Explanation

The automatic class selection routine has rejected this request. Reason is the ACS exit code.

System action

Automatic class selection is rejected for this file or directory. A new management class is not assigned to this file or directory.

Storage Administrator Response

None. The rejection of automatic class selection was requested by installation-written code.

Suggested Action

None.

IGD1002S	Abend occurred in ACS REXX exit at address <i>address</i>, abend code = <i>abend code</i>
-----------------	--

Explanation

An abend has occurred in the installation-written REXX exit or a program invoked by the REXX exit.

System action

A management class is not assigned to this file or directory.

Storage Administrator Response

Modify the ACS REXX routine.

Suggested Action

None.

IGD1006I	<i>Message from the ACS module exit</i>
-----------------	--

Explanation

This is a message from the ACS module exit.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD1009I	<i>Message from the ACS routine</i>
-----------------	--

Explanation

This is a message from the ACS routine.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD1011E	ACS processing failed due to invalid management class <i>management class</i> assigned by the ACS routine
-----------------	--

Explanation

The ACS routine has assigned a management class that is not valid in the active configuration.

System action

Automatic class selection is failed for this file or directory. A management class is not assigned to this file or directory.

Storage Administrator Response

Modify the ACS routine or activate a configuration containing the management class.

Suggested Action

None.

IGD1017E	ACS processing failed for file <i>fn ft dirid</i>
-----------------	--

Explanation

An error has occurred that has caused automatic class selection to fail for this file.

System action

A management class is not assigned to this file.

Storage Administrator Response

See associated message for further information on the error condition.

Suggested Action

None.

IGD1018E **ACS processing failed for directory**
dirid

Explanation

An error has occurred that has caused automatic class selection to fail for this directory.

System action

A new management class is not assigned to this directory.

Storage Administrator Response

See associated message for further information on the error condition.

Suggested Action

None.

IGD1021E **Invocation of the ACS REXX exit**
produced negative return code =
return code

Explanation

Invocation of the installation-written REXX exit has returned a negative value. The assumption is made that the system has generated a negative value during invocation of the REXX exit because the REXX exit should not have been written to issue negative return codes.

System action

Automatic class selection is failed for this file or directory. A management class is not assigned to this file or directory.

Storage Administrator Response

Ensure that the REXX routine is returning only nonnegative integers. Check the console for any system messages with explanations for the negative value.

Suggested Action

None.

IGD1022E **Invalid parameter list encountered**
during ACS processing, reason
code = reason code

Explanation

Automatic class selection has detected an error when the ACS routine was invoked from the installation-written module exit. The *reason code* identifies the error:

Reason Code Description

2012

An invalid value has been found in the ACERODSG (file organization) field of ACERO. This value must be null.

2013

An invalid value has been found in the ACERORCG (file record organization) field of ACERO. This value must be null.

2014

An invalid value has been found in the ACERODST (file type) field of ACERO. This value must be null.

2015

An invalid value has been found in the ACEROXMD (execution mode) field of ACERO. This value must be null.

2020

An invalid value has been found in the ACERODNT (file name type) field of ACERO. This value must be null.

2102

An invalid value has been found in the ACEROSIZ (size) field of ACERO. This value must be zero for ACS processing of a directory.

2103

An invalid combination of values has been found in the ACERODIR (directory), ACEROFN (file name), and ACEROFT (file type) fields of ACERO. One of the following conditions has occurred:

- ACERODIR field is null or blank, and at least one of the ACEROFN and ACEROFT fields is null or blank.
- ACERODIR field is *not* null or blank, and at least one of the ACEROFN and ACEROFT fields is *not* null or blank.

2104

An invalid value has been found in the ACEROFPI (file pool ID) field of ACERO. This value must not be null or blank.

2106

An invalid value has been found in the ACEROMC (input management class) field of ACERO. The ACEROMCL (input management class length) field must be greater than or equal to 0, and less than or equal to 8.

2107

An invalid value has been found in the ACEROMC (input management class) field of ACERO. The ACEROMCV (input management class name) field must not be blank or null when the ACEROMCL (management class length) field is nonzero.

2108

An invalid value has been found in the ACEROONR (owner) field of ACERO. This value must not be null or blank.

2109

An invalid value has been found in the ACEROPTH (path name) field of ACERO. One of the following conditions has occurred:

- Two directory level separators are adjacent (for example, A..B.C).
- The path name begins with one or more directory level separators (for example, .A.B.C).
- The path name ends with one or more directory level separators (for example, A.B.C..).

Valid values are:

- null or blank
- userid[.d1[.d2...[.d8]]]

2110

An invalid combination of values has been found in the ACEROPTH (path name), ACERODIR (directory), and ACEROONR (owner ID) fields of ACERO. If the ACEROPTH field is null or blank (that is, the top directory is being processed), the value in ACEROONR field must be equal to the value in the ACERODIR field.

2111

An invalid combination of values has been found in the ACEROPTH (path name) and the ACEROONR (owner) fields of ACERO. The first directory of the directory path name (that is, the top directory) must be equal to the owner name.

2112

An invalid combination of values has been found in the ACEROPTH, (path name) and the ACEROPMC (parent management class) fields of ACERO. The ACEROPMC field must be null when ACEROPTH field is null or blank (that is, when the top directory is processed).

2113

An invalid value has been found in the ACEROPTH (path name) field of ACERO. The top directory or a subdirectory of the path name contains more characters than the maximum allowable. The maximum number of characters in the top directory is 8, and in a subdirectory is 16.

2114

An invalid value has been found in the ACEROPTH (path name) field of ACERO. The path name contains more than the maximum number of directory levels allowed when a file or a directory is processed. The maximum number of directory levels in the path name is 9 for a file and 8 for a directory.

2115

An invalid value has been found in the ACEROPMC (parent management class) field of ACERO. The ACEROPML (parent management class length) field must be greater than or equal to 0, and less than or equal to 8.

2116

An invalid value has been found in the ACEROPMC (parent management class) field of ACERO. The ACEROPMV (parent management class name) field must not be blank or null when the ACEROPML (parent management class length) field is nonzero.

2117

An invalid value has been found in the ACEROFMT (record format) field of ACERO. This value must be null or blank for ACS processing of a directory.

2118

An invalid value has been found in the ACEROFMT (record format) field of ACERO. This value must be **F** or **V** for ACS processing of a file.

2120

An invalid value has been found in the ACEROUOR (user ID) field of ACERO. This value must not be null or blank.

2150

An invalid value has been found in the ACEROJAC (ACCT_JOB) field of ACERO. This value must be null (that is, ACEROJNM must be zero).

2151

An invalid value has been found in the ACEROSAC (ACCT_STEP) field of ACERO. This value must be null (that is, ACEROSNM must be zero).

2152

An invalid value has been found in the ACEROAPP (application name) field of ACERO. This value must be null or blank.

2153

An invalid value has been found in the ACERODD (DD name) field of ACERO. This value must be null or blank.

2154

An invalid value has been found in the ACERODDC (data class name associated with the resource owner of the file) field of ACERO. This value must be null (that is, the ACERODDL [data class length] field must be zero).

2155

An invalid value has been found in the ACERODMC (management class name associated with the resource owner of the file) field of ACERO. This value must be null (that is, the ACERODML [management class length] field must be zero).

2156

An invalid value has been found in the ACERODSC (storage class name associated with the resource owner of the file) field of ACERO. This value must be null (that is, the ACERODSL [storage class length] field must be zero).

2157

An invalid value has been found in the ACERODSN (file or collection) field of ACERO. This value must be null or blank.

2158

An invalid value has been found in the ACERODSO (file owner) field of ACERO. This value must be null or blank.

2159

An invalid value has been found in the ACEROEXP (expiration date) field of ACERO. This value must be null or blank.

2160

An invalid value has been found in the ACEROGRP (group ID) field of ACERO. This value must be null or blank.

2161

An invalid value has been found in the ACEROJOB (job name) field of ACERO. This value must be null or blank.

2162

An invalid value has been found in the ACERODC (data class name - input only value) field of ACERO. This value must be null (that is, the ACERODCL [data class length] field must be zero).

2163

An invalid value has been found in the ACEROSC (storage class name - input only value) field of ACERO. This value must be null (that is, the ACEROSCL [storage class length] field must be zero).

2164

An invalid value has been found in the ACEROMSZ (maximum size) field of ACERO. This value must be zero.

2165

An invalid value has been found in the ACEROMEM (member name) field of ACERO. This value must be null or blank.

2166

An invalid value has been found in the ACEROMVG (MSS volume group name) field of ACERO. This value must be null or blank.

2167

An invalid value has been found in the ACERONVL (number of volsers) field of ACERO. This value must be zero.

2168

An invalid value has been found in the ACEROPGM (program name) field of ACERO. This value must be null or blank.

2169

An invalid value has been found in the ACERORTP (retention period) field of ACERO. This value must be zero.

2170

An invalid value has been found in the ACEROUNT (unit name) field of ACERO. This value must be null or blank.

System action

Automatic class selection is failed for this file or directory.

Storage Administrator Response

Check the module routine. See reason code description for further information on the error condition.

Suggested Action

None.

IGD1024I **ACS message produced for file *fn ft dirid***

Explanation

A message has been produced during automatic class selection for this file.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD1025I **ACS message produced for directory *dirid***

Explanation

A message has been produced during automatic class selection for this directory.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD1031W **ACS processing rejected by the REXX exit, reason = *reason code***

Explanation

The ACS REXX exit has rejected this request. Reason is return or exit code from the REXX exit. An error running the REXX exit can also cause this.

System action

Automatic class selection is rejected for this file or directory. A management class is not assigned to this file or directory.

Storage Administrator Response

None, if this was requested by installation-written code. If an error occurred running the REXX exit, check the console for any system messages that may explain the reason code. REXX errors can produce 200xx format reason codes; the xx error explanation can be found in the [z/VM: REXX/VM Reference](#).

Suggested Action

None.

IGD1035E **ACS processing failed due to invalid management class *management class* assigned by REXX exit**

Explanation

The installation-written REXX exit has assigned a management class that is not valid in the active configuration.

System action

Automatic class selection is failed for this file or directory. A management class is not assigned to this file or directory.

Storage Administrator Response

Modify the REXX exit or activate a configuration containing the management class.

Suggested Action

None.

IGD1036I ***Message from the ACS REXX exit***

Explanation

This is a message from the ACS REXX exit.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD1051I **ACS processing rejected by the module exit, reason = *reason code***

Explanation

The ACS module exit rejected this request. Reason is the reason code (register 0) from the module exit.

System action

Automatic class selection is rejected for this file or directory. A management class is not assigned to this file or directory.

Storage Administrator Response

None.

Suggested Action

None.

IGD1055E **ACS processing failed due to invalid management class *management class* assigned by module exit**

Explanation

The installation-written module exit has assigned a management class that is not valid in the active configuration.

System action

Automatic class selection has failed for this file or directory. A management class is not assigned to this file or directory.

Storage Administrator Response

Modify the module exit or activate a configuration containing the management class.

Suggested Action

None.

IGD1060S	Abend occurred in ACS module exit
-----------------	--

Explanation

An abend has occurred in the installation-written module exit or a program invoked by the module exit.

System action

A management class is not assigned to this file or directory.

Storage Administrator Response

Modify the ACS module exit.

Suggested Action

None.

IGD1065E	ACS processing failed due to error in module exit, return code = <i>return code</i>, reason code = <i>reason code</i>
-----------------	--

Explanation

The installation-written module exit has an error. It has returned an invalid return code or a return code indicating an error.

System action

Automatic class selection has failed for this file or directory. A management class is not assigned to this file or directory.

Storage Administrator Response

Modify the module exit. See the *z/VM: DFSMS/VM Storage Administration* for the valid return codes and their meanings.

Suggested Action

None.

IGD1070W	ACS module exit deactivated
-----------------	------------------------------------

Explanation

The module exit has been deactivated because of an error or abend in the exit. Any further ACS processing with the current active configuration will not run the module exit.

System action

The exit no longer runs.

Storage Administrator Response

Check the DFSMS log to determine what has occurred to cause deactivation and take appropriate action. An activate is required before the exit can be run again.

Suggested Action

None.

IGD1075E	Deactivation of ACS module exit failed
-----------------	---

Explanation

Deactivation of the module exit was attempted because of an error abend in the exit. The deactivation has failed and the exit is still active.

System action

The exit continues to run.

Storage Administrator Response

Check the DFSMS log to determine what has occurred to cause the deactivation request and to take appropriate action. An activate with a new exit or no exit causes processing of the old exit to stop.

Suggested Action

None.

IGD1080E	ACS processing failed due to invalid management class <i>management class</i>. Input
-----------------	---

management class is invalid and was not changed

Explanation

The input management class has not changed during ACS processing and is not valid in the active configuration.

System action

Automatic class selection has failed for this file or directory. A management class will not be assigned to this file or directory.

Storage Administrator Response

Change the management class for this file or directory. To prevent further problems use the ACS routine or ACS exits to change this management class, or activate a configuration containing this management class.

Suggested Action

None.

IGD3100I

Explanation

(Message number 3100 reserved and not used.)

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD3101I	Error in ACS translator, reason code <i>reason_code</i>, in module name <i>module_name</i> and event name <i>event_name</i>
-----------------	--

Explanation

An unexpected error has occurred in the ACS translator.

System action

Translation of the ACS routine is ended when this error occurs. If possible, a dump of the ACS translator work areas is taken.

Storage Administrator Response

Save the ACS routine, return codes, reason codes, and the ACS translator work area dump (if any). Contact the IBM Support Center.

Suggested Action

None.

IGD3102I	Error reading ACS source file. DMSREAD reason code = <i>reason_code</i>
-----------------	--

Explanation

An error has occurred reading the ACS routine source file.

System action

Translation of the ACS routine is terminated.

Storage Administrator Response

Refer to *z/VM: CMS Callable Services Reference* for a description of the reason code. Correct the error and translate the ACS routine source file again.

Suggested Action

None.

IGD3111I	Invalid reference to read/only variable <i>variable_name</i> in storgrp ACS routine.
-----------------	---

Explanation

Certain read/only variables are not allowed in a storage group selection routine.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Refer to *z/VM: DFSMS/VM Storage Administration* for a list of prohibited read/only variables. Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3112I	Right parenthesis was expected but not found
-----------------	---

Explanation

A right parenthesis has been expected but not found in an EXIT, IF, SELECT, or WHEN statement; a subscripted variable; a subscripted variable in a SET statement; or a subscripted variable in a WRITE statement.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3113I	Literal longer than 255 characters - end quotation mark may be missing
-----------------	---

Explanation

The maximum length of a literal is 255 characters.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3114I	Left parenthesis was expected but not found
-----------------	--

Explanation

A left parenthesis has been expected but not found in an EXIT, SELECT, or WHEN statement; or at the start of a FILTLIST INCLUDE or EXCLUDE list.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3115I	Literal continuation character or single quote expected but not found
-----------------	--

Explanation

A literal must be enclosed in single quotation marks.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3116I	Unexpected statement type <i>source_text</i> encountered - subsequent statements may be ignored
-----------------	--

Explanation

The translator did not recognize the statement.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3117I	Integer or integer type <i>source_text</i> is greater than the maximum 2147483647 that is allowed
-----------------	--

Explanation

The number is too large. Either the number is more than 10 numeric characters, or it is greater than 2147483647.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3118I	Missing continuation character or end of literal - blank line found instead
-----------------	--

Explanation

Each line for the literal must have a continuation character.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3119I	End of procedure before end of literal
-----------------	---

Explanation

Each literal must be ended by a single quotation. The ACS translator did not find the closing quotation before the end of the input file.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3120I	End of procedure before end of comment
-----------------	---

Explanation

Each comment must be ended by a '*/'. The ACS translator has not found the end of the comment before the end of the input file.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3121I	Megabyte value <i>value</i> is greater than the maximum 2097151 that is allowed
-----------------	--

Explanation

Numeric values having an MB suffix cannot be larger than 2097151 MB.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3130I	Missing comma or right parenthesis in FILTLIST definition statement
-----------------	--

Explanation

Items in FILTLIST INCLUDE or EXCLUDE lists must be separated by commas. The lists must be terminated by a right parenthesis.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3132I Invalid FILTLIST name

Explanation

The first character of a FILTLIST name must be a letter, a national character, a percent sign, an asterisk, or an underscore. The remaining characters can be any of the aforementioned five, a digit, or a period. If the FILTLIST name is preceded by an ampersand, it can contain only letters, digits, national characters, and underscores.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3133I FILTLIST name *filtnst_name* longer than 32 characters

Explanation

The maximum length of a FILTLIST name is 32 characters.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3134I Number of filter literals greater than 255

Explanation

The maximum number of literals allowed in a FILTLIST INCLUDE or EXCLUDE list is 255.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3135I FILTLIST or mask comparison uses invalid relational operator

Explanation

Only the relational operators EQ (=) and NE(≠) are allowed in FILTLIST and mask comparisons.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3136I Duplicate FILTLIST name *filtnst_name* defined

Explanation

The name has already been used as a FILTLIST name.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3137I	Invalid syntax for FILTLIST statement - include/exclude not specified
-----------------	--

Explanation

A FILTLIST must have either an INCLUDE list, an EXCLUDE list, or both.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3138I	Invalid specification for include or exclude list
-----------------	--

Explanation

The list must start with a left parenthesis and end with a right parenthesis. List items must be separated by commas.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3139I	Invalid subscripted read/only variable
-----------------	---

Explanation

The read/only variable cannot be subscripted.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Refer to *z/VM: DFSMS/VM Storage Administration* for a list of read/only variables that can use subscripts. Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3140I	Subscript value exceeds allowable range of max_value
-----------------	---

Explanation

Subscript value exceeds maximum allowed.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3141I	Invalid subscript
-----------------	--------------------------

Explanation

An invalid subscript has been detected. It is set to zero so that processing can continue.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3142I Invalid use of special characters in mask *source_text*

Explanation

Two or more adjacent '*' are not allowed in a mask.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3143I Invalid use of special characters in directory path mask *source_text*

Explanation

In an ACS routine, the mask value uses special characters incorrectly in one of the following ways:

- The mask contains three or more asterisks in a row,
- A qualifier in the mask uses two asterisks in a row,
- The mask contains two or more periods in a row, or
- The mask ends in a period.

System action

The error is noted in the listing and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3150I Nesting limit exceeded

Explanation

Too many operands have been encountered in an IF-THEN-ELSE or a SELECT statement. The maximum number of operands allowed is 32.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3151I Relational operator missing or invalid

Explanation

Valid relational operators are LT, LE, EQ, NE, GE and GT.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3152I Invalid comparison between operands

Explanation

Either an invalid comparison between a character and a numeric character has occurred, or an invalid comparison between literals has occurred.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3153I Invalid expression in a IF statement

Explanation

An invalid expression is located in an IF statement.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3154I Invalid expression in a WHEN statement

Explanation

The relational expression in a SELECT statement of the second form is invalid.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3155I FILTLIST *filtlist_name* referenced but not defined

Explanation

The referenced FILTLIST name has not been defined.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3156I Excessive use of Boolean operators

Explanation

The code generated for an IF statement resulted in an excessive number of Boolean operators.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Simplify the IF statement and retranslate.

Suggested Action

None.

IGD3157I Invalid operand encountered in a comparison

Explanation

The operand must either begin with an ampersand (for example a FILTLIST name) or be a R/O variable, a R/W variable, a mask, a literal, a number or a subscripted variable.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3158I Invalid comparison - length of operands conflict**Explanation**

The length of the literal in a comparison must, at most, be equal to the length allowed for the variable.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3160I Missing clause for THEN**Explanation**

The THEN clause must be either a FILTLIST, a DO statement, an EXIT statement, an IF statement, a SELECT statement, a SET statement, or a WRITE statement.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3161I Missing THEN keyword on an IF statement**Explanation**

An IF statement must have a THEN keyword.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3162I Missing clause for ELSE**Explanation**

The ELSE clause must be either a FILTLIST, a DO statement, an EXIT statement, an IF statement, a SELECT statement, a SET statement, or a WRITE statement.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3170I Missing clause for WHEN**Explanation**

For a SELECT statement of the first type, the WHEN clause must be a value. For a SELECT statement of the second type, the WHEN clause must be a valid relational expression.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3171I Missing WHEN keyword or left parenthesis for a SELECT statement

Explanation

A SELECT statement must have at least one WHEN statement. The WHEN clause must be enclosed in left and right parentheses.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3172I **Missing END keyword for a SELECT statement**

Explanation

A SELECT statement must be terminated with an END.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3174I **Missing clause for OTHERWISE**

Explanation

An OTHERWISE statement on a SELECT must have a clause.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3175I **Invalid value specified on SELECT statement**

Explanation

The value specified must be either a R/W variable, a subscripted variable, or a R/O variable.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3180I **Missing END keyword for a DO statement**

Explanation

A DO statement must be terminated with an END.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3190I **Invalid value specified for CODE on the EXIT statement**

Explanation

The CODE value must be a number.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3200I **Text of WRITE statement greater than 250 characters - end quotation mark may be missing**

Explanation

Either the text for a WRITE statement is too long or the ending quotation mark is missing.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3201I **Text of WRITE statement missing or invalid**

Explanation

The text for a WRITE statement must be a literal, a subscripted variable, a R/O variable, a R/W variable, or a combination of literals and variables.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3202I **Invalid use of subscripted read/only variable on WRITE statement**

Explanation

The subscript must be a number or another R/O variable.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3210I **PROC statement missing or invalid**

Explanation

The keyword PROC is missing or misspelled.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3211I **Read/write variable name missing or invalid on PROC statement**

Explanation

The PROC statement must have a R/W variable (with or without a leading ampersand).

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3212I **Missing END keyword for the ACS routine**

Explanation

An ACS routine must terminate with an END.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3213I **End of procedure before end of source file**

Explanation

The source file contained statements after the terminating END statement for the procedure.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3214I **Duplicate PROC statement encountered**

Explanation

More than one PROC keyword was encountered.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3215I **PROC statement must be first statement in ACS routine**

Explanation

The source file contained statements other than comments before the PROC keyword was encountered.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3220I **Invalid syntax for SET statement**

Explanation

The R/W variable name must be followed by an "=" or "EQ" operator.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3221I **Invalid setting of read/write variable in ACS routine**

Explanation

The read/write variable named is not valid for this ACS routine. It must match the read/write variable name used on the PROC statement.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3222I Invalid assignment or missing literal in SET statement

Explanation

The value assigned to the read/write variable in the SET statement must be either a valid read/only variable or a literal.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3223I Invalid list assignment

Explanation

List assignment is allowed only for the STORGRP read/write variable.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3224I Invalid read/only variable r/o_var_name on SET statement

Explanation

The read/only variable specified is not valid for this ACS routine.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3225I List of values assigned to &STORGRP greater than 15

Explanation

No more than 15 values can be assigned to a storage group.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3226I Value specified on SET exceeded allowable length

Explanation

The names for constructs assigned to the read/write variable can be from 1 to 8 characters long.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3227I **SET statement not encountered in ACS routine**

Explanation

An ACS routine must contain at least one SET statement.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3228I **Invalid setting of &STORGRP - cannot be null**

Explanation

Null setting for STORGRP read/write variable cannot be used.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3229I **Invalid use of subscripted read/only variable assigned on SET statement**

Explanation

SET value cannot be a subscripted variable.

System action

The error is noted in the listing, and translation continues.

Storage Administrator Response

Correct the statement containing the error and retranslate.

Suggested Action

None.

IGD3900I **ACS TRANSLATOR ***** TIME**
time DATE date PAGE page_number

Explanation

This informational message is used as part of the ACS routine listing title.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD3901I **SOURCE CONFIGURATION**
FN FT DIRID:
source_configuration_file_name

Explanation

This informational message is used as part of the ACS routine listing title.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD3902I **ACS SOURCE FN FT DIRID:**
ACS_source_file_name

Explanation

This informational message is used as part of the ACS routine listing title.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD3910I **SUMMARY OF ERROR MESSAGES:**

Explanation

This informational message is the ACS routine listing heading for the summary of errors detected by the ACS translator.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD3911I **TRANSLATION RETURN CODE:**
return_code

Explanation

This informational message lists the results of the ACS routine translation in the ACS routine listing.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

IGD3912I **SIZE OF OBJECT TABLE:**
size(bytes)

Explanation

This informational message lists the size (in bytes) of the ACS routine object table. This message is produced only if the ACS routine is translated successfully.

System action

None.

Storage Administrator Response

None.

Suggested Action

None.

Chapter 5. DFSMS/VM Return and Reason Codes

This chapter contains:

- ACS routine return codes
- ISMF return and reason codes
- DFSMS command processor return codes
- Library hardware error reason codes
- CP completion status values

For information on IUCV return codes, see *z/VM: CP Programming Services*. For information on RMS return codes see *z/VM: DFSMS/VM Removable Media Services*.

ACS Routine Return Codes

This section contains return codes issued by the automatic class selection routine.

The ACS routine return codes may be issued from the ACS interface routine after an ACS redrive. [Table 1](#) on [page 179](#) lists standard return codes used by the ACS routine.

Return Code	Meaning
0 (X'00')	Successful
8 (X'08')	Invalid parameter list; register 0 contains the reason code.
12 (X'0C')	The main ACS routine set a nonzero exit code via the EXIT ACS statement; register 0 contains the exit code.
16 (X'10')	ACS internal error; register 0 contains the ACS reason code.
20 (X'14')	ACS internal error; register 0 contains the ACS reason code.
24 (X'18')	ACS internal error; register 0 contains the ACS reason code.

For ACS routine reason codes, refer to [message IGD1022E](#).

ISMF Return and Reason Codes

This section documents information that is Diagnosis, Modification or Tuning Information provided by DFSMS/VM and contains return and reason codes issued by ISMF.

ISMF Return Codes

When one DFSMS/VM function calls another, the return code from the called function is placed in Register 15. [Table 2](#) on [page 179](#) lists standard return codes used by ISMF.

Note: Return codes defined in specific message explanations are those returned to ISMF by the functions it has called.

Return Code	Meaning
0 (X'00')	Successful
4 (X'04')	Function performed with minor error

<i>Table 2. ISMF Standard Return Codes (continued)</i>	
Return Code	Meaning
8 (X'08')	Function not performed; no termination
12 (X'0C')	Function not performed; terminating error
16 (X'10')	Function not performed; terminating error
20 (X'14')	Function not performed; terminating error
24 (X'18')	Incorrect syntax; terminating error

ISMF Reason Codes

Code

Description

0005

Unexpected return code (DGTFEOE1) comes from routines called by the file application component.

0006

Errors have occurred during previous processing. Check the previous log entries for detailed error information.

0009

Automatic data area is in use. An ISMF common service routine has been entered and the frozen storage for its automatic data area is already in use.

0010

Selection criteria is invalid and produces an empty list.

0011

Filter criteria is invalid and produces an empty list.

0012

Prolog failure: Storage for the invoking module's automatic data area has not been obtained.

0013

Epilog failure: Automatic data area cannot be freed from the invoking module.

0014

Panel number is invalid. A valid panel number is 1, 2, or 3.

0016

Convert utility: Target data length must be 4 bytes or less to convert a character string to its fixed binary representation.

0017

Invalid character has been found in the data to be converted. Data conversion cannot take place. In some cases, imbedded blanks are invalid.

0018

Desired DAB has not been found in the DAB list.

0019

Data to be converted contains all blanks and cannot be converted.

0044

Convert utility: Source data length for converting record format is invalid. It must be 1 byte.

0045

Convert utility: Target data length must be at least 5 bytes to hold the converted record format.

0046

Convert utility: Record format cannot be determined from the input.

0051

RETRY routine is in control.

- 0052**
No storage has been allocated. Return code = 4.
- 0058**
All storage is not freed. Return code = 4.
- 0059**
Delete request has not been issued. Return code = 4.
- 0061**
LOAD macro has failed. Control has been given to the error routine specified in the LOAD macro invocation. Return code = 4.
- 0062**
ISPF has failed. The specified panel cannot be found. Return code = 12.
- 0065**
ISPF SETMSG has failed. Panel message has not been found or the syntax is invalid. Return code = 12.
- 0066**
ISPF SETMSG service has failed. A severe error has occurred in processing ISPF SETMSG service. Return code = 20.
- 0067**
ISPF log has failed. Log message is invalid or not found. Return code = 12.
- 0068**
ISPF log has failed. A severe error has occurred in ISPF log service. Return code = 20.
- 0071**
Unable to build the storage control table (SCT).
- 0074**
ISPF SELECT has failed. Truncation error in storing the ZCMD or ZSEL variable. Return code = 16.
- 0075**
ISPF SELECT has failed. Severe error. Return code = 20.
- 0076**
An invalid return code has been received from ISPF SELECT.
- 0077**
Invalid logging type has been passed to the ISMF log utility.
- 0086**
Convert utility: Source data length must be 4 bytes to convert a fullword fixed binary number representing bytes into the corresponding kilobyte representation.
- 0087**
Convert utility: The source data length must be 3 bytes to convert a fixed binary date into its character string representation.
- 0088**
Convert utility: The target data length must be at least 8 bytes to hold a converted date in its character string format, 'YY/MM/DD'.
- 0089**
Convert utility: Specified source index is invalid.
- 0090**
Convert utility: Specified target index is invalid.
- 0091**
Convert utility: Invalid year has been found while performing a date conversion.
- 0092**
Convert utility: Invalid month has been found while performing a date conversion.
- 0093**
Invalid day has been found while performing a date conversion.

0094

Convert utility: Source data length must be 8 bytes when converting a date in the character string format, 'YY/MM/DD', into a fixed packed decimal format, 'YYDDDS', where S is the sign bit.

0095

Convert utility: Target data length must be 3 bytes when converting a date in the character string format, 'YY/MM/DD', into a fixed packed decimal format, 'YYDDDS', where S is the sign bit.

0096

Convert utility: Source data length can be a maximum of 8 bytes when converting a character string to its fixed binary representation.

0097

Convert utility: Source data length must be 3 bytes when converting a date in packed decimal format to its character string representation of 'YY/MM/DD'.

0100

Convert utility: Unable to load the conversion translate table (CTTB).

0101

Invalid scroll amount, the valid format is: P (page); H (half); D (data); M (maximum); C (current); NNNN (a number from 1 to 9999).

0102

Command not found in the application command table.

0103

One or more commands not found in the application command table.

0105

Application command table pointer = 0.

0106

Command table anchor block pointer = 0.

0107

Array name pointer = 0.

0108

Format name pointer = 0.

0109

Command line pointer = 0.

0111

Command line length = 0.

0112

Command length is invalid.

0113

Command specified is in disable status in the application command table.

0114

Panel type is invalid. Function only supports a list panel.

0115

Command or line operator control blocks chain is not 0 before storage is freed.

0116

Application ID is invalid.

0117

No application table is being loaded.

0119

Termination type is invalid.

0120

Command table initialization has failed.

- 0121**
Command table entry count = 0.
- 0122**
An error has occurred while command processor tried to process the error routine.
- 0123**
CTABCLCB is not equal to CPPLCLCB.
- 0124**
Nonzero return code has been received from ISPF CONTROL service.
- 0126**
Invalid storage size is passed to the get-memory routine.
- 0127**
Invalid storage ID is passed to the get-memory routine.
- 0128**
Unexpected column name is found in DAB. DABs may be out of order.
- 0129**
Invalid cursor control block is chained from the command processor parameter list (CPPL).
- 0130**
Invoker's APID does not match current CTABAPID.
- 0131**
Invoker's APID has not been found in the CTAB chain.
- 0132**
Two CTABs have duplicate APIDs that match the invoker's APID.
- 0138**
Invalid system completion code is passed in the retry work area.
- 0139**
Incorrect number of parameters has been specified.
- 0140**
Member name specified is too long.
- 0141**
TBSAVE: Table is not open. Return code = 12.
- 0142**
TBSAVE: Table output library is not open. Return code = 16.
- 0143**
TBSAVE: Severe error. Return code = 20.
- 0144**
TBSAVE: Unexpected return code.
- 0150**
TBERASE: Table does not exist in output library. ISPF return code = 8.
- 0151**
TBERASE: Table in use, ENQUEUE has failed. ISPF return code = 12.
- 0152**
TBERASE: Table output library not allocated. ISPF return code = 16.
- 0153**
TBERASE: Unspecified severe error. ISPF return code = 20.
- 0154**
TBERASE: Unexpected return code. ISPF return code is not 0, 8, 12, 16, or 20.
- 0160**
ISMF commands: Required parameter is missing.
- 0161**
ISMF commands: Required parameter is too long.

- 0162**
ISMF commands: Required parameter has invalid characters.
- 0163**
ISMF commands: Too many parameters.
- 0174**
Master/Server: Server is unavailable.
- 0180**
File type of DGTTABL or DGTTLIB should be MACLIB.
- 0188**
Convert utility: The target data length must be at least 10 bytes to hold a converted date in its character string format 'YYYY/MM/DD'.
- 0189**
Convert utility: An invalid century and year in the format 'YYYY' is found when performing a date conversion.
- 0191**
Convert utility: An invalid century is found when performing a date conversion.
- 0197**
Convert utility: The source data length must be 4 bytes when converting a date in packed decimal format to its character string representation of 'YYYY/MM/DD'.
- 0200**
Line operator anchor block pointer = 0.
- 0201**
The list command and line operator conflict.
- 0202**
Line operator has not been found in the application line operator table.
- 0203**
Entry in the line operator field is greater than 10 characters.
- 0205**
Program has failed because of a failure in the invoked external routine. Refer to the failed external routine field.
- 0206**
Application line operator table pointer = 0.
- 0207**
Line operator processor work area pointer = 0.
- 0208**
Invalid return code from ISPF/PDF BROWSE service.
- 0209**
Duplicate table entry has been found while loading the table entries. Only one of the duplicates is loaded.
- 0212**
Line operator length is invalid.
- 0213**
Line operator field length = 0.
- 0214**
DGTFLLP3 rewrites the saved ERTB entry so that the error message can be displayed on screen.
- 0215**
TOTLINES field is zero.
- 0216**
Line operator does not have 'H' in column one but is asking DGTFLLP2 to check if it is a hide line operator.

0217

LPP2ALL and LPP2HI flags are off. No checking or verification is done by this program.

0218

Return code from DGTEFOFI is zero, but no value has been returned to the entry number field. An invalid combination of return code and value has been returned.

0219

Caller's ID is invalid. Valid IDs are 'CT', 'LP'.

0220

Invalid value in LOOPCNT.

0225

Invalid return code from ISPF/PDF EDIT service.

0226

ISPF CONTROL service has failed.

0227

Invalid value has been specified.

0230

No invocation is set for the hide line operator. LPPLHIDE is off.

0231

Hide amount is not numeric.

0232

LAI address (LPPLLAIA) is 0.

0233

Line operator does not have 'H' at column one and is not a hide line operator.

0234

No entry in the list area image to be processed. LPPLLAIT is less than 1.

0235

Hide range exceeds allowable maximum of 99999.

0236

LPPLENT is less than 1.

0237

Hide amount overlaps another pending line operator.

0238

HIDEAMT = 0.

0239

HIDEAMT is not in the allowable range of 1 to 99999.

0240

LPPLENT is greater than LPPLLAIT.

0242

LPPLROWA = 0.

0245

LPCB address = 0.

0246

Invalid value returned from format service. Valid values are 'Y' or 'N'. NAME of the format service can be found in the ISPF log.

0250

Invalid FIND parameter: ISMF user has not entered a column tag.

0251

Invalid command parameter: Only one parameter is accepted for this command.

0255

Value of the scroll variable is invalid.

- 0256**
Area name from LPCB is invalid.
- 0260**
FSSTATE: Invalid character in file ID. Return code = 20.
- 0261**
FSSTATE: Invalid file mode. Return code = 24.
- 0262**
FSSTATE: File not found. Return code = 28.
- 0263**
FSSTATE: Disk not accessed. Return code = 36.
- 0264**
FSSTATE: Error code other than 20, 24, 28, or 36 has been received.
- 0265**
FSREAD: File not found. Return code = 1.
- 0266**
FSREAD: Invalid buffer address. Return code = 2.
- 0267**
FSREAD: Permanent I/O error. Return code = 3.
- 0268**
FSREAD: Number of records to be read is less than or equal to zero (or greater than 32,768 for an 800-byte formatted disk). Return code = 5.
- 0269**
FSREAD: Invalid file format (only checked when the file is first opened for reading). Return code = 7.
- 0270**
FSREAD: Incorrect length. Buffer size is too small for item read. Return code = 8.
- 0271**
FSREAD: File open for output (for an 800-byte formatted disk). Return code = 9.
- 0272**
FSREAD: Number of records is greater than 1 for variable-length file. Return code = 11.
- 0273**
FSREAD: End of file, or record number is greater than the number of records in the file. Return code = 12.
- 0274**
FSREAD: Variable-length file has invalid displacement in active file table. Return code = 13.
- 0275**
FSREAD: Invalid character in file name. Return code = 14.
- 0276**
FSREAD: Invalid character in file type. Return code = 15.
- 0277**
FSREAD: An I/O error occurred on an FBA device. This is indicated by a nonzero condition code from a Diagnose X'20'. Error detected in module DMSDIO. Return code = 19.
- 0278**
FSREAD: Insufficient free storage available for file management control areas. Return code = 25.
- 0279**
FSREAD: Requested item number plus number of items exceeds file system capacity. Return code = 26.
- 0280**
FSREAD: Error code other than 1, 2, 3, 5, 7, 8, 9, 11, 12, 13, 14, 15, 19, 25, or 26 has been received.
- 0281**
FSCLOSE: File is not open or no read or write has been issued. Return code = 6.

0282

FSCLOSE: Error code other than 6 has been received.

0301

Format service anchor block (FSAB) does not exist. Pointer to FSAB in the global data repository block (GDRB) is 0.

0302

Format anchor block (FAB) is not found. No match of format name and array name exists in a FAB.

0303

Control block structure with the same format and array name already exists.

0304

Variables of list area (VLA) are invalid. VLA may be incomplete.

0305

Input parameter number of entries (ENTNUM) is invalid. Value is greater than the total number of entries in the LAI or is a negative number.

0306

Input parameter multiline (MULLINE) is invalid. Value of MULLINE is 2, but this is a single line entry.

0307

Input parameter number of entries in the input array (INPENT) is invalid. Number of entries specified in INPENT is not equal to the number of entries actually in the LAI.

0308

Data column descriptor (DCD) for corresponding data attribute block (DAB) does not exist.

0309

Input parameter area is invalid. Area name is not one of the following: input, object, data, or command.

0310

Input parameter offset is invalid. Offset is out of range.

0311

Data attribute block pointer (DABLPTR) does not point to a valid DABL.

0312

FDBLEFT or FDBRITE in the format data block (FDB) is invalid. Value is less than 0 or greater than the number of displayable data columns.

0316

ISPF/PDF BROWSE has failed. Zero length data. Return code = 12.

0317

ISPF/PDF BROWSE has failed. Return code = 14.

0318

Input parameter column name list (COLLIST) is invalid. At least one of the column names in the COLLIST has not been found.

0319

Column tag specified by the user is invalid.

0320

Column tag specified is not displayed.

0321

Entry identified by the ROWID is not displayed.

0322

ISPF/PDF BROWSE has failed. Return code = 16.

0323

Cursor is not placed in a field of the LIST panel.

0324

Cursor is placed in one of the fields: fixed area (entry statement, data column statement) or warning.

0326

Cursor is placed in a field of the LIST panel, but it is not one of the following: command line, entry statement, data column statement, warning, column headings, tags, or LAI.

0327

ISPF/PDF BROWSE has failed. Severe error, unable to continue. Return code = 20.

0328

ISPF/PDF EDIT has failed. Return code = 16.

0329

Value of FDBVSIZE (the vertical size of the list area of the current display with factor of split screen considered) in module DGTFFOF1 is invalid.

0331

Value of MAXL (length of variables NAME1 and NAME2) in module DGTFFOF1 is invalid.

0332

Incorrect number in the entry statement of the fixed area.

0334

Left parenthesis is missing in the tag text.

0335

Length of the output variable is not equal to the length of the data to be retrieved.

0336

Value of COLSIZE in module DGTFFOY1 is invalid.

0337

Length of the static load module text is invalid.

0338

Input parameter area option (AREAOP) is invalid.

0339

One of the control block lengths in the static load module is incorrect.

0340

Invalid return code.

0341

Input parameter ADDR FAB is invalid.

0342

Input parameter CRPLAI or CRPVAL is invalid.

0343

FSAB exists without any FAB. Format services have not been cleaned.

0344

Character scroll amount in DGTF FOM1 is invalid. Amount is neither PAGE nor MAX.

0345

ISPF/PDF EDIT has failed. Severe error, unable to continue. Return code = 20.

0347

Object name (second column of list) is blank.

0349

Invalid column heading length. The column heading length obtained from the message library is less than that stored in the static text, or greater than the length of the data area in the list panel.

0400

Sort parameter is invalid.

0401

Filter syntax is invalid. Only one set of filter criteria may be specified.

0404

No changes have been detected in the filter criteria. List is already filtered according to the specified filter criteria. No new filter has taken place.

- 0405**
Filter flags are not properly initialized. One of the following flags must be on: ADDFLAG, DELFLAG, or MODFLAG.
- 0406**
Invalid filter type has been specified by the user, and detected by the filter module. Valid filter types are: FT01–FT15.
- 0408**
The user has specified an invalid relational operator. Valid relational operators are: EQ, NE, GT, GE, LT, and LE.
- 0410**
Panel name from the ERTB is invalid.
- 0411**
Column name specified in the DAB is not recognized.
- 0412**
Invalid relational operator. Valid relational operators for the specified column are EQ and NE.
- 0413**
Invalid relational operator. The only valid relational operator for the specified column is EQ.
- 0420**
Invalid input parameter tags for module DGTFSO04.
- 0454**
Invalid operator has been entered by the user, but is not detected by the panel check routine.
- 0455**
Screen logical number obtained from the profile pool is either invalid (<0) or not in the defined range (1 to 8).
- 0456**
Requested column cannot be found in the file application static module.
- 0457**
Invalid scroll amount has been entered by the user.
- 0470**
Conflict between CPPLMAD and DGTEWORD. CPPLMAD indicates that there is a parameter, but the length of the parameter returned by DGTEWORD is not greater than zero.
- 0471**
Invalid pointer (GDRBIACB) to the first ISMF application control block (IACB).
- 0472**
An error exists in the chaining of IACBs.
- 0473**
A conflict exists in the IACB pointers.
- 0474**
The pointer (GDRBIACB) to the first IACB is 0.
- 0527**
Call to DELETE has been unsuccessful.
- 0528**
Array does not exist.
- 0529**
Invalid sort order: It must be A or D.
- 0530**
SELBFLG1 is not specified or is incorrectly specified. One bit must be on.
- 0531**
Caller's DAB does not match with any VDEFINE DABs.

- 0532**
Scan for the nth row has been unsuccessful. The last row found is returned.
- 0533**
Improper search direction. Direction default is to next.
- 0534**
DABL contains no DABs. Array cannot be created.
- 0535**
Get storage for ARVT/RWCB control block has failed.
- 0536**
SRVTARB1 or SRVTARN1, or both, in SRVT control block are not initialized.
- 0537**
Extension DAB name is not returned in the extension variable list by ISPF.
- 0538**
DABCLLEN is invalid.
- 0539**
Array already exists.
- 0541**
Condition value for an extension DAB is invalid.
- 0542**
Return code is invalid.
- 0581**
Convert utility: Address of the control data attribute block is 0.
- 0600**
NUCXLOAD unsuccessful. Requested module cannot be loaded.
- 0601**
No matching SCT entry has been found.
- 0604**
Unable to build load list block (LLBL) entry.
- 0605**
No matching LLBL entry has been found.
- 0607**
Delete common service: Use count for the common service routine is already zero.
- 0608**
Convert utility: Truncated data. Target area specified is not large enough to contain the converted data. Data has been truncated.
- 0610**
Convert utility: Length of the source data must be from 1 to 4 bytes to convert fixed binary numbers.
- 0611**
Convert utility: Invalid source data length. Length of the data to be converted must be less than 0.
- 0612**
Convert utility: Target data length is invalid. Length of the target data must be less than 0.
- 0613**
Convert utility: Source data address = 0. Address of the data to be converted is 0.
- 0614**
Convert utility: Target address = 0. Address specified for the target address is 0.
- 0616**
Starting address is larger than ending address. Input parameters supplied to the word parsing routine (DGTEWORD) are invalid.
- 0617**
Log: Message not found. Return code = 12.

- 0618**
Log: Severe error. Return code = 20.
- 0619**
Log: Invalid return code.
- 0620**
Request has been made to log status information, but no additional message IDs are specified. At least one message ID must be specified.
- 0621**
Convert utility: Invalid conversion code.
- 0622**
Convert utility: Invalid justification code.
- 0624**
Invalid return code from ISPF VDELETE.
- 0625**
Invalid return code from ISPF VPUT.
- 0626**
Invalid return code from ISPF VGET.
- 0627**
Invalid return code from ISPF VDEFINE.
- 0628**
Invalid return code from ISPF SETMSG.
- 0629**
Invalid return code from ISPF GETMSG.
- 0630**
Invalid return code from ISPF DISPLAY.
- 0631**
ISPF DISPLAY: Terminated by END or RETURN. Return code = 8. User requested termination via END or RETURN command.
- 0632**
ISPF DISPLAY: Specified panel, message, or cursor field is not found. Return code = 12.
- 0633**
ISPF DISPLAY: Truncation or translation error in storing defined variables. Return code = 16.
- 0634**
ISPF DISPLAY: Severe error. Return code = 20.
- 0635**
ISPF GETMSG: Specified message has not been found. Return code = 12.
- 0636**
ISPF GETMSG: Severe error. Return code = 20.
- 0637**
ISPF SETMSG: Specified message has not been found. Return code = 12.
- 0638**
ISPF SETMSG: Severe error. Return code = 20.
- 0639**
ISPF VDEFINE: Variable is not found. Return code = 8.
- 0640**
ISPF VDEFINE: Data truncation has occurred. Return code = 16.
- 0641**
ISPF VDEFINE: Severe error. Return code = 20.
- 0642**
ISPF VGET: Variable is not found. Return code = 8.

- 0643**
ISPF VGET: Truncation or translation error has occurred during data movement. Return code = 16.
- 0644**
ISPF VGET: Severe error. Return code = 20.
- 0645**
ISPF VPUT: Variable is not found. Return code = 8.
- 0646**
ISPF VPUT: Truncation has occurred while copying variables to the application profile pool. Return code = 16.
- 0647**
ISPF VPUT: Severe error. Return code = 20.
- 0648**
ISPF VDELETE: At least one variable has not been found. Return code = 8.
- 0649**
ISPF VDELETE: Severe error. Return code = 20.
- 0650**
ISPF TBDELETE: For nonkeyed tables, the table is empty. The ISPF current row pointer remains at the top. For keyed tables, the row specified by the key variables does not exist. The ISPF current row pointer is set to top. ISPF return code = 8.
- 0651**
ISPF TBDELETE: Table is not open.
- 0652**
ISPF TBDELETE: Severe error.
- 0653**
ISPF TBDELETE: Invalid return code.
- 0654**
ISPF TBEND: Table is not open.
- 0655**
ISPF TBEND: Severe error.
- 0656**
ISPF TBEND: Invalid return code.
- 0657**
ISPF TBTOP: Table is not open.
- 0658**
ISPF TBTOP: Severe error.
- 0659**
ISPF TBTOP: Invalid return code.
- 0660**
ISPF TBVCLEAR: Table is not open.
- 0661**
ISPF TBVCLEAR: Severe error.
- 0662**
ISPF TBVCLEAR: Invalid return code.
- 0663**
ISPF TBADD: A row with the same key already exists. The ISPF current row pointer is set to the top (zero). ISPF return code = 8.
- 0664**
ISPF TBADD: Table is not open.
- 0665**
ISPF TBADD: Numeric convert error.

- 0666**
ISPF TBADD: Severe error.
- 0667**
ISPF TBADD: Invalid return code.
- 0668**
ISPF TBPUR: For nonkeyed tables, the ISPF current row pointer is at the top and remains at the top. For keyed tables, the key does not match that of the current row. The ISPF current row pointer is set to top. ISPF return code = 8.
- 0669**
ISPF TBPUR: Table is not open.
- 0670**
ISPF TBPUR: Numeric convert error.
- 0671**
ISPF TBPUR: Severe error.
- 0672**
ISPF TBPUR: Invalid return code.
- 0673**
ISPF TBGET: For nonkeyed tables, the ISPF current row pointer is at the top and remains at the top. For keyed tables, the row specified by the value in the key variables does not exist. The ISPF current row pointer is set to top.
- 0674**
ISPF TBGET: Table is not open.
- 0675**
ISPF TBGET: Insufficient space to return all extension variables names.
- 0676**
ISPF TBGET: Severe error.
- 0677**
ISPF TBGET: Invalid return code.
- 0678**
ISPF TBCREATE: Table already exists.
- 0679**
ISPF TBCREATE: Table in use, enqueue has failed.
- 0680**
ISPF VCPY: Variable not found. Return code = 8.
- 0681**
ISPF TBCREATE: Severe error.
- 0682**
ISPF TBCREATE: Invalid return code.
- 0683**
ISPF TBSORT: Table is not open.
- 0684**
ISPF TBSORT: Numeric convert error.
- 0685**
ISPF TBSORT: Severe error.
- 0686**
ISPF TBSORT: Invalid return code.
- 0687**
ISPF TBBOTTOM: Table is empty.
- 0688**
ISPF TBBOTTOM: Table is not open.

- 0689**
ISPF TBBOTTOM: Insufficient space provided to return all extension variables.
- 0690**
ISPF TBBOTTOM: Severe error.
- 0691**
ISPF TBBOTTOM: Invalid return code.
- 0692**
ISPF TBSARG: All column variables are null and the name-list parameter has not been specified.
- 0693**
ISPF TBSARG: Table is not open.
- 0694**
ISPF TBSARG: Severe error.
- 0695**
ISPF TBSARG: Invalid return code.
- 0696**
ISPF TBSKIP: TBSKIP has failed because the current row pointer (CRP) cannot go beyond the number of rows in the table.
- 0697**
ISPF TBSKIP: Table is not open.
- 0698**
ISPF TBSKIP: Insufficient space provided to return all extension variables.
- 0699**
ISPF TBSKIP: Severe error.
- 0700**
ISPF TBSKIP: Return code is invalid.
- 0701**
ISPF TBSCAN: Row does not exist. No match is found.
- 0702**
ISPF TBSCAN: Table is not open.
- 0703**
ISPF TBSCAN: Insufficient space provided to return all extension variables.
- 0704**
ISPF TBSCAN: Severe error.
- 0705**
ISPF TBSCAN: Return code is invalid.
- 0706**
ISPF TBADD: GETMAIN error. Return code = 20.
- 0707**
Caller is not authorized to invoke this module.
- 0708**
ISPF VCOPY: Truncation has occurred. Return code = 16.
- 0709**
ISPF VCOPY: Severe error. Return code = 20.
- 0726**
ISPF TBQUERY: Table is not open. Return code = 12.
- 0727**
ISPF TBQUERY: Insufficient space provided. Return code = 16.
- 0728**
ISPF TBQUERY: Severe error. Return code = 20.

0729

ISPF TBQUERY: Unexpected return code.

0730

ISPF VCPY: Invalid return code.

1000

Invalid return code. An invalid (unexpected) return code has been received from the called function. The possible reasons are:

- logic error in called function
- mismatch between calling and called function (for example, called function may have added a new return code which the caller is not aware of).

1002

Invalid visual ID. The visual ID of the control block is invalid. The possible reasons are:

- the pointer to the control block contains an invalid address
- the visual ID of the control block is incorrectly initialized.

1026

VOLSER verification: An invalid character has been found.

1027

VOLSER verification: Too many asterisks have been found. Only one asterisk may be specified in a partial specification.

1058

Print has failed.

1075

VOLSER verification: VOLSER is blank.

1076

VOLSER verification: VOLSER is single asterisk.

1077

No column name match has been found in static column load module. See feedback in the ERTB problem description area for column name requested and static column load module name.

1079

Unexpected panel number has been encountered. See feedback in the ERTB problem description area field for the unexpected panel number.

1093

Unexpected GETMAIN request flag has been received. See feedback in the ERTB problem description area for the unexpected request flag value.

1104

ISPF TBOPEN: Table does not exist.

1105

ISPF TBOPEN: Enqueue has failed; table in use.

1106

ISPF TBOPEN: Table input library is not allocated.

1107

ISPF TBOPEN: Severe error.

1108

ISPF TBOPEN: Invalid return code.

1109

ISPF TBCLOSE: Table is not open. Return code = 12.

1110

ISPF TBCLOSE: Table output library is not open. Return code = 16.

- 1111**
ISPF TBCLOSE: Severe error. Return code = 20.
- 1112**
ISPF TBCLOSE: Unexpected return code.
- 1113**
Last use mode is undefined for hide.
- 1115**
Nonzero return code from DGTCDT01.
- 1230**
Invalid criteria name specified in IACL. See feedback for the invalid name.
- 1231**
Device type verification: Invalid character is found.
- 1232**
Device type verification: Device type is blank.
- 1233**
Device type verification: More than one asterisk has been specified in a partial specification.
- 1234**
Device type verification: Partial specification has not been requested, but an asterisk is found in the input device name.
- 1235**
Device type verification: Partial specification has been requested, but no asterisk is specified.
- 1236**
Device type verification: Device type is a single asterisk.
- 1237**
Device type verification: Device type is not a supported generic name.
- 1250**
Save command error: Invalid list name. List name cannot begin with 'ISR', 'ISP', or 'DGT' and it cannot have single or double quotes.
- 1254**
ALTER error: Nonzero return code from ALTER. See feedback in the ERTB problem description area for return code and reason code.
- 1270**
Repeat line operator is used without the previous line operator.
- 1271**
Error has occurred during processing of user line operator or command.
- 1272**
ISPF VREPLACE: Truncation occurred during data movement.
- 1273**
ISPF VREPLACE: Severe error.
- 1274**
ISPF VREPLACE: Invalid return code.
- 1275**
Error has occurred during creation of user command anchor block.
- 1276**
Invalid application ID for this service.
- 1277**
User command has failed.
- 1278**
Error has occurred during processing of a list.

- 1279**
Error has occurred during initialization of user command.
- 1280**
Invalid return code for user command initialization.
- 1281**
User command control variable cannot be retrieved from a shared variable pool.
- 1283**
Invalid area has been specified. Valid values are ALL, DATA, or BOTH.
- 1284**
Invalid value has been specified for FROM. Valid values are LAI or SLAI.
- 1290**
The CRP cannot position to top of array.
- 1315**
Cannot process command against an empty list.
- 1316**
DGTEGMEM (get storage): Invalid return code.
- 1317**
DGTEFMEM (free storage): Invalid return code.
- 1318**
DGTESERV (service acquisition): Invalid return code.
- 1319**
DGTEARPS (array positioning): Invalid return code.
- 1320**
DGTEARUP (array update): Invalid return code.
- 1321**
Unexpected return code from internal routines. See previous ERTB entries for details.
- 1330**
DGTEFOGV (get data from VLA): Get VLA minidisk name field error. Name field is null or tagged as in error or undefined.
- 1331**
DGTEFOGV (get data from VLA): Get VLA minidisk address field error. Address field is null or tagged as in error or undefined.
- 1332**
DGTEFOGV (get data from VLA): Get VLA minidisk size field error. Size field is null or tagged as in error or undefined.
- 1333**
DGTESERV (Service Acquisition): Return code = 0, but no request ID has been delivered in the MDML as expected.
- 1334**
Operation has been previously requested.
- 1335**
Operation associated with specified request ID has already started.
- 1336**
Operation associated with specified request ID has already completed.
- 1337**
Specified request ID cannot be found.
- 1338**
Operation associated with specified request cannot complete because of a system failure.
- 1339**
An unexpected error has been detected by the master/server machine.

1340

An unexpected error has been detected by the master machine.

1555

Storage not freed by application has been freed by main dialog. This is an informational message.

2032

Cannot attempt connect_path. Declare_buffer has previously failed. Cannot try connect.

2033

Invalid SAPL entry pointer.

2034

No communication block is specified. Function handler cannot find CPCB address.

2035

A conversion error occurred acquiring data. Service acquisition has received a bad return from the conversion utility.

2036

Invalid entry count in SAPL. Service acquisition list has invalid entry count.

2037

Invalid SARB type. Service acquisition received invalid request block type.

2042

Sever path request has been processed. CPCB has been removed from storage.

2043

Service acquisition request ID mismatch. The ID of the response sent to the master does not match what is returned by the master machine.

2044

Service acquisition timeout occurred. No response has been received from the master machine within preset amount of time.

2045

FSSTATE failed, DGTVCNTL DATA VMSYS:DFSMS.CONTROL file not found. Default master user ID is used.

2046

I/O error (open or read) for DGTVCNTL DATA VMSYS:DFSMS.CONTROL. Use of default master user ID is attempted.

2047

FCBNUM does not equal the actual number of FCB entries. The list of saved lists may be incomplete.

2050

I/O error on the configuration file.

2051

The directory for a library has not been found, therefore the library's entries cannot be acquired and the list of saved lists may be incomplete.

2052

Error in the parameter list passed to DGTFJL33. A library name has not been specified or is invalid. The library's entries cannot be acquired and the list of saved lists may be incomplete.

2053

Error occurred while attempting to get an additional GLTN block to add to the GLTN chain. Some of the library's entries cannot be acquired and the list of saved lists may be incomplete.

2054

Error occurred during SVC 202 for 'RDBUF' command. Some or all entries of a library may not have been acquired and the list of saved lists may be incomplete.

2055

DGTFJL33 (get data for GTLN): An attempt has been made to read above the top of the storage.

2056

A library is neither a 'LIB' file nor a BSEP maclib. Some or all of the library's entries may not have been acquired and the list of saved lists may be incomplete.

2057

DGTFJL31 (list application prefix): Invalid return code from the get data for GTLN module (DGTFJL33).

2058

TBOPEN failed for a table. The list of saved lists may be incomplete.

2060

DGTEARST (row count): Invalid return code.

2061

DGTEARFN (find row): Invalid return code.

2062

Displayable row count does not match number of rows retrieved from array.

2063

FOLOAD: Cannot update screen from array.

2064

No displayable entries in list.

2065

No valid request IDs in list.

2066

No request ID for this item.

2067

User is not authorized to perform function.

2068

User is not authorized to perform this function for another user.

3000

ESTAE macro invocation has failed with return code = 4.

3001

ESTAE macro invocation has failed with return code = 8.

3002

ESTAE macro invocation has failed with return code = 12.

3003

ESTAE macro invocation has failed with return code = 16.

3004

ESTAE macro invocation has failed with return code = 20.

3005

ESTAE macro invocation has failed with return code = 24.

3006

ESTAE macro invocation has failed with an unknown return code.

3007

ISPLINK (CONTROL) service has failed with return code = 20.

3008

An ABEND has occurred. The retry routine has completed.

3009

ISPLINK (DISPLAY) has issued return code = 0; return code = 8 was expected.

3010

ISPLINK (DISPLAY) has issued return code = 12; return code = 8 was expected.

3011

ISPLINK (DISPLAY) issued return code = 16; return code = 8 was expected.

- 3012**
ISPLINK (DISPLAY) issued return code = 20; return code = 8 was expected.
- 3019**
FREEMAIN has issued return code = 12; page table is paged out.
- 3023**
DGTCLGCS has failed with return code = 12.
- 3025**
One or more calls to ISPLINK (VDEFINE) have failed.
- 3026**
One or more calls to ISPLINK (VDELETE) have failed.
- 3032**
Termination has not completed.
- 3033**
Initialization has failed.
- 3034**
An unexpected return code has been received and is logged by the called module.
- 3035**
ESTAE is not successful, but processing has continued.
- 3036**
VDEFINE has failed.
- 3038**
Load command processor modules have failed.
- 3040**
ISMF command table processor initialization has failed.
- 3041**
VPUT has failed.
- 3042**
VDELETE has failed.
- 3044**
Unable to release command processor control blocks.
- 3045**
ESTAE termination has abended.
- 3049**
Application selection has failed.
- 3051**
Prolog failure in DGTFCTSE.
- 3052**
Load ISMF command table has failed.
- 3057**
Invalid option has not been detected by DGTFASV.
- 3068**
VGET has failed.
- 3071**
Unable to process command.
- 3072**
Invalid command has not been detected by DGTFCTCK.
- 3074**
Command processor, DGTFCTPR, has failed.
- 3076**
Control service has failed with a nonzero return code.

- 3080**
Empty file. PDF BROWSE issued return code = 12.
- 3081**
Specified member has not been found; PDF BROWSE issued return code = 14.
- 3082**
No members in library. PDF BROWSE issued return code = 16.
- 3083**
Severe error has been encountered. PDF BROWSE issued return code = 20.
- 3084**
Invalid return code from PDF BROWSE.
- 3085**
Nonzero return code from ISPF control function.
- 3103**
File not found.
- 3110**
DGTCLD01 has issued return code = 12.
- 3111**
DGTCLD01 has issued an unknown return code.
- 3114**
DGTCDT01 has issued return code = 12.
- 3115**
DGTCDT01 has issued an unknown return code.
- 3117**
Error has occurred in DFSMS/VM configuration services.
- 3119**
Configuration file release has failed.
- 3127**
Invalid option has not been detected by DGTFFLSV.
- 3130**
Edit has failed.
- 3131**
Translate has failed.
- 3135**
ISPLINK (DISPLAY) has issued an unknown return code; return code = 8 was expected.
- 3136**
ISPLINK (CONTROL) failed with an unknown return code.
- 3138**
Translator prepare input has failed.
- 3140**
Translator has failed.
- 3143**
Unable to allocate.
- 3148**
Browse has failed.
- 3154**
Count parameter out of range.
- 3172**
Construct saved with a return code of 0.
- 3183**
Invalid option not detected by panel verification.

- 3218**
Unable to convert to displayable form.
- 3234**
File not found.
- 3235**
Caller is not authorized to access the file.
- 3236**
Read access requested and file is empty.
- 3237**
Element not found.
- 3239**
ACS routine not translated because of user errors. The listing contains error messages.
- 3245**
Invalid units of allocation.
- 3246**
Function name not found in function table.
- 3252**
Release command processor modules have failed.
- 3254**
Prolog failure.
- 3255**
No IACB to release.
- 3256**
Nonzero return code from DGTCLD01.
- 3257**
DFSMS/VM indicates that a resource is not available.
- 3258**
DGTEGMEM has issued a nonzero return code.
- 3259**
An error has occurred in the ACS translator.
- 3260**
An error has occurred in the ACS executor.
- 3261**
The file has been previously updated.
- 3262**
DGTEFMEM has issued a nonzero return code.
- 3263**
DGTELDMD (LOAD) error.
- 3264**
DGTEDTMD (DELETE) error.
- 3265**
Element already exists.
- 3266**
DGTEFMEM error and DGTEDTMD error.
- 3267**
Invalid value of APPFMODE from the ISMF profile variable table variables (DGTMPVTV).
- 3268**
Configuration file is not formatted.
- 3269**
Invalid access mode parameter for CSI.

- 3270**
Invalid function code parameter for CSI.
- 3271**
A configuration file is accessed with the access token.
- 3272**
No configuration file is accessed with the access token.
- 3273**
ABEND logging has failed with an unexpected return code.
- 3274**
The file is not a source configuration file.
- 3275**
Invalid element type.
- 3276**
Blank construct name.
- 3277**
Retrieve information from VLA has failed.
- 3278**
The file is not a configuration file.
- 3279**
Cannot delete the configuration file base.
- 3280**
List services is unable to find a match on the DAB column name.
- 3281**
List services is unable to add a row of data to the array.
- 3282**
List services is unable to release the ISMF reserved storage.
- 3283**
Array services modules cannot be loaded.
- 3284**
Format services modules cannot be loaded.
- 3285**
Duplicate APID is found.
- 3286**
DGTEGMEM (GET STORAGE) error.
- 3287**
DGTEFMEM (FREE STORAGE) error.
- 3288**
Initialize format services has failed.
- 3289**
Move display window has failed.
- 3290**
Initialize line operator executor has failed.
- 3291**
Unable to release line operator executor control block.
- 3292**
Creation of the list area image (LAI) has failed.
- 3293**
A status check of the array has failed.
- 3294**
A sort of the array has failed.

- 3295**
Obtaining of the cursor position has failed.
- 3296**
Positioning of the cursor has failed.
- 3297**
Updating of the fixed area has failed.
- 3298**
Highlighting of the error entry has failed.
- 3299**
Display of a panel has failed.
- 3300**
Unable to process input.
- 3301**
The line operator and list command conflict.
- 3302**
DGTFAC (CSI access configuration file) issued return code = 12.
- 3303**
DGTCFGT (CSI GET ELEMENT) issued return code = 12.
- 3305**
Invalid SG type detected by convert.
- 3306**
No matching elements have been found.
- 3307**
Names are too long, elements are deleted.
- 3308**
Common filter service error.
- 3309**
List tailoring, DGTFCLI, has failed.
- 3310**
Validation indicates errors.
- 3311**
Not authorized to activate.
- 3312**
SSI has not scheduled an activation.
- 3313**
File is in use.
- 3315**
List services anchor block does not exist.
- 3316**
DFSMS/VM is not operational.
- 3317**
Screen logical number is not within the bounds of the array.
- 3318**
DFSMS/VM is not active; there is no active configuration.
- 3319**
Translation of column tags into column names has failed.
- 3320**
Maximum number of valid commands allowed on panel (20) has been exceeded.
- 3321**
Invalid value encountered when converting data from displayable format to internal format.

- 3322**
Either the GDRBLSAB or GDRBLSVT is invalid, or both are invalid.
- 3328**
Read of test directory has failed.
- 3329**
Unrecognizable string in test file.
- 3336**
Listing writer: Invalid file type.
- 3342**
Listing writer: Invalid pointer to data.
- 3343**
Listing writer: Invalid title has been specified.
- 3344**
Listing writer: Load of DGTFIORT has failed.
- 3350**
Write of test file has failed.
- 3351**
Unknown ACS routine type.
- 3352**
Listing writer: Invalid function has been specified.
- 3354**
LRECL for listing file is invalid.
- 3360**
Listing writer has failed.
- 3361**
Cannot change active configuration.
- 3362**
Caller is not authorized to invoke this function.
- 3364**
ACS test library cannot have a LRECL of less than 60.
- 3365**
Not authorized to open the listing file for output.
- 3366**
Unable to process the line operator.
- 3368**
Out of space for the file.
- 3501**
The specified file or directory does not exist or you are not authorized for it.
- 3502**
File mode is not an accessed SFS directory.
- 3503**
File mode is an accessed minidisk.
- 3505**
The specified directory is not found or the user is not authorized to access the directory.
- 3506**
Listing file cannot be found; therefore, it is not deleted.
- 3507**
The record format of the listing file is invalid.
- 3508**
Configuration file has been damaged and cannot be used.

- 3509**
The record length of the ACS source file is invalid.
- 3510**
The record length of the ACS test file is invalid.
- 3511**
No ACS module exit routine has been found.
- 3512**
ACS module exit routine cannot be loaded.
- 3513**
No ACS REXX exit routine found.
- 3514**
ACS REXX exit routine cannot be loaded.
- 3515**
Source configuration file not found. Activation is not scheduled.
- 3516**
Source configuration file is invalid. Activation is not scheduled.
- 3517**
DFSMS/VM communication error.
- 3518**
Error occurred while opening the translator listing file.
- 3519**
Error occurred while closing the translator listing file.
- 3520**
Test Activate has returned an unexpected combination of return code and module or REXX exit status.
- 3522**
Unidentified errors found with ACS module exit routine.
- 3525**
Unidentified errors found with ACS REXX exit routine.
- 3527**
Communication with the DFSMS master cannot be established.
- 3528**
User not authorized to issue the command.
- 3529**
DFSMS master is not accepting the command.
- 3530**
Resubmit the status command to the DFSMS master.
- 3531**
Request identifier not found for the command.
- 3532**
Request identifier has already been discarded.
- 3533**
No request identifiers queued for query.
- 3534**
DFSMS/VM internal error.
- 3535**
The command information passed to the DFSMS master is invalid. Processing of the status command failed.
- 3536**
The operation code passed to the DFSMS master is invalid. Processing of the status command has failed.

- 3537**
Master machine is not available.
- 3538**
At least one validation message is missing.
- 3539**
An error occurred while opening the source configuration file.
- 3540**
An error occurred in reading the source configuration file.
- 3541**
An error occurred in writing the source configuration file.
- 3542**
An unexpected reason code returned from DFSMS/VM.
- 3544**
All selected data has been returned by DMSGETDI.
- 3545**
The DFSMS master machine has passed back an invalid control block (bad eye catcher or bad version or zero length).
- 3546**
The entry is not a directory.
- 3547**
A query function is currently active. QUERY command cannot be issued again.
- 3548**
XEDIT failed with a nonzero return code.
- 3549**
Neither PDF BROWSE nor CUF BROWSE is available.
- 3550**
CUF BROWSE failed with a nonzero return code.
- 3551**
PDF option is not valid when PDF is not available.
- 3552**
DFSMS/VM master is not authorized to access the file pool where the source configuration file resides.
- 3553**
Source configuration file at version of DFSMS/VM.
- 3554**
Insufficient space in secondary storage.
- 3555**
Insufficient space in primary storage.
- 3556**
Secondary storage value out of range.
- 3557**
No value found for secondary storage.
- 3558**
The operation attempted is valid only for BASE and ALIAS files. The operation failed because the file list entry is not a BASE or ALIAS file.
- 3559**
The operation attempted is valid only for BASE and ALIAS files or directories. The operation failed because the file list entry is not a BASE or ALIAS file or a directory.

DFSMS/VM Return Codes

This section contains return codes issued by DFSMS commands, as well as CP completion codes, which may appear in DFSMS/VM messages.

For information on specific library hardware error and other DFSMS/VM reason codes, see the "Return Codes and Reason Codes for CSL Routines" appendix in [z/VM: DFSMS/VM Removable Media Services](#).

DFSMS Command Return Codes

The following table lists DFSMS command return codes and their meanings and can be used to interpret messages issued by the DFSMS commands.

DFSMS Command Processor Return Codes

Return Code	Meaning
0	Successful processing.
4	SKIP option has been ignored during DFSMS COPY. A problem has been detected with the minidisk during DFSMS CHECK.
24	Syntax error occurred.
28	File or directory not found or already exists, or insufficient authority.
32	File not in expected format, or file does not contain the expected information, or an attempt was made to execute a LOADMOD command while in CMS subset mode.
36	File mode not accessed. Problem with source or target minidisk during DFSMS COPY.
40	No default file pool assigned.
41	Insufficient storage.
55	Communications error.
70	File sharing conflict. This includes locking conflicts and failures caused by uncommitted changes.
74	Requested function not available for minidisks.
76	Authorization error.
88	Block size invalid for device during DFSMS COPY.
99	Required system resource not available (the CSL library is not installed, or server is not available).
100	I/O error has occurred during DFSMS COPY. Device error has occurred during DFSMS CHECK.
104	Functional error for which the system is responsible. Insufficient storage for DFSMS COPY or DFSMS CHECK.
200	Allocation error has occurred for DFSMS CHECK.
201	Allocation error has occurred for DFSMS CHECK.
256	Unexpected error for which the system is responsible. The output minidisk not large enough for DFSMS COPY.

Table 3. DFSMS Command Processor Return Codes (continued)

Return Code	Meaning
300	Internal logic error has occurred during DFSMS COPY.
301	Internal logic error has occurred during DFSMS COPY.
302	Internal logic error has occurred during DFSMS COPY.
303	Internal logic error has occurred during DFSMS COPY.
304	Internal logic error has occurred during DFSMS COPY.

DFSMS/VM Reason Codes

For information on specific library hardware error and other DFSMS/VM reason codes, see the "Return Codes and Reason Codes for CSL Routines" appendix in *z/VM: DFSMS/VM Removable Media Services*.

CP Completion Status

Table 4 on page 209 lists the CP completion status values provided to aid in interpreting the master virtual machine messages, which display completion status.

Table 4. CP Completion Status

IUCV Error Conditions	Meaning
X'800000'	Reply too long
X'400000'	Send protection exception
X'200000'	Send address exception
X'100000'	Answer protection exception
X'080000'	Answer address exception
X'040000'	Message rejected
X'020000'	Parmdata reply sent
X'010000'	reserved
X'008000'	Receive protection except
X'004000'	Receive address exception
X'002000'	Reply protection exception
X'001000'	Reply address exception
X'000800'	Path was severed
X'000400'	Buffer list error
X'000200'	reserved
X'000100'	reserved

Notices

This information was developed for products and services offered in the US. This material might be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information may contain examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information may contain sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Programming Interface Information

This manual documents information NOT intended to be used as Programming Interfaces of DFSMS/VM.

Trademarks

IBM, the IBM logo, and ibm.com[®] are trademarks or registered trademarks of International Business Machines Corp., in the United States and/or other countries. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on [IBM Copyright and trademark information](http://www.ibm.com/legal/copytrade) (<https://www.ibm.com/legal/copytrade>).

The registered trademark Linux[®] is used pursuant to a sublicense from the Linux Foundation, the exclusive licensee of Linus Torvalds, owner of the mark on a worldwide basis.

Adobe, Acrobat, PostScript and all Adobe-based trademarks are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, other countries, or both.

Other company, product, and service names may be trademarks or service marks of others.

Terms and Conditions for Product Documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the IBM website.

Personal Use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

Commercial Use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

IBM Online Privacy Statement

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see:

- The section entitled **IBM Websites** at [IBM Privacy Statement](https://www.ibm.com/privacy) (<https://www.ibm.com/privacy>)
- [Cookies and Similar Technologies](https://www.ibm.com/privacy#Cookies_and_Similar_Technologies) (https://www.ibm.com/privacy#Cookies_and_Similar_Technologies)

Bibliography

This topic lists the publications in the z/VM library. For abstracts of the z/VM publications, see [z/VM: General Information](#).

Where to Get z/VM Information

The current z/VM product documentation is available in [IBM Documentation - z/VM \(https://www.ibm.com/docs/en/zvm\)](https://www.ibm.com/docs/en/zvm).

z/VM Base Library

Overview

- [z/VM: License Information](#), GI13-4377
- [z/VM: General Information](#), GC24-6286

Installation, Migration, and Service

- [z/VM: Installation Guide](#), GC24-6292
- [z/VM: Migration Guide](#), GC24-6294
- [z/VM: Service Guide](#), GC24-6325
- [z/VM: VMSES/E Introduction and Reference](#), GC24-6336

Planning and Administration

- [z/VM: CMS File Pool Planning, Administration, and Operation](#), SC24-6261
- [z/VM: CMS Planning and Administration](#), SC24-6264
- [z/VM: Connectivity](#), SC24-6267
- [z/VM: CP Planning and Administration](#), SC24-6271
- [z/VM: Getting Started with Linux on IBM Z](#), SC24-6287
- [z/VM: Group Control System](#), SC24-6289
- [z/VM: I/O Configuration](#), SC24-6291
- [z/VM: Running Guest Operating Systems](#), SC24-6321
- [z/VM: Saved Segments Planning and Administration](#), SC24-6322
- [z/VM: Secure Configuration Guide](#), SC24-6323

Customization and Tuning

- [z/VM: CP Exit Customization](#), SC24-6269
- [z/VM: Performance](#), SC24-6301

Operation and Use

- [z/VM: CMS Commands and Utilities Reference](#), SC24-6260
- [z/VM: CMS Primer](#), SC24-6265
- [z/VM: CMS User's Guide](#), SC24-6266
- [z/VM: CP Commands and Utilities Reference](#), SC24-6268

- [z/VM: System Operation](#), SC24-6326
- [z/VM: Virtual Machine Operation](#), SC24-6334
- [z/VM: XEDIT Commands and Macros Reference](#), SC24-6337
- [z/VM: XEDIT User's Guide](#), SC24-6338

Application Programming

- [z/VM: CMS Application Development Guide](#), SC24-6256
- [z/VM: CMS Application Development Guide for Assembler](#), SC24-6257
- [z/VM: CMS Application Multitasking](#), SC24-6258
- [z/VM: CMS Callable Services Reference](#), SC24-6259
- [z/VM: CMS Macros and Functions Reference](#), SC24-6262
- [z/VM: CMS Pipelines User's Guide and Reference](#), SC24-6252
- [z/VM: CP Programming Services](#), SC24-6272
- [z/VM: CPI Communications User's Guide](#), SC24-6273
- [z/VM: ESA/XC Principles of Operation](#), SC24-6285
- [z/VM: Language Environment User's Guide](#), SC24-6293
- [z/VM: OpenExtensions Advanced Application Programming Tools](#), SC24-6295
- [z/VM: OpenExtensions Callable Services Reference](#), SC24-6296
- [z/VM: OpenExtensions Commands Reference](#), SC24-6297
- [z/VM: OpenExtensions POSIX Conformance Document](#), GC24-6298
- [z/VM: OpenExtensions User's Guide](#), SC24-6299
- [z/VM: Program Management Binder for CMS](#), SC24-6304
- [z/VM: Reusable Server Kernel Programmer's Guide and Reference](#), SC24-6313
- [z/VM: REXX/VM Reference](#), SC24-6314
- [z/VM: REXX/VM User's Guide](#), SC24-6315
- [z/VM: Systems Management Application Programming](#), SC24-6327
- [z/VM: z/Architecture Extended Configuration \(z/XC\) Principles of Operation](#), SC27-4940

Diagnosis

- [z/VM: CMS and REXX/VM Messages and Codes](#), GC24-6255
- [z/VM: CP Messages and Codes](#), GC24-6270
- [z/VM: Diagnosis Guide](#), GC24-6280
- [z/VM: Dump Viewing Facility](#), GC24-6284
- [z/VM: Other Components Messages and Codes](#), GC24-6300
- [z/VM: VM Dump Tool](#), GC24-6335

z/VM Facilities and Features

Data Facility Storage Management Subsystem for z/VM

- [z/VM: DFSMS/VM Customization](#), SC24-6274
- [z/VM: DFSMS/VM Diagnosis Guide](#), GC24-6275
- [z/VM: DFSMS/VM Messages and Codes](#), GC24-6276
- [z/VM: DFSMS/VM Planning Guide](#), SC24-6277

- *z/VM: DFSMS/VM Removable Media Services*, SC24-6278
- *z/VM: DFSMS/VM Storage Administration*, SC24-6279

Directory Maintenance Facility for z/VM

- *z/VM: Directory Maintenance Facility Commands Reference*, SC24-6281
- *z/VM: Directory Maintenance Facility Messages*, GC24-6282
- *z/VM: Directory Maintenance Facility Tailoring and Administration Guide*, SC24-6283

Open Systems Adapter

- *Open Systems Adapter/Support Facility on the Hardware Management Console* (https://www.ibm.com/docs/en/SSLTBW_2.3.0/pdf/SC14-7580-02.pdf), SC14-7580
- *Open Systems Adapter-Express ICC 3215 Support* (<https://www.ibm.com/docs/en/zos/2.3.0?topic=osa-icc-3215-support>), SA23-2247
- *Open Systems Adapter Integrated Console Controller User's Guide* (https://www.ibm.com/docs/en/SSLTBW_2.3.0/pdf/SC27-9003-02.pdf), SC27-9003
- *Open Systems Adapter-Express Customer's Guide and Reference* (https://www.ibm.com/docs/en/SSLTBW_2.3.0/pdf/iaa2z1f0.pdf), SA22-7935

Performance Toolkit for z/VM

- *z/VM: Performance Toolkit Guide*, SC24-6302
- *z/VM: Performance Toolkit Reference*, SC24-6303

The following publications contain sections that provide information about z/VM Performance Data Pump, which is licensed with Performance Toolkit for z/VM.

- *z/VM: Performance*, SC24-6301. See *z/VM Performance Data Pump*.
- *z/VM: Other Components Messages and Codes*, GC24-6300. See *Data Pump Messages*.

RACF® Security Server for z/VM

- *z/VM: RACF Security Server Auditor's Guide*, SC24-6305
- *z/VM: RACF Security Server Command Language Reference*, SC24-6306
- *z/VM: RACF Security Server Diagnosis Guide*, GC24-6307
- *z/VM: RACF Security Server General User's Guide*, SC24-6308
- *z/VM: RACF Security Server Macros and Interfaces*, SC24-6309
- *z/VM: RACF Security Server Messages and Codes*, GC24-6310
- *z/VM: RACF Security Server Security Administrator's Guide*, SC24-6311
- *z/VM: RACF Security Server System Programmer's Guide*, SC24-6312
- *z/VM: Security Server RACROUTE Macro Reference*, SC24-6324

Remote Spooling Communications Subsystem Networking for z/VM

- *z/VM: RSCS Networking Diagnosis*, GC24-6316
- *z/VM: RSCS Networking Exit Customization*, SC24-6317
- *z/VM: RSCS Networking Messages and Codes*, GC24-6318
- *z/VM: RSCS Networking Operation and Use*, SC24-6319
- *z/VM: RSCS Networking Planning and Configuration*, SC24-6320

TCP/IP for z/VM

- *z/VM: TCP/IP Diagnosis Guide*, GC24-6328
- *z/VM: TCP/IP LDAP Administration Guide*, SC24-6329
- *z/VM: TCP/IP Messages and Codes*, GC24-6330
- *z/VM: TCP/IP Planning and Customization*, SC24-6331
- *z/VM: TCP/IP Programmer's Reference*, SC24-6332
- *z/VM: TCP/IP User's Guide*, SC24-6333

Prerequisite Products

Device Support Facilities

- Device Support Facilities (ICKDSF): User's Guide and Reference (https://www.ibm.com/docs/en/SSLTBW_2.5.0/pdf/ickug00_v2r5.pdf), GC35-0033

Environmental Record Editing and Printing Program

- Environmental Record Editing and Printing Program (EREP): Reference (https://www.ibm.com/docs/en/SSLTBW_2.5.0/pdf/ifc2000_v2r5.pdf), GC35-0152
- Environmental Record Editing and Printing Program (EREP): User's Guide (https://www.ibm.com/docs/en/SSLTBW_2.5.0/pdf/ifc1000_v2r5.pdf), GC35-0151

Related Products

XL C++ for z/VM

- *XL C/C++ for z/VM: Runtime Library Reference*, SC09-7624
- *XL C/C++ for z/VM: User's Guide*, SC09-7625

z/OS

IBM Documentation - z/OS (<https://www.ibm.com/docs/en/zos>)



Product Number: 5741-A09

Printed in USA

GC24-6276-73

